



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Mobile Services Deployment Guide

ORS Configuration

12/14/2025

Contents

- 1 ORS Configuration
 - 1.1 Setting ORS Option
 - 1.2 Deploying DFM Files
 - 1.3 Next Steps

ORS Configuration


This page details the ORS configuration steps required before you can use your Genesys Mobile Services installation.

Setting ORS Option

Start

1. [Start Configuration Manager](#).
2. In Configuration Manager, select *Environment > Applications*.
3. Locate and open the Application object for your Orchestration Server. Note: This should be the same Application object you created a connection to when [configuring your Genesys Mobile Services Application object](#).
4. Select the *Options* tab.
5. Open the *orchestration* section.
6. Set the value of the option *parse-start-params* to *true*.
7. Click *OK* to save your changes.

End




Deploying DFM Files

Included with your installation are special configuration files, called DFM, which are required for Orchestration Server-based services. These files define Genesys Mobile Services-specific SCXML constructs that are required for the execution of SCXML applications used within Orchestration Server-based Services. For the Orchestration Server-based Services to function correctly, the following DFM files need to be configured in your Orchestration Server Application object:

- Storage
- Notification
- Callback
- Genesys Mobile-Based Services

The latest DFM definition files are included with the GMS installation. Details about deploying these DFM in your environment are provided below. After deploying these DFM, you can use either an actual device with the demo application or an HTTP client (such as RestClient) to send API requests to Orchestration Server-based services. Refer to the Genesys Mobile Services API Reference for syntax of the requests.

 **Note:** You must restart Orchestration Server after deploying DFM files for the changes to take effect.

Start

1. **Start Configuration Manager.**
2. In Configuration Manager, select *Environment > Applications*.
3. Locate and open the Application object for your Orchestration Server. Note: This should be the same Application object you created a connection to when **configuring your Genesys Mobile Services Application object**.
4. Select the *Options* tab.
5. Open the *dfm* section.
6. Create and configure one option for each DFM, using the option value to specify the file path. Details are provided in the table below.
7. Click *OK* to save your changes.
8. Restart Orchestration Server (ORS). ORS reads the DFM configuration on startup.

Important: At least one GMS node must be up and running in order for ORS to start, and to successfully read the DFM file. If there is only one GMS node in your deployment and it is not running, ORS will **not** start. In the case of multiple GMS's, point the DFM links to a load balancer.

End

List of DFM Options for Orchestration Server

Service	Option Name	Option Value
Storage	gsgStorage	http://<gms_host>:<gms_port>/genesys/dfm/storage.jsp
Notification	gsgNotification	http://<gms_host>:<gms_port>/genesys/dfm/notification.jsp
Genesys Mobile-Based Services	gsgBasedServices	http://<gms_host>:<gms_port>/genesys/dfm/services.jsp
Callback	gsgCallback	http://<gms_host>:<gms_port>/genesys/dfm/callback.jsp

Next Steps

Although the GMS installation is now complete, there are additional steps required before using Genesys Mobile Services.

- [Basic Configuration](#)
- [Configuring Chat Support](#)