



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

SIP Voicemail HA Deployment Guide

Creating Virtual IP control scripts (Linux)

12/12/2025

Creating Virtual IP control scripts (Linux)

Start

1. On the primary VM Server, create a shell file to enable the Virtual IP interface that is named SC_VIP_UP.SH, and enter the following commands into the file:

[+] Commands for SC_VIP_UP.SH

```
#!/bin/sh
# Set the path in which log files will be stored
Logpath=<Specify the path to log files>
# For example Logpath=/home/Logs
echo -e "\n-----Bringing VIP Up-----" >> $Logpath/Takeover_On.log
date >> $Logpath/Takeover_On.log
# Set the following parameter corresponding to your machine configuration
Interface=<Interface in which VIP should be added>
# For example Interface=eth0:1
Virtual_IP=<Virtual IP of the Machine>
# For example Virtual_IP=172.24.133.254
Gateway=<Gateway of the Machine>
# For example Gateway=10.1.1.1
ping_count=1
loop_count=20
# Looping up to 20 count or till VIP disabled in the HA pair
for (( i=1; i<=$loop_count;i++ ))
do
result=$(ping -c $ping_count $Virtual_IP | grep "bytes from")
if [ "$result" ]
then
echo "$i ping reply got from the HA pair" >> $Logpath/Takeover_On.log
sleep 1
else
echo "VIP disabled in the HA pair" >> $Logpath/Takeover_On.log
# Enabling the VIP once it is disabled in paired host
break
fi
done

/sbin/ifconfig $Interface $Virtual_IP up
# Update the ARP cache of the gateway
arping -s $Virtual_IP $Gateway -f
echo -e "\n-----VIP enabled in this machine-----" >> $Logpath/Takeover_On.log
date >> $Logpath/Takeover_On.log
exit
```

2. In the shell file, replace the variables indicated by angle brackets with appropriate values.
3. On both GSVM server host computers, create a shell file to disable the Virtual IP interface that is named SC_VIP_DOWN.SH, and enter the following commands into the file:

[+] Commands for SC_VIP_DOWN.SH

```
# Set the path in which log files will be stored
Logpath= <Specify the path to log files>
```

```
# For example Logpath=/home/Logs
echo -e "\n-----Bringing VIP down-----" >> $Logpath/Takeover_Off.log
date >> $Logpath/Takeover_Off.log
# Set the following parameter corresponding to your machine configuration
Interface=<Interface in which VIP should be added>
Virtual_IP=<Virtual IP of the Machine>
/sbin/ifconfig $Interface down
sleep 10
# Update arpcache of the local machine
ping -c 2 $Virtual_IP
echo -e "-----VIP disabled-----" >> $Logpath/Takeover_Off.log
```

4. In the shell file, replace the variables indicated by angle brackets with appropriate values.
5. Add the SC_VIP_DOWN script as a startup script by adding the script to the current run-level of the machine.
 - a. Copy SC_VIP_DOWN.SH to the /etc/init.d folder.
 - b. Create a symlink from your run-level directory to execute when a system starts to disable the Virtual IP. For example, if the run-level is 5, the creation of symlink is as follows:
"ln -s /etc/init.d/<scriptfile> /etc/rc.d/rc5.d/S50<scriptfile>"
The S50 tells the system to start the script when it starts.

End

Next Steps

 [Genesys Applications](#) OR  [Back to Task Table](#)