



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Performance Management Advisors Deployment Guide

Contact Center Advisor Mobile Edition

5/6/2025

Contact Center Advisor Mobile Edition

Contact Center Advisor—Mobile Edition (CCAdv—ME) installation is an option in the CCAdv/WA module installer. For installation instructions, see [Deploying CCAdv and WA](#).

Role-Based Access Control for Mobile Devices

It is important to define a basic set of permissions in Configuration Server, so that users can view objects and functionality in the Application interface. For example, users with permissions to the CCAdv module (and ME) and permissions to view the Performance Monitor cannot view anything if they do not have access to any of the metrics and/or business attributes. They can log in to the Advisor interface, but the real-time tab will not appear if they do not have permissions to use at least one metric.

Required Permissions

Users who have access to ME will need the following minimum permissions:

- permissions to at least one contact center and/or application
- permissions to one of the following objects:
 - reporting region
 - geographic region
 - operating unit
- permissions to at least one metric

Important

If a user does not have permissions to view any of the default metrics, the first metric that displays in the ME Metrics or Hierarchy list is the first metric in the Column Chooser Available metrics list to which the user does have access permissions.

Using object permissions, you can assign a user's access permission to certain objects. When you apply permissions to an object, they apply equally to all properties of the object—if a user has access permissions, they see the entire object.

CCAdv—ME loads metrics dynamically based on user permissions taken from the server cache. It loads the metrics through `/ca-ws/columns.do`, to ensure the metrics information is up-to-date. If

metrics permissions change after a user chooses to display that metric, it is displayed with no data. However, when a user reselects the metrics to display, the list is refreshed.

The following permissions are implemented in the CCAdv—ME MapResource:

- metrics
- operating units
- reporting regions
- geographical regions
- contact centers
- application groups

Relevant objects are loaded on-demand, based on the user access permissions granted for each object.

Mobile Edition Privileges

Compared to Contact Center Advisor, the Mobile Edition has limited functionality. Therefore, CCAdv—ME requires only a subset of functional privileges. The following table provides a comparison of CCAdv privileges with Mobile Edition privileges.

Privileges	In CCAdv	In ME
ContactCenterAdvisor.Dashboard.canView		✓
ContactCenterAdvisor.Dashboard.AgentGroupsPane.canView		
ContactCenterAdvisor.Dashboard.ColumnChooser.canView		✓
ContactCenterAdvisor.Dashboard.EnterpriseStats.canView		✓
ContactCenterAdvisor.Dashboard.PivotSelect.canView		
ContactCenterAdvisor.PerformanceMonitor.canView		✓
ContactCenterAdvisor.PerformanceMonitor.CallFlowPane.canView		✓
ContactCenterAdvisor.PerformanceMonitor.CurrentCapacity.canView		✓
ContactCenterAdvisor.ActionManagementReport.canView		
ContactCenterAdvisor.AlertManagement.canView		

[+] Dashboard Privilege

The Dashboard privilege (ContactCenterAdvisor.Dashboard.canView) controls access to the CCAdv dashboard. Users with this privilege can access the CCAdv dashboard, the CCAdv tab in the Advisors interface, and log in to CCAdv—ME.

Important

Users cannot log in to CCAdv—ME if they do not have the privilege to access the Dashboard.

[+] Column Chooser Privilege

The Column Chooser privilege (`ContactCenterAdvisor.Dashboard.ColumnChooser.canView`) determines which metrics the user can choose for display. Users with this privilege can choose which metrics to display on the dashboard, access the **Column Chooser** button on the dashboard, and access the **Metrics** tab in the Mobile application.

Important

Users will either see a disabled Metrics tab (iOS) or will not see the Metrics menu/button (Blackberry) if they do not have the privilege to access Column Chooser.

[+] Enterprise Stats Privilege

The Enterprise Stats privilege (`ContactCenterAdvisor.Dashboard.EnterpriseStats.canView`) controls the display of the Enterprise Stats row in the dashboard. Users with this privilege can see the Enterprise Performance row in the dashboard.

Important

Users will see N/A in the Enterprise Performance row in the dashboard, if they do not have the privilege to access Enterprise Stats.

[+] Performance Monitor Privilege

The Performance Monitor privilege (`ContactCenterAdvisor.PerformanceMonitor.canView`) determines who can view the Performance Monitor. Users with this privilege can access to the **Performance Monitor** button on the dashboard and the right-arrow button (which directs to the **Performance Monitor** view) on each row of stats.

Important

Users will not see any arrow buttons (iOS) or menu/buttons (Blackberry) if they do not have the privilege to access Performance Monitor.

[+] Call Flow Stats Privilege

The Call Flow Stats privilege (`ContactCenterAdvisor.PerformanceMonitor.CallFlowPane.canView`) determines who can view the Call Flow stats in the Performance Monitor. Users with this privilege can view the Call Flow stats in the Performance Monitor.

Important

Users will see the Call Flow stats pane, but no data will be displayed if they do not have the privilege to access Call Flow Stats. The behavior prompted by this flag is the same for both CCAdv and CCAdv—ME.

[+] Current Capacity Stats Privilege

The Current Capacity Stats privilege (`ContactCenterAdvisor.PerformanceMonitor.CurrentCapacity.canView`) determines who can view the Current Capacity stats in the Performance Monitor. Users with this privilege can view the Current Capacity stats in the Performance Monitor.

Important

Users will see the Current Capacity stats pane, but no data will be displayed if they do not have the privilege to access Call Flow Stats. The behavior prompted by this flag is the same for both CCAdv and CCAdv—ME.

Functionality Privileges

Functionality privileges determine what tasks the user can perform or what functions a user can

execute on objects to which he/she has access.

Privileges are configured by using roles. If a privilege is present in a role, then any users assigned that role have access to the functionality controlled by that privilege. The value for the privilege key can be anything, or can be left blank.

Privileges for each role are stored as key-value pairs in the Annex tab of that role in Genesys Configuration Manager.

For more information about the CCAAdv functional privileges, see the [Contact Center Advisor and Workforce Advisor Administrator User's Guide](#).