



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

SpeechMiner Administration Guide

SMART Command Line

12/14/2025

SMART Command Line

SMART Command Line is useful when you are working with a development system and a production system. That is, the command line option enables the administrator to run a command in the production system, that imports and applies SMART programs and topics that were created in the development system. The programs and topics are exported from the development system as a UPF file.

Important

Before you perform the **SMART Command Line**, you must first **configure which database** should be used by the command line.

Configure which database should be used by the SMART Command Line

SMConfig

1. Log into **SMConfig**.
2. Select **Services**.
3. In the Services window, select **Update config files**.
4. Select the computer on which you want to run the SMART Command Line.
5. Click **Save**.

SMART

1. Go to **C:\Program Files (x86)\Genesys\Software\utopy\product\bin\release**.
2. Open **smartc.exe.config** and find the following section:

```
<connectionStrings>
  <add name="web_con_str"
  connectionString="server=[DBServer];uid=[DBUser];pwd=[DBPassword];database=[DBName];Min
  Pool Size=10;Max Pool Size=1000;connection lifetime=10" />
</connectionStrings>
```

3. Replace the code in the square brackets with the correct values and remove the square brackets.
4. Save the **smartc.exe.config** file.

Run the SMART Command Line

1. Open a command line, type smartc followed by the parameters you want to use and press **Enter**.

For example: smartc.exe [-i file.upf] [-a [-l Yes|No|Cancel]] [-u user -p password [-s|-g]]

The following is a list of the parameters you can use:

Command	Description
-i file.upf	Import the file.upf file.
-a	Apply changes to production.
-l Yes/No/Cancel	Specify whether or not to unlock locked items.
-u user	User name.
-p password	User's password.
-s	Specify SpeechMiner authentication (default).
-g	Specify Genesys authentication.