



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Microsoft Skype for Business Deployment Guide

Disable Lobby Bypass

12/13/2025

Disable Lobby Bypass

Description

It is possible to enable Skype for Business to use a lobby functionality. Enabling this feature in Skype for Business will result in callers being placed into a lobby rather than being directly admitted to a conference. The callers then need to be invited into the conference. This functionality is set on a Skype for Business Pool, and when configuring a new Pool by default the lobby feature is not enabled, meaning that callers will bypass the lobby and be directly admitted to a conference.

Background

Conferences are scheduled by the Skype for Business T-Server and are used to maintain Genesys call control. When scheduling conferences, the Skype T-Server specifies a LobbyBypass flag that automatically allows all callers to bypass a lobby and be directly admitted to a conference. However, this will cause issues when using the Skype for Business T-Server with a Skype for Business Pool that does not have lobby bypass enabled. Essentially, the Pool is configured to have callers wait in the lobby while T-Server is trying to pass a flag that allows callers to bypass the lobby. In order to prevent such issues a new option is introduced in the Skype for Business T-Server that will make it aware of whether a Pool is configured to use a lobby or has lobby bypass enabled.

Skype T-Server Configuration Options

Sections and options in this chapter are defined in the **Annex** tab of the **Switch** object of T-Server.

lobby-bypass-enabled

Section: conference-services

Default Value: True

Valid Values: true, false

Changes Take Effect: For next scheduled conference

Introduced: 8.5.001.67

Related Feature: Disable Lobby Bypass

Specifies whether the UCMA Connector enables a flag, lobby bypass, used for implementation of call control when scheduling conferences. When set to true, conferences created by the Connector allow participants to bypass a virtual lobby when joining private meetings. When set to false, conferences created by the Connector allow participants to join private meetings only through a virtual lobby.

PBX Configuration

The option that enables lobby bypass on a Skype for Business Pool is called **PstnCallersBypassLobby**, and this option is set in the Meeting Configuration. For more details please see:

- <https://docs.microsoft.com/en-us/skypeforbusiness/manage/conferencing/meeting-configuration-settings>

Limitations and constraints

The Skype T-Server will not be able to schedule conferences for new calls if the settings in Skype for Business and Skype T-Server configuration are inconsistent.