

# **GENESYS**

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

User's Guide

**Configure Context Services** 

# Configure Context Services

**Purpose:** To configure Context Services in the Configuration Layer.

## Contents

- 1 Configure Context Services
  - 1.1 Procedure
  - 1.2 Multiple Context Services on a Single Database

#### Procedure

1. To disable the other services, set the following parameters in the services section of the Options tab of the Context Services UCS application:

SystemInformation=DISABLE CustomerView=ENABLE ConfigSynchro=DISABLE Contact=DISABLE OMContacts=DISABLE Archive=DISABLE ArchiveSynchro=DISABLE Callback=DISABLE Chat=DISABLE DataIntegrityCorrection=DISABLE DataStatistics=DISABLE Index=DISABLE Ixn=DISABLE KnowledgeLibrary=DISABLE OMInteraction=DISABLE OMInteractions=DISABLE OMResponse=DISABLE PhoneCall=DISABLE ResourceProperty=DISABLE Stat=DISABLE Stencil=DISABLE URSService=DISABLE

The following screen shot displays this configuration in Genesys Administrator.

	0	Senesys Administrator	Tena	int: Environment	P New Window Log out	
MONITORING PROVISIONI	NG DI	EPLOYMENT OPERATIONS				
ROVISIONING > Environment	> Appl	ications > UCS_Lin_b				
avigation	«	UCS_Lin_b Unknown - Exited - \Applications\7.	Multimedia \			
Search	÷ )	🕻 Cancel 房 Save & Close 🍃 Save 🛃 Save & New 🛛 🗄	🖁 Reload 🛛 🙀 Uninstall 🛛 📫 Start	📓 Stop 🔣 Graceful Stop		
Environment		Configuration Options Permissi	ons Dependencies	Alarms	Logs	
Alarm Conditions		New 🙀 Delete 🎐 Export 🐳 Import			View: Advanced View (Options)	
🛃 Scripts						
Application Templates		Name A	Section	Option	Value	
Applications		Filter	Filter	Filter	Filter	
Hosts		) services (22 Items) services/Archive	services	Archive	disable	
Solutions		services/ArchiveSvnchro	services	ArchiveSynchro	disable	
Jime Zones		services/Callback	services	Callback	disable	
Business Units/Sites		services/Caliback	services	Caliback	disable	
Tenants		services/ConfigSynchro	services	ConfigSynchro	disable	
Jable Access Points		services/Contact	services	Contact	disable	
Formats		services/CustomerView	services	CustomerView	enable	
Fields		services/DataIntegrityCorrection	services	DataIntegrityCorrection	disable	
n leius		services/DataStatistics	services	DataStatistics	disable	
		services/Index	services	Index	disable	
		services/lxn	services	Ixn	disable	
		services/KnowledgeLibrary	services	KnowledgeLibrary	disable	
		services/OMContacts	services	OMContacts	disable	
		services/OMInteraction	services	OMInteraction	disable	
		services/OMInteractions	services	OMInteractions	disable	
		services/OMResconse	services	OMResponse	disable	
		services/PhoneCall	services	PhoneCall	disable	
Switching	•	services/ResourceProperty	services	ResourceProperty	disable	
Routing/eServices	(+)	services/Stat	services	Stat	disable	
Desktop	Ē	services/Stencil	services	Stencil	disable	
Accounts	Ē	services/SystemInformation	services	SystemInformation	disable	
Voice Platform	Ŧ	services/URSService	services	URSService	disable	
•		🛛 🖉 Page 1 of 2 🕨 🔰 🍣			Displaying objects	1 - 100 -61
Outbound Contact		N N Lagel. 012 / MI KC			Displaying Objects	1 100 01 1

#### Important

CustomerView is the only enabled parameter.

- 2. To disable Remote Method Invocation (RMI), set the enable-rmi parameter in the settings section on the Options tab of the Ontext Services UCS application to false.
- 3. To assign the RMI port, set the ucsapi parameter in the ports section on the Options tab of the Context Services UCS application to a correct port number. For example, 7550.

#### Important

Even if RMI is not used, this port number must be assigned.

## Multiple Context Services on a Single Database

When configuring multiple Context Services on the same database:

- 1. Start one Context Services with the option ConfigSynchro set to ENABLE and all other options set to DISABLE.
- 2. Configure all other Context Services instances as described previously, with the listed options set to DISABLE.

When in the customizing phase, you may have to change the configuration of the core Profile attributes in the Configuration Layer. In this case:

- One (and only one) instance must have the option ConfigSynchro set to ENABLE. Use this instance to update Profiles or Services metadata.
- After each change, reload the cache on each of other instances using /metadata/cache URI.