

GENESYS

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Configurations Options Reference Manual

Application Parameter Options

Application Parameter Options

Set options in this section in the Application Parameters of a port's properties, using the following navigation path:

• Configuration Server Application object > Configuration tab > Server Info section > Listening Ports > Port Info

Application Parameter options are not associated with a configuration option section, and do not appear in the options or annex of a Configuration Server Application object.

backlog

Default Value: 5

Valid Values: Any positive integer greater than 4

Changes Take Effect: Immediately

Specifies the maximum number of outstanding connection requests from clients. When the maximum is reached, Configuration Server does not accept a new request until an outstanding request is processed.

Important

This option is for advanced use only, and is logged only in Debug level logs. Use this option only when requested by Genesys Customer Care.

user

Default Value: No default value Valid Values: 1 or not set

Changes Take Effect: Immediately

When set to 1, the port refuses all connection requests from applications that do not require user-level authentication. When not set, or set to any other value, the option is ignored.