

GENESYS

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Info Mart Physical Data Model for a PostgreSQL Database

Table SDR USER INPUTS FACT

Table SDR USER INPUTS FACT

Description

Introduced: 8.5.004.09

Modified: 8.5.116.45 (size of the SESSION_ID column increased); 8.5.010.16 (UPDATE_AUDIT_KEY added); 8.5.010 (in Microsoft SQL Server, data type for UTTERANCE and INTERPRETATION modified in multi-language databases); 8.5.008 (data type for UTTERANCE and INTERPRETATION increased from 50 to 512 characters)

In partitioned databases, this table is partitioned.

This fact table provides a record of user input activity within an SDR session. A new row is added for every user input during the session.

Tip

To assist you in preparing supplementary documentation, click the following link to download a comma-separated text file containing information such as the data types and descriptions for all columns in this table: Download a CSV file.

Hint: For easiest viewing, open the downloaded CSV file in Excel and adjust settings for column widths, text wrapping, and so on as desired. Depending on your browser and other system settings, you might need to save the file to your desktop first.

Column List

Legend

Column	Data Type	Р	M	F	DV
SESSION_ID	varchar(128)	X	X		
START_DATE_TIM	l <mark>E<u>i</u>rktlev</mark> ger	X	Χ	X	
SEQUENCE_ID	integer	X	Χ		

Column	Data Type	Р	M	F	DV
START_TS_MS	numeric(19)				
DURATION_MS	numeric(19)		Χ		0
UTTERANCE	varchar(512)		X		NO_VALUE
INTERPRETATION	varchar(512)		X		NO_VALUE
CONFIDENCE	varchar(50)		X		1
CONDITIONAL_O	PTMandSar(50)		X		n/a
SDR_INPUT_KEY	integer		X	X	-2
SDR_USER_INPUT	<mark>T_ikiEe∕</mark> ger		X	X	-2
SDR_INPUT_OUT	C OnMe g ≰EY		X	X	-2
SDR_APPLICATIO	N <u>i</u> rkt le ger		X	Χ	-2
CREATE_AUDIT_k	(EYumeric(19)		X	X	
UPDATE_AUDIT_k	(EYumeric(19)			Χ	

SESSION ID

Modified: 8.5.116.45 (size of the column increased)

The ID as assigned to the session by Orchestration Server. In combination with SEQUENCE_ID, the SESSION_ID forms a value of the composite primary key for this table. You can use the SESSION_ID to link the SDR USER INPUTS FACT record with an SDR SESSION FACT.

START_DATE_TIME_KEY

Identifies the start of a 15-minute interval in which the call began. Use this value as a key to join the fact tables to any configured DATE_TIME dimension, in order to group the facts that are related to the same interval and/or convert the START TS timestamp to an appropriate time zone.

SEQUENCE ID

The unique identifier of the input block within the SDR. In combination with SESSION_ID, the SEQUENCE ID forms a value of the composite primary key for this table.

START TS MS

Modified: 8.5.008 (no longer mandatory)

The UTC-equivalent value, in milliseconds, of the date and time at which the user input started.

DURATION_MS

The duration, in milliseconds, of the activity within the user input block.

UTTERANCE

Modified: 8.5.010 (in Microsoft SQL Server, data type modified in multi-language databases); 8.5.008 (data type increased from 50 to 512 characters) The actual user input that was captured.

- For voice input processed by Automatic Speech Recognition (ASR), the actual phrase the caller uttered for example, *Billing*.
- For DTMF input, the digit the caller pressed for example, 2.

INTERPRETATION

Modified: 8.5.010 (in Microsoft SQL Server, data type modified in multi-language databases); 8.5.008 (data type increased from 50 to 512 characters)
The application-defined string or DTMF value of the selected option represented by UTTERANCE.

CONFIDENCE

On a scale of 0 to 1, the degree of confidence in the accuracy of the interpretation of the user input.

CONDITIONAL OPTIONS

A string representing the valid DTMF when conditional options are enabled. The default value (n) indicates that conditional options are not enabled. This value can vary from call to call for the same application.

SDR INPUT KEY

The key that is used to join the SDR INPUT dimension to the fact tables.

SDR USER INPUT KEY

The key that is used to join the SDR USER INPUT dimension to the fact tables.

SDR INPUT OUTCOME KEY

The key that is used to join the SDR INPUT OUTCOME dimension to the fact tables.

SDR APPLICATION KEY

The key that is used to join the SDR APPLICATION dimension to the fact tables.

CREATE AUDIT KEY

The surrogate key that is used to join to the CTL_AUDIT_LOG control table. The key specifies the lineage for data creation. This value can be useful for aggregation, enterprise application integration (EAI), and ETL tools — that is, applications that need to identify newly added data.

UPDATE AUDIT KEY

Introduced: Release 8.5.010.16

The surrogate key that is used to join to the CTL_AUDIT_LOG control table. The key specifies the lineage for data update. This value can be useful for aggregation, enterprise application integration (EAI), and ETL tools — that is, applications that need to identify recently modified data.

Index List

CODE	U	С	Description
I_SDR_USER_INPUTS_FACT	_SDT		Improves access time, based on the Start Date Time key.

Index I_SDR_USER_INPUTS_FACT_SDT

Field	Sort	Comment
START_DATE_TIME_KEY	Ascending	

Subject Areas

No subject area information available.