



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

GVP Documentation Supplement

[Enable Inline Grammar Access by URL](#)

5/6/2025

Enable Inline Grammar Access by URL

Follow these steps to enable inline grammar access by URL:

Windows IIS Environment

1. Verify that IIS is installed and started, and that MCP is installed.
2. Create and add the directory `inlinetmp` under `C:\Program Files\Common Files\GCTI\www\gvp\mcp\<MCP_application>\grammar\`.

Steps 3 and 4 are automatically performed by the MCP installation in a Windows 32-bit environment, but must be performed manually in a 64-bit environment:

3. Add the application `mcp` in IIS, which points to `C:\Program Files\Common Files\GCTI\www\gvp\mcp`.
4. Enable **Directory Browsing** and add the mime type `application/octet-stream` for the extension `*` to the application `mcp` in IIS.

Linux Environment

1. Verify that MCP is installed.
2. Create the virtual directory `/var/www/gvp/mcp/` by adding these lines of code to the file `/etc/http/conf/httpd.conf`:

```
Alias /mcp/ "/var/www/gvp/mcp/"
<Directory "/var/www/gvp/mcp/">
    Options Indexes MultiViews
    AllowOverride None
    Order allow,deny
    Allow from all
    ExpiresActive On
    ExpiresDefault "now plus 5 minutes"
</Directory>
```

3. Enable the `httpd` service
(run `chkconfig` and specify `level 345 httpd on`) ????????
4. Start the `httpd` service (run `start` in the directory `/etc/init.d/httpd`).
5. Add the directory `inlinetmp`, with grant read and access permission granted to all files and directories beneath `/var/www/gvp/mcp/<MCP_application>/grammar/`.