

GENESYS

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Voice Platform

https Section

https Section

- https.certificate.algorithm
- https.client.authentication
- https.connector.type
- https.keystore.path
- https.keystore.type
- https.protocol

- · https.random.algorithm
- https.security.provider
- password

https.certificate.algorithm

Default Value: SunX509

Valid Values: Name of HTTPS algorithm **Changes Take Effect:** at start/restart

The SSL algorithm used for the configured keystore.

https.client.authentication

Default Value: none

Valid Values:

none

No certificate request, so client-side authentication is disabled.

required

A certificate is requested and the server will require a valid, non-empty certificate response to establish the connection. (Only works for BIO connector type).

preferred

A certificate is requested, but the server will still establish the connection if the certificate response is empty.

Changes Take Effect: at start/restart

HTTPS client authentication requirements.

https.connector.type

Default Value: 2

Valid Values:

NIO

Non-blocking NIO connector (Refer to Jetty's JavaDoc for class org.mortbay.jetty.security.SslSelectChannelConnector for more information).

BIO

Blocking BIO connector (Refer to Jetty's JavaDoc for class org.mortbay.jetty.security.SslSocketConnector for more information).

Changes Take Effect: at start/restart

The type of Jetty connector to use

https.keystore.path

Default Value: \${user.home}/.keystore

Valid Values: A directory path

Changes Take Effect: at start/restart

The path to the keystore file, which will be used for all the HTTPS connectors.

https.keystore.type

Default Value: JKS

Valid Values: A HTTPS keystore type Changes Take Effect: at start/restart

The type of keystore, which defines the file format that the security implementation supports.

https.protocol

Default Value: TLS

Valid Values:

SSL

Supports some version of SSL.

SSLv2

Supports SSL version 2 or higher.

SSLv3

Supports SSL version 3; may support other versions.

TLS

Supports some versions of TLS.

TLSv1

Supports TLS version 1; may support other versions.

Changes Take Effect: at start/restart

The cryptographic protocol to use.

https.random.algorithm

Default Value:

Valid Values: Name of the RNG (Random Number Generator) algorithm

Changes Take Effect: at start/restart

Refer to the JDK JavaDoc for class java.security.SecureRandom for more information.

https.security.provider

Default Value:

Valid Values: Name of Java security provider

Changes Take Effect: at start/restart

Refer to the JDK JavaDoc for class java.security.Provider for more information.

password

Default Value:

Valid Values: A string

Changes Take Effect: at start/restart



The password for the keystore file.