

GENESYS

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Workspace Desktop Edition

Genesys Configuration Options Current

Table of Contents

Workspace Desktop Edition Options Reference	3
Workspace Desktop Edition	4
interaction-workspace Section	43
Team Communicator Presence Options	254
interaction-queue-presence Section	255
queue-presence Section	258
routing-point-presence Section	261
TServer Section	264
Interaction Workspace	267
interaction-workspace Section	293
Team Communicator Presence Options	437
interaction-queue-presence Section	438
queue-presence Section	440
routing-point-presence Section	442
Change History	444

Workspace Desktop Edition Options Reference

Welcome to the Options Reference for Genesys Workspace.

Important

For information about how to use these options to configure Genesys Web Services functionality and behavior, refer to the *Workspace Desktop Edition Deployment Guide*.

This document describes the configuration options for the following components of Genesys Workspace:

- Workspace Desktop Edition 8.5
- Interaction Workspace 8.1

Workspace Desktop Edition

The majority of Workspace configuration options are configured in the interaction-workspace section. This is a section that you create in the annex of the object to which you want to apply the option. Most of these options can be configured hierarchically at the Application, Tenant, Agent Group, or User level; some can be configured on other objects such as DNs, skills, and switches. For more information about using Workspace configuration options, refer to Introduction to Configuration Options.

The KPI section, Statistics section, and Not Ready Reason Codes objects are not included in this option reference.

The values specified for many options can also be overridden by Routing Strategies that reference Transaction objects.

Workspace options are grouped by functionality. The first word in the name of the option indicates the functional area to which the option belongs. For example, the option chat.emojis-business-attribute is part of the **chat** functionality group. It enables you to specify the name of the **business attribute** that contains the **emojis** that agents enabled for the Chat channel can use in the Chat window. The options are named to help you know quickly what the option does.

The *Workspace Deployment Guide* contains topics specific to configuring options as a group to manage each functional area. For example, you can read about setting up the Chat channel in the Chat topic.

Options for this component are contained in the following configuration sections:

- interaction-queue-presence
- interaction-workspace
- queue-presence

- routing-point-presence
- TServer

Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

Power users: Download a CSV file containing default and valid values and descriptions.

The following options are configured on the Application, Tenant, Agent Group, User, or other object.

Section	Option	Default	Changes Take Effect
interaction-queue- presence	associated-object-ids	No default value	When the application is started or restarted
interaction-queue- presence	associated-statistic-type	No default value	When the application is started or restarted
interaction-queue- presence	error-level	10	When the application is started or restarted.
interaction-queue- presence	object-ids	No default value	When the application is started or restarted
interaction-queue- presence	statistic-name		When the application is started or restarted.
interaction-queue- presence	statistic-text	interaction(s) waiting.	When the application is started or restarted.
interaction-queue- presence	warning-level	5	When the application is started or restarted.
interaction-workspace	<media-type>.auto- answer</media-type>	false	At the next interaction.
interaction-workspace	<media-type>.auto- answer.enable-reject</media-type>	false	At the next interaction.
interaction-workspace	<media-type>.auto- answer.timer</media-type>	0	At the next interaction.
interaction-workspace	<media-type>.contact- history.enable-combine- interaction-with-current</media-type>	true	Immediately.
interaction-workspace	<media-type>.contact- history.enable-combine- ixn-with-current</media-type>	true	Immediately.
interaction-workspace	<media-type>.prompt- for-done</media-type>	false	At the next interaction.
interaction-workspace	<media-type>.pull- from-history-isenabled</media-type>	false	Immediately.
interaction-workspace	<media-type>.ringing- bell</media-type>	Sounds\ Ring.mp3 10 -1 primary	At the next interaction.
interaction-workspace	<media-type>.toast- information-key</media-type>	Subject	At the next interaction.
interaction-workspace	accessibility.agent- state-change-bell		At the next interaction.
interaction-workspace	accessibility.disable- hyperlinks	false	The next time an interaction containing a hyperlink is displayed.
interaction-workspace	accessibility.focus-on-interaction-toast	false	At the next interaction.
interaction-workspace	accessibility.interaction- state-change-bell		At the next interaction.
interaction-workspace	accessibility.visual-	false	When the application is
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
	impairment-profile		started or restarted.
interaction-workspace	accessibility.warning- message-bell		At the next interaction.
interaction-workspace	accessibility. <media- type>.focus-on- interaction-toast</media- 	false	At the next interaction.
interaction-workspace	active- recording.voice.recorder- uri		At application restart.
interaction-workspace	active- recording.voice.recording- type	NETANN	At application restart.
interaction-workspace	agent-status.enabled- actions-by-channel	Ready,NotReady,NotReady	y RreamedjAftelyCallWork,Dnd
interaction-workspace	agent-status.enabled- actions-global	Ready,NotReady,NotReady	y Remanaedj Aftely CallWork,Dnd
interaction-workspace	agent-status.not-ready- reasons		Immediately.
interaction-workspace	alert.timeout	10	When the application is started or restarted.
interaction-workspace	application.available- layouts	main-window	When the application is started or restarted.
interaction-workspace	application.secondary- audio-out-device	\$AllNonDefault\$	When the application is started or restarted.
interaction-workspace	application.wiki-help- locale		At next request to the online help.
interaction-workspace	application.wiki-help- welcome-page		At next request to on- line help.
interaction-workspace	broadcast.color.high- priority	#FF5E99FF	Immediately.
interaction-workspace	broadcast.color.important- priority	#FFE81100	Immediately.
interaction-workspace	broadcast.color.low- priority	#FF7EC0C2	Immediately.
interaction-workspace	broadcast.color.minimal- priority	#FFC7C7C7	Immediately.
interaction-workspace	broadcast.color.normal- priority	#FFC48C88	Immediately.
interaction-workspace	broadcast.displayed- columns	MessageTypeIcon,Message	When the application is a lype Sender Subject, Priori started or restarted.
interaction-workspace	broadcast.dn		When the application is started or restarted.
interaction-workspace	broadcast.enable- removal	all	At next access to a message.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	broadcast.enable- removal-priority	Important	At next access to a message.
interaction-workspace	broadcast.mark-read- timeout	5	When the application is started or restarted.
interaction-workspace	broadcast.message- content	Subject, Sender, Priority, Da	t A £TolpecrBoxdymessage.
interaction-workspace	broadcast.preview- timeout	10	At the next message.
interaction-workspace	broadcast.sound.high- priority		At the next interaction.
interaction-workspace	broadcast.sound.importar priority	t-	At the next interaction.
interaction-workspace	broadcast.sound.low- priority		At the next interaction.
interaction-workspace	broadcast.sound.minimal- priority		At the next interaction.
interaction-workspace	broadcast.sound.normal- priority		At the next interaction.
interaction-workspace	broadcast.subscribed.topi	c s All,\$Agent\$,\$AgentGroup\$	When the application is started or restarted.
interaction-workspace	broadcast.system- messages-auto-mark- read	true	At next change of counter value.
interaction-workspace	broadcast.toast- summary	Sender, Priority,Subject,FewWords	At the next message.
interaction-workspace	broadcast.value- business-attribute		When the application is started or restarted.
interaction-workspace	callback.callback- information.content	DesiredTime, Type, Number, Instructions	At the next interaction.
interaction-workspace	callback.callback- information.frame-color	1. FF17849D	At the next interaction.
interaction-workspace	callback.callback- information.header- foreground-color	#FFFFFFF	At the next interaction.
interaction-workspace	callback.callback-types- business-attribute		At the next interaction.
interaction-workspace	callback.gms-url		At next callback request.
interaction-workspace	callback.ringing-bell	Sounds\ Ring.mp3 10 -1 primary	At the next interaction.
interaction-workspace	case-data.float- separator		Immediately.
interaction-workspace	channel-	\$Window.Title\$	Immediately.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
	information.window-title		
interaction-workspace	chat.agent.prompt-color	#FF2E6599	Immediately.
interaction-workspace	chat.agent.text-color	#FF3D464D	Immediately.
interaction-workspace	chat.attachment- download-timeout	20	Immediately.
interaction-workspace	chat.auto-answer	false	At the next interaction.
interaction-workspace	chat.auto- answer.enable-reject	false	At the next interaction.
interaction-workspace	chat.auto-answer.timer	0	At the next interaction.
interaction-workspace	chat.auto-mark-done- non-owner-agent	false	Immediately
interaction-workspace	chat.auto-mark-done- non-owner-agent.timer	0	Immediately
interaction-workspace	chat.auto-mark-done- owner-agent	false	Immediately
interaction-workspace	chat.auto-mark-done- owner-agent.timer	0	Immediately
interaction-workspace	chat.client.prompt-color	#FFAF4F0B	Immediately.
interaction-workspace	chat.client.text-color	#FF3D464D	Immediately.
interaction-workspace	chat.emojis-business- attribute		At the next interaction.
interaction-workspace	chat.enable-auto- disconnect	true	At the next interaction.
interaction-workspace	chat.historical.maximum- age	0	At the next interaction.
interaction-workspace	chat.max-attachments- files	0	At the next interaction.
interaction-workspace	chat.max-attachments- size	0	At the next interaction.
interaction-workspace	chat.max-file-size	0	At the next interaction.
interaction-workspace	chat.new-message-bell		Immediately
interaction-workspace	chat.nickname	\$Agent.UserName\$	At the next interaction.
interaction-workspace	chat.on-hold-queue	No default value	At the next attempt to put a chat in a queue.
interaction-workspace	chat.other- agent.prompt-color	#FF295B00	Immediately.
interaction-workspace	chat.other-agent.text- color	#FF3D464D	Immediately.
interaction-workspace	chat.pending-response- to-customer	30,50	At the next interaction.
interaction-workspace	chat.pending-response- to-customer-bell		Immediately
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	chat.prompt-for-end	false	At the next interaction.
interaction-workspace	chat.reconnect-attempts	5	At the next interaction.
interaction-workspace	chat.reconnect-timeout	10	At the next interaction.
interaction-workspace	chat.restricted- attachment-file-types		At the next interaction.
interaction-workspace	chat.rich-media-widget- width	300	At the next interaction.
interaction-workspace	chat.ringing-bell	Sounds\ Ring.mp3 10 -1 primary	At the next interaction.
interaction-workspace	chat.show-attachment- image-thumbnail	never	At the next interaction.
interaction-workspace	chat.show-unread- notification	true	At the next sent message.
interaction-workspace	chat.simple-transcript	false	At the next interaction.
interaction-workspace	chat.system.text-color	#FF8C8C8C	Immediately.
interaction-workspace	chat.time-stamp	true	Immediately.
interaction-workspace	chat.toast-information- key	Subject	At the next interaction.
interaction-workspace	chat.transcript-enable- history-filters	false	At the next interaction.
interaction-workspace	chat.transcript- message-text-direction	ltr	At the next interaction.
interaction-workspace	chat.typing-isenabled	true	At the next interaction.
interaction-workspace	chat.typing-timeout	10	At the next interaction.
interaction-workspace	chatserver.addp.local- timeout	0	At the next interaction.
interaction-workspace	chatserver.addp.remote- timeout	0	At the next interaction.
interaction-workspace	chatserver.addp.trace- mode	off	At the next interaction.
interaction-workspace	chatserver.ip-version	auto	At the next interaction.
interaction-workspace	chatserver.tls-mutual	false	When the application is started or restarted.
interaction-workspace	contact.all-interactions- default-time-filter-main	1W	When the application is started or restarted.
interaction-workspace	contact.all-interactions- displayed-columns	Status, Subject, Start Date, I	When the application is started or restarted.
interaction-workspace	contact.all-interactions- displayed-columns- treeview	Status,Subject,StartDate	When the application is started or restarted.
interaction-workspace	contact.all-interactions- quick-search-attributes	Subject	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	contact.available- directory-page-sizes	5,10,25,50	When the application is started or restarted.
interaction-workspace	contact.cache-timeout- delay	600	When the application is started or restarted.
interaction-workspace	contact.date-search- types	On,OnOrAfter,Before,Betw	When the application is een started or restarted.
interaction-workspace	contact.default- directory-page-size	10	When the application is started or restarted.
interaction-workspace	contact.directory- advanced-default	LastName,PhoneNumber	When the application is started or restarted.
interaction-workspace	contact.directory-auto- append-star-to-search	true	
interaction-workspace	contact.directory- default-mode	ListView	Immediately.
interaction-workspace	contact.directory- displayed-columns	LastName,FirstName,Phon	When the application is eNumber, Email Address started or restarted.
interaction-workspace	contact.directory- enabled-modes	ListView,GridView	When the application is started or restarted.
interaction-workspace	contact.directory- permissions. <contactattr< td=""><td>buteName></td><td>At the next contact search.</td></contactattr<>	buteName>	At the next contact search.
interaction-workspace	contact.directory- search-attributes	LastName,FirstName,Phon	When the application is eNumber, Email Address started or restarted.
interaction-workspace	contact.directory- search-types	begins-with,is	When the application is started or restarted.
interaction-workspace	contact.displayed- attributes	Title, First Name, Last Name,	When the application is Phone Number Email Address started or restarted.
interaction-workspace	contact.editable- attributes	\$AII\$	When the application is started or restarted.
interaction-workspace	contact.history- advanced-default	Status,StartDate	When the application is started or restarted.
interaction-workspace	contact.history-auto- append-star-to-search	true	At the next search
interaction-workspace	contact.history-custom- attribute- values. <attribute- name></attribute- 		When the application is started or restarted.
interaction-workspace	contact.history-custom- attributes-search-types	is	When the application is started or restarted.
interaction-workspace	contact.history-default- time-filter-main	1M	When the application is started or restarted, or at the next interaction.
interaction-workspace	contact.history- displayed-columns	Status, Subject, Start Date, E	When the application is no date of restarted.
interaction-workspace	contact.history-	Status,Subject,StartDate	When the application is
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
	displayed-columns- treeview		started or restarted.
interaction-workspace	contact.history.filters- <attribute></attribute>		At the next contact search.
interaction-workspace	contact.history.highlight- current-interaction	false	At the next interaction
interaction-workspace	contact.history.media- filters	voice,email,chat,sms	When the application is started or restarted.
interaction-workspace	contact.history-quick- search-attributes	Subject	When the application is started or restarted.
interaction-workspace	contact.history-search- attribute-group. <group- name></group- 		When the application is started or restarted.
interaction-workspace	contact.history-search- attributes	Status,StartDate,EndDate	When the application is started or restarted.
interaction-workspace	contact.history.voice- detail-attributes	Date,Contact,PhoneNumb	When the application is er Duration started or restarted.
interaction-workspace	contact.last-called- agent.enable	true	Immediately.
interaction-workspace	contact.last-called- agent. <media- type>.enable</media- 	true	Immediately.
interaction-workspace	contact.lookup.auto- assign-mode	true	At the next interaction
interaction-workspace	contact.lookup.enable	true	Immediately.
interaction-workspace	contact.lookup.enable- create-contact	true	Immediately.
interaction-workspace	contact.lookup.voice.use- dialed-phone-number	false	When the application is started or restarted.
interaction-workspace	contact.lookup. <media- type>.auto-assign- mode</media- 	true	
interaction-workspace	contact.lookup. <media- type>.enable</media- 	true	Immediately.
interaction-workspace	contact.lookup. <media- type>.enable-create- contact</media- 	true	Immediately.
interaction-workspace	contact.mandatory- attributes	FirstName,LastName	When the application is started or restarted.
interaction-workspace	contact.metrics.enable- interactions-in-progress	true	When the application is started or restarted.
interaction-workspace	contact.metrics.time- frame-customer- notification	1	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	contact.multi-value- attribute- display. <contact- attribute></contact- 	Value, Description	When the application is started or restarted.
interaction-workspace	contact.multiple-value- attributes	EmailAddress,PhoneNumb	When the application is started or restarted.
interaction-workspace	contact.multiple-value- attributes-enable- default-description	false	When the application is started or restarted.
interaction-workspace	contact.myhistory- default-time-filter-main	1W	When the application is started or restarted.
interaction-workspace	contact.myhistory- displayed-columns	Status, Subject, Start Date, E	When the application is started or restarted.
interaction-workspace	contact.myhistory- displayed-columns- treeview	Status,Subject,StartDate	When the application is started or restarted.
interaction-workspace	contact.myhistory- quick-search-attributes	Subject	When the application is started or restarted.
interaction-workspace	contact.threading-ucs- interaction.enable	true	Immediately.
interaction-workspace	contact.timeout-delay	60	When the application is started or restarted.
interaction-workspace	contact.ucs- interaction. <media- type>.enable-create</media- 	true	Immediately.
interaction-workspace	contact.ucs- interaction. <media- type>.enable-lookup</media- 	true	Immediately.
interaction-workspace	contact.ucs- interaction. <media- type>.use-server-date</media- 	false	When the application is started or restarted.
interaction-workspace	dial-plan-rule- <name></name>		When the application is started or restarted.
interaction-workspace	disaster-recovery.auto- restore	true	When the application is started or restarted
interaction-workspace	disaster- recovery.disable-login- errors	false	When the application is started or restarted.
interaction-workspace	disaster- recovery.enabled	false	When the application is started or restarted
interaction-workspace	disaster- recovery.eservices- random-delay-range	5	When the application is started or restarted
interaction-workspace	disaster- recovery.eservices-site	No default value	
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
nteraction-workspace	disaster-recovery.peer- site	DRPeer	When the application is started or restarted
nteraction-workspace	disaster- recovery.preferred-site	Preferred	When the application is started or restarted
nteraction-workspace	disaster- recovery.restore-agent- state	true	When the application is started or restarted.
nteraction-workspace	disaster- recovery.timeout	60	When the application is started or restarted
nteraction-workspace	disaster-recovery.wait- for-sipphone-timeout	0	When the application is started or restarted
nteraction-workspace	display-format.acd- queue.name	\$ACDQueue.AnnexValue\$	\$ACD@diatelyDictionaryValue\$
nteraction-workspace	display-format.action- code.name	\$ActionCode.AnnexValue\$	\$%Action ia belg. Dictionary Value
nteraction-workspace	display-format.agent- group.name	\$AgentGroup.AnnexValue	\$ \$Argnedit&trelly p.DictionaryValu
nteraction-workspace	display-format.agent- name	\$Agent.FullName\$ \$Agent	. UsenNdiats \$y.
nteraction-workspace	display-format.business- attribute.name	\$BusinessAttribute.Annex	V ahonenelsiBusiy nessAttribute.Dic
nteraction-workspace	display-format.caller- name	\$Contact.FirstName\$ \$Contact.LastName\$ \$Inte	Immediately eraction.MainParty\$
nteraction-workspace	display-format.case- name-format	\$Contact.FirstName\$ \$Contact.LastName\$ \$Into	Immediately eraction.MainParty\$
nteraction-workspace	display-format.chat- agent-name	\$ChatAgent.FullName\$ \$0	Ch atı Agedi a te ligkname \$ \$ Chat Ag
nteraction-workspace	display-format.chat- customer-name	\$Contact.FirstName\$ \$Contact.LastName\$ \$Par	ty.DisplayName\$
nteraction-workspace	display-format.contact- name	\$Contact.FullName\$	Immediately.
nteraction-workspace	display-format.current- agent-name	\$Agent.FullName\$ \$Agent	. UsenNdiats \$y.
nteraction-workspace	display- format.customer-name- format	\$Contact.FirstName\$ \$Contact.LastName\$ \$Par	ty.DisplayName\$
nteraction-workspace	display- format.field.name	\$Field.AnnexValue\$ \$Field	. Dringtringerdpiagy&/ay lue\$ \$Field.Name
nteraction-workspace	display- format.folder.name	\$Folder.AnnexValue\$ \$Fol	d emDiedioatæ lyValue\$ \$Folder.N
nteraction-workspace	display- format.interaction- callback-name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$ \$Inte	Immediately. eraction.MainParty\$)
nteraction-workspace	display-	\$Interaction.Type\$	Immediately.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect	
	format.interaction-chat- name	(\$Contact.FirstName\$ \$Contact.LastName\$ \$Inte	eraction.MainParty\$)	
interaction-workspace	display- format.interaction- email-name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$ \$Inte	Immediately. eraction.MainParty\$)	
interaction-workspace	display- format.interaction-im- name	\$Interaction.Type\$ \$Interaction.MainParty\$	Immediately.	
interaction-workspace	display- format.interaction- outbound-pull-preview- name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$ \$Inte	Immediately. eraction.MainParty\$)	
interaction-workspace	display- format.interaction- outbound-push-preview- name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$ \$Inte	Immediately. eraction.MainParty\$)	
interaction-workspace	display- format.interaction- queue.name	\$InteractionQueue.Annex	When the application is Values sinter action Queue.D started or restarted.	ictionaryV
interaction-workspace	display- format.interaction-sms- name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$ \$Inte	Immediately. eraction.MainParty\$)	
interaction-workspace	display- format.interaction- voice-name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$ \$Inte	Immediately. eraction.MainParty\$)	
interaction-workspace	display- format.interaction- workitem-name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$ \$Inte	Immediately. eraction.MainParty\$)	
interaction-workspace	display- format.outbound-record- name	\$OutboundRecord.PhoneT - \$OutboundRecord.PhoneN	At the next interaction.	
interaction-workspace	display-format.party- name-format	\$Party.DisplayName\$	Immediately.	
interaction-workspace	display-format.routing- point.name	\$RoutingPoint.AnnexValue	e\$ s\Roediagely int.Dictionary\	/alue\$ \$Ro
interaction-workspace	display- format.skill.name	\$Skill.AnnexValue\$ \$Skill.	D lotionealia्रार्थ्या प्रe\$ \$Skill.Nam	ie\$
interaction-workspace	display-format.virtual- queue.name	\$VirtualQueue.AnnexValue	e \$ \$ vietdiat@ly eue.Dictionary	Value\$ \$Vi
interaction-workspace	display- format.workbin.name	\$Workbin.AnnexValue\$ \$V	V ornkıbriedDätëliy naryValue\$ \$V	Vorkbin.Dis
interaction-workspace	editor.font-size-units	point	At the next interaction.	
interaction-workspace	editor.shortcuts.prefix	#	Immediately	
interaction-workspace	editor.user-agent-http- header	Mozilla/4.0 (compatible; MSIE 7.0)	At next interaction.	
Section	Option	Default	Changes Take Effect	

Section	Option	Default	Changes Take Effect
interaction-workspace	email.attachment- download-timeout	20	Immediately.
interaction-workspace	email.auto-answer	false	At the next interaction.
interaction-workspace	email.auto- answer.enable-reject	false	At the next interaction
interaction-workspace	email.auto-answer.timer	0	At the next interaction.
interaction-workspace	email.can-change-text- direction	false	
interaction-workspace	email.default-queue		At the next interaction.
interaction-workspace	email.forward.enable- cc-addresses	false	At the next interaction.
interaction-workspace	email.forward.enable-instructions	false	At the next interaction.
interaction-workspace	email.forward.enable- multiple-to-addresses	false	At the next interaction.
interaction-workspace	email.forward-queue		Immediately.
interaction-workspace	email.from-addresses	\$EMAILSERVER\$	When the application is started or restarted.
interaction-workspace	email.from- addresses.force-default- on-reply	false	When the application is started or restarted.
interaction-workspace	email.html-format	true	At the next interaction.
interaction-workspace	email.include-original- text-in-reply	true	At the next interaction.
interaction-workspace	email.include-standard- response-subject-on- insert	false	At the next interaction.
interaction-workspace	email.inline-forward- prefix	Fwd:	Immediately.
interaction-workspace	email.inline-forward- queue		Immediately.
interaction-workspace	email.mandatory- subject	false	At next attempt to send an email.
interaction-workspace	email.max-attachments- size	0	At the next interaction.
interaction-workspace	email.move-inbound-to- in-progress-workbin-on- reply	false	At the next interaction.
interaction-workspace	email.outbound.copy- editable-case-data-in- inbound	false	At the next interaction.
interaction-workspace	email.outbound.editable- bcc-addresses	true	At the next interaction.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	email.outbound.editable- cc-addresses	true	At the next interaction.
interaction-workspace	email.outbound.editable- to-addresses	true	At the next interaction.
interaction-workspace	email.outbound-queue		Immediately.
interaction-workspace	email.prompt-for-done	false	At the next interaction.
interaction-workspace	email.pull-from-history- isenabled	true	Immediately.
interaction-workspace	email.qa-review- dispositions-business- attribute		At the next interaction.
interaction-workspace	email.quote-char	>	Immediately.
interaction-workspace	email.quote-header	On <date>, <contact> wrote:</contact></date>	Immediately.
interaction-workspace	email.reply-copy- category-id	false	At the next interaction.
interaction-workspace	email.reply-format	auto	At the next interaction.
interaction-workspace	email.reply-prefix	Re: <space></space>	Immediately.
interaction-workspace	email.resend-prefix	No default value	Immediately
interaction-workspace	email.restricted- attachment-file-types		At the next interaction.
interaction-workspace	email.ringing-bell	Sounds\ Ring.mp3 10 -1 primary	At the next interaction.
interaction-workspace	email.set-ownerid-on- send	true	At the next interaction.
interaction-workspace	email.signature		At the next interaction.
interaction-workspace	email.toast-information- key	Subject	At the next interaction.
interaction-workspace	eservices.disconnect- on-logoff	false	When the application is started or restarted.
interaction-workspace	eservices.session- restore-mediatype	chat,email,sms	At the next interaction.
interaction-workspace	eservices.session- restore-timeout	0	At the next interaction.
interaction-workspace	expression.callable- phone-number	No default value	When the application is started or restarted
interaction-workspace	expression.email- address	\w+([-+.]\w+)*@\w+([- .]\w+)*\.\w+([]\w+)*	At the next interaction.
interaction-workspace	expression.outbound- campaign-phone- number	^[\(\)\-\.\+\d\ s*#]*[\d]+[\(\)\-\.\+\d\ s*#/]*\$	At the next interaction.
interaction-workspace	expression.phone- number	(?:(?:[\+]?([\d]{1,3}(?:[]* [\-	At the next interaction.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
		.])))?[(]?([\d]{1,3})[\- /)]?(?:[]+ [\- .])?)?([\d]{5,})	
interaction-workspace	expression.phone- number.supported- characters	0123456789#*	At the next interaction.
interaction-workspace	expression.team- communicator-phone- number	^[\(\)\-\.\+\d\ s*#]*[\d]+[\(\)\-\.\+\d\ s*#/]*\$	At the next use of Team Communicator.
interaction-workspace	expression.url	See description.	At the next interaction.
interaction-workspace	gadget- statistics.displayed-call- center-statistics		Immediately.
interaction-workspace	gadget- statistics.displayed-kpis		Immediately.
interaction-workspace	gadget-statistics.nb- tagged-stats-per-page	5	When the application is started or restarted.
interaction-workspace	gadget-statistics.show	true	When the application is started or restarted.
interaction-workspace	gadget.window-title	\$Window.Title\$	Immediately.
interaction-workspace	general.configuration- agent-collection- loading-method	read-objects	When the application is started or restarted.
interaction-workspace	general.configuration- business-attribute- cache-preload	No default value	When the application is started or restarted.
interaction-workspace	general.configuration- business-attribute- folder-cache-preload	No default value	When the application is started or restarted.
interaction-workspace	general.configuration- object-collection-cache- timeout	0	When the application is started or restarted.
interaction-workspace	general.configuration- transaction-cache- preload		When the application is started or restarted.
interaction-workspace	general.configuration- update-notification	All	When the application is started or restarted.
interaction-workspace	general.gad.attached- data	false	At the next interaction.
interaction-workspace	general.non-unicode- connection-encoding		When the application is started or restarted
interaction-workspace	general.writable- downloaded- attachment-file-types	No default value	At next attachment download.
interaction-workspace	gui.editor-zoom-range	100	When the application is
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
			started or restarted.
interaction-workspace	gui.emoji-font-name	Segoe UI	At the next interaction.
interaction-workspace	gui.magnification-factor	normal	When the application is started or restarted.
interaction-workspace	gui.themes	Default,HighContrast,Blue	When the application is Royale Fancy started.
interaction-workspace	im.agent.prompt-color	#FF2E6599	Immediately.
interaction-workspace	im.agent.text-color	#FF3D464D	Immediately.
interaction-workspace	im.auto-answer	false	When the application is started or restarted.
interaction-workspace	im.new-message-bell		Immediately
interaction-workspace	im.other-agent.prompt- color	#FF295B00	Immediately.
interaction-workspace	im.other-agent.text- color	#FF3D464D	Immediately.
interaction-workspace	im.prompt-for-end	false	At the next interaction.
interaction-workspace	im.ringing-bell	Sounds\ Ring.mp3 10 -1 primary	At the next interaction.
interaction-workspace	im.simple-transcript	false	Immediately
interaction-workspace	im.system.text-color	#FF8C8C8C	Immediately.
interaction-workspace	im.time-stamp	true	Immediately.
interaction-workspace	im.toast-timeout	10	At the next interaction.
interaction-workspace	interaction.auto-focus	true	When the application is started or restarted.
interaction-workspace	interaction.auto- focus. <media-type></media-type>	true	When the application is started or restarted.
interaction-workspace	interaction-bar.allows- floating-transparency	true	When the application is started or restarted.
interaction-workspace	interaction-bar.detail- tooltip.max-height	164	Immediately.
interaction-workspace	interaction-bar.enable- quick-access	true	When application is started or restarted.
interaction-workspace	interaction-bar.quick- access-auto-open	true	When the application is started or restarted.
interaction-workspace	interaction-bar.quick- access-auto- open. <media-type></media-type>	true	When the application is started or restarted.
interaction-workspace	interaction-bar.quick- access-modes	Pinned,Floating	At the next interaction.
interaction-workspace	interaction-bar.quick- access-modes. <media- type></media- 	Pinned,Floating	At the next interaction.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	interaction.case- data.content	History,CaseData	At the next interaction.
interaction-workspace	interaction.case- data.email.mandatory- actions	Transfer, Forward	The next time an agent transfers and/or forwards an e-mail interaction.
interaction-workspace	interaction.case- data.enable-url-preview	false	At the next interaction.
interaction-workspace	interaction.case- data.format-business- attribute		At the next interaction
interaction-workspace	interaction.case- data.frame-color	#FF17849D	At the next interaction.
interaction-workspace	interaction.case- data.header-foreground- color	#FFFFFFF	At the next interaction.
interaction-workspace	interaction.case-data.is-read-only-on-idle	true	At the next interaction.
interaction-workspace	interaction.case- data. <media- type>.mandatory- actions</media- 		At the next interaction.
interaction-workspace	interaction.consult-user- data	public	Immediately.
interaction-workspace	interaction.disposition.dis mode	o <mark>lay-</mark> tree-view	When the application is started or restarted.
interaction-workspace	interaction.disposition.em actions	ail.mandatory-	At the next interaction.
interaction-workspace	interaction.disposition.is- mandatory	false	Immediately.
interaction-workspace	interaction.disposition.is-read-only-on-idle	false	Immediately.
interaction-workspace	interaction.disposition.key name	DispositionCode	Immediately.
interaction-workspace	interaction.disposition.use attached-data		Immediately.
interaction-workspace	interaction.disposition.use connection-id		Immediately.
interaction-workspace	interaction.disposition.val business-attribute	u <mark>e</mark> - DispositionCode	Immediately.
interaction-workspace	interaction.disposition. <m type>.mandatory- actions</m 	ledia-	At the next interaction.
interaction-workspace	interaction.evaluate- real-party-for-agent	true	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	interaction.evaluate- real-party-for- agent.expression	.*	When the application is started or restarted.
interaction-workspace	interaction- management.available- interaction-page-sizes	5,10,25,50	When the application is started or restarted.
interaction-workspace	interaction- management.filters		When the application is started or restarted.
interaction-workspace	interaction- management.interactions- filter.displayed-columns	- From,To,Subject,Received	When the application is started or restarted.
interaction-workspace	interaction- management.snapshot- timeout-delay	10	Immediately
interaction-workspace	interaction.override- option-key	IW_OverrideOptions	At the next interaction.
interaction-workspace	interaction.reject-route		At the next interaction.
interaction-workspace	interaction.unconditional- force-close	false	Immediately
interaction-workspace	interaction.window.popup- topmost-z-order	true	At the next interaction if the value is changed to 'true', or when the application is started or restarted if the value is changed to 'false'.
interaction-workspace	interaction.window.show- case-interaction-panel- button	true	At the next interaction.
interaction-workspace	interaction.window.show-in-taskbar	true	At the next interaction.
interaction-workspace	interaction.window-title	See the Description.	When the application is started or restarted.
interaction-workspace	interactions.window.allows transparency-on-winos6	false	At the next interaction.
interaction-workspace	intercommunication.chat.c	conference.invite-	At the next interaction.
interaction-workspace	intercommunication.chat.c	queue	At the next interaction.
interaction-workspace	intercommunication.chat.r based-actions	outing-	At the next interaction.
interaction-workspace	intercommunication.chat.r based-targets	routing-	At the next interaction.
interaction-workspace	intercommunication.email	.queue	At the next interaction.
interaction-workspace	intercommunication.email based-actions	.routing-	At the next interaction.
interaction-workspace	intercommunication.email	.routing-	At the next interaction.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
	based-targets		
interaction-workspace	intercommunication.im.ro based-actions	uting- MakeIM	When the application is started or restarted.
interaction-workspace	intercommunication.im.ro based-targets	uting-	At the next interaction.
interaction-workspace	intercommunication.im.ro points	uting-	At the next interaction.
interaction-workspace	intercommunication.sms.c		At the next interaction.
interaction-workspace	intercommunication.sms.r based-actions	outing- OneStepTransfer	At the next interaction.
interaction-workspace	intercommunication.sms.r based-targets	outing-	At the next interaction.
interaction-workspace	intercommunication.voice based-actions	routing- Makecall,OneStepConfere	en Ale,thicCoexteircoecce;Cioe Ste
interaction-workspace	intercommunication.voice based-targets	routing-	At the next interaction.
interaction-workspace	intercommunication.voice points	routing-	At the next interaction.
interaction-workspace	intercommunication.voice target-types	mail enabled Agent, Agent Group	Immediately
interaction-workspace	intercommunication.voice points	<mark>mail.routing</mark> - No default value	Immediately
interaction-workspace	intercommunication. <med type="">.queue</med>	dia-	At the next interaction.
interaction-workspace	intercommunication. <med type>.routing-based- actions</med 	dia-	At the next interaction.
interaction-workspace	intercommunication. <med type>.routing-based- targets</med 	dia-	At the next interaction.
interaction-workspace	keyboard.hotkey.agent- not-ready		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.agent- not-ready-with- reason. <action-code></action-code>		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.agent- ready		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.decrease microphone-volume- active-sip-call	-	When the application is started or restarted.
interaction-workspace	keyboard.hotkey.decrease speaker-volume-active- sip-call	-	When the application is started or restarted.
interaction-workspace	keyboard.hotkey.hold-		When the application is
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
	active-call		started or restarted.
interaction-workspace	keyboard.hotkey.increase- microphone-volume- active-sip-call		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.increase- speaker-volume-active- sip-call		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.mute- microphone-active-sip- call		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.mute- speaker-active-sip-call		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.release- active-call		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.toaster.a	ccept	When the application is started or restarted.
interaction-workspace	keyboard.hotkey.toaster.d	ecline	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.action.l		When the application is started or restarted.
interaction-workspace	keyboard.shortcut.campai record	<mark>9P.get</mark> -Shift+R	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.contact	:.@sslgr/Acontact	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.contact	r@ts elt R	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.contact	Satvlet S	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.hambu	rger.open	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interactattachments	tion.chat.add-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interact	tion.chat.conference	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interact	tion.chat.end	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interact	ti lvo. defa.luktiv atue	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interact	tion.chat.transfer	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interact	tion.consult	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interactattachments	tion.email.add-	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	keyboard.shortcut.interac	tion.email.cancelforward	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.email.completeforward	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.email.delete	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.email.forward	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interactors	tion.email.inline-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac send	tion.email.interim-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac		When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac back-to-origin-queue	tion email put- Ctrl+Shift+B	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	ti © ttr enR ail.reply	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion email reply- Ctrl+Shift+Aly-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	ti © tr en Sail.save	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interacin-workbin	tion email save- Ctrl+Shift+W	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	ti G tr enRei tusend	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.email.transfer	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	ti © ttrlmDelease	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interacdone	tion mark-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac record	tion.preview.call-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac record	tion.preview.cancel-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interacdone	tion.preview.mark-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac done-get-next	tion preview.mark-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac record	tion.preview.reject-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac preview.mark-done	tion.pull-	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	keyboard.shortcut.interac preview.mark-done-get- next	tion.pull-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.sms.delete	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.sms.transfer	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.voice.answer-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.voice.hold-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac recording-call	tion.voice.pause-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.voice.reconnect-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion voice release-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.voice.resume-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac recording-call	tion.voice.resume-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac step-conference	tion.voice.single-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac step-transfer	tion.voice.single-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac recording-call	tion.voice.start-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac recording-call	tion.voice.stop-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac contact	tion.webcallback.call-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.webcallback.mark-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac to-workbin	tion.workitem.move-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac back-to-origin-queue	tion.workitem.put-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.workitem.transfer	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.state.ld	og6trt+Alt+X	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.state.n ready	<mark>ot</mark> Čtrl+Alt+N	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.state.n	otCtrl+Alt+Z	When the application is
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
	ready-after-call-work		started or restarted.
interaction-workspace	keyboard.shortcut.state.re	eacty I+Alt+R	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.team- communicator.focus	No default value	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.teamle	ad.chat.bargein	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.teamle monitoring	ad.chat.stop-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.teamle monitoring	ad.stop-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.teamle	ad.voice.bargein	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.teamle	ad.voice.coaching	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.teamle	ad.voice.monitor	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.teamle monitoring	ad.voice.stop-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.toaster	.aCtr dp tG	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.toaster	. detali + M	When the application is started or restarted.
interaction-workspace	kpi.displayed-kpis		Immediately.
interaction-workspace	kpi.refresh-time	10	When the application is started or restarted.
interaction-workspace	kpi.show-agent-groups	true	When the application is started or restarted.
interaction-workspace	license.lrm-enabled	false	When the application is started or restarted.
interaction-workspace	log.default-filter-type	Сору	Immediately.
interaction-workspace	log.ESDK	All	Immediately.
interaction-workspace	log.expire	10	Immediately.
interaction-workspace	log.filter- data. <keyname></keyname>	Сору	Immediately.
interaction-workspace	log.max-age	10	When the application is started or restarted.
interaction-workspace	log.PSDK	Standard	Immediately.
interaction-workspace	log.PSDK.SwitchPolicy	Standard	Immediately.
interaction-workspace	log.segment	10MB	When the application is started or restarted.
interaction-workspace	log.Trace	\$Application.RootApplicati	olmDrantedial beglyInteractionWor
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	log.verbose	Trace	Immediately.
interaction-workspace	login.available-place- groups		When the application is started or restarted.
interaction-workspace	login.chat.auto-not- ready-reason		When the application is started or restarted
interaction-workspace	login.chat.can- unactivate-channel	false	When the application is started or restarted.
interaction-workspace	login.chat.is-auto-ready	false	When the application is started or restarted.
interaction-workspace	login.default-place		When the application is started or restarted.
interaction-workspace	login.email.auto-not- ready-reason		When the application is started or restarted
interaction-workspace	login.email.can- unactivate-channel	false	When the application is started or restarted.
interaction-workspace	login.email.is-auto- ready	false	When the application is started or restarted.
interaction-workspace	login.enable-login- without-channel	true	When the application is started or restarted.
interaction-workspace	login.enable-place- completion	true	When the application is started or restarted.
interaction-workspace	login.enable-same- agent-place	true	When the application is started or restarted.
interaction-workspace	login.im.auto-not-ready- reason		When the application is started or restarted
interaction-workspace	login.im.available- queues	ACDQueue	When the application is started or restarted.
interaction-workspace	login.im.can-unactivate- channel	false	When the application is started or restarted
interaction-workspace	login.im.is-auto-ready	false	When the application is started or restarted
interaction-workspace	login.im.prompt-agent- login-id	false	When the application is started or restarted.
interaction-workspace	login.im.prompt-dn- password	false	When the application is started or restarted.
interaction-workspace	login.im.prompt-queue	false	When the application is started or restarted.
interaction-workspace	login.place-location- source	standard	When the application is started or restarted.
interaction-workspace	login.place-selection- type	Place	When the application is started or restarted.
interaction-workspace	login.place-state- timeout	30	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	login.prompt-place	false	When the application is started or restarted.
interaction-workspace	login.sip-cluster.phone- number		When the application is started or restarted.
interaction-workspace	login.sip-cluster.store- recent-phone-number	true	When the application is started or restarted.
interaction-workspace	login.sms.auto-not- ready-reason		When the application is started or restarted
interaction-workspace	login.sms.can- unactivate-channel	false	When the application is started or restarted.
interaction-workspace	login.sms.is-auto-ready	false	When the application is started or restarted.
interaction-workspace	login.store-recent-place	true	When the application is started or restarted.
interaction-workspace	login.store-username	true	When the application is started or restarted.
interaction-workspace	login.voice.auto-not- ready-reason		When the application is started or restarted
interaction-workspace	login.voice.available- queues	ACDQueue	When the application is started or restarted.
interaction-workspace	login.voice.can- unactivate-channel	false	When the application is started or restarted
interaction-workspace	login.voice.force-relogin	false	When the application is started or restarted
interaction-workspace	login.voice.is-auto-ready	false	When the application is started or restarted
interaction-workspace	login.voice.prompt- agent-login-id	false	At the next interaction
interaction-workspace	login.voice.prompt-dn- less-phone-number	false	When the application is started or restarted.
interaction-workspace	login.voice.prompt-dn- password	false	When the application is started or restarted.
interaction-workspace	login.voice.prompt- queue	true	When the application is started or restarted.
interaction-workspace	login.voice.restore-dn- less-phone-number-on- logout	true	When the application is started or restarted
interaction-workspace	login.voice.use-dn-less- login-extension	false	At next voice channel login.
interaction-workspace	login.webcallback.auto- not-ready-reason		When the application is started or restarted
interaction-workspace	login.webcallback.can- unactivate-channel	false	When the application is started or restarted.
interaction-workspace	login.webcallback.is-	false	When the application is
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
	auto-ready		started or restarted.
interaction-workspace	login.workmode	unknown	When the application is started or restarted or if the agent changes place.
interaction-workspace	login. <media- type>.auto-not-ready- reason</media- 	false	When the application is started or restarted.
interaction-workspace	login. <media- type>.can-unactivate- channel</media- 	false	When the application is started or restarted.
interaction-workspace	login. <media-type>.is- auto-ready</media-type>	false	When the application is started or restarted.
interaction-workspace	logout.enable-exit-on- logoff-error	true	When the application is started or restarted.
interaction-workspace	logout.voice.use-login- queue-on-logout	true	When the application is started or restarted.
interaction-workspace	main-window.auto-hide- display-delay	0	At the next interaction.
interaction-workspace	main-window.bypass- auto-hide-conditions	false	When the application is started or restarted.
interaction-workspace	main-window.window- title	\$Window.Title\$	Immediately.
interaction-workspace	openmedia.bundle.sms	sms,smssession	When the application is started or restarted.
interaction-workspace	openmedia.workitem- channels		When the application is started or restarted.
interaction-workspace	options.clean-up-former- record-location	false	When the application is started or restarted.
interaction-workspace	options.record-location		When the application is started or restarted.
interaction-workspace	options.record-option- locally-only	false	When the application is started or restarted.
interaction-workspace	outbound.assured- connection.allow- release-engaging-call- timeout	-1	When the application is started or restarted.
interaction-workspace	outbound.call-result- automatically-selected		At the next interaction.
interaction-workspace	outbound.call-result-is- mandatory	false	Immediatly.
interaction-workspace	outbound.call-result- values	Answered,AnsweringMach	ninAt, Blusyn, AktAinterran; tMonong N
interaction-workspace	outbound- callback.ringing-bell	Sounds\ Ring.mp3 10 -1 primary	At the next interaction.

Section	Option	Default	Changes Take Effect
interaction-workspace	outbound.callback-types	personal,campaign	At the next interaction.
interaction-workspace	outbound.campaign- stale-timeout	0	When the application is started or restarted.
interaction-workspace	outbound.complete- record-before-transfer	false	At the next transfer attempt.
interaction-workspace	outbound.fields.float- separator-in-db		Immediately.
interaction-workspace	outbound.load-at- startup	false	When the application is started or restarted.
interaction-workspace	outbound.push- preview.auto-answer	false	At the next interaction.
interaction-workspace	outbound.push- preview.auto- answer.enable-reject	false	At the next interaction.
interaction-workspace	outbound.push- preview.auto- answer.timer	0	At the next interaction.
interaction-workspace	outbound.push- preview.media-types	outboundpreview	When the application is started or restarted.
interaction-workspace	outbound.push- preview.use-combined- channel	true	When the application is started or restarted.
interaction-workspace	outbound.record- information.frame-color	#FF17849D	At the next interaction.
interaction-workspace	outbound.record- information.header- foreground-color	#FFFFFFF	At the next interaction.
interaction-workspace	outbound.reschedule- inherit-parent- availability-interval	false	When the application is started or restarted.
interaction-workspace	outbound.sound.campaigr updated	า-	At the next interaction.
interaction-workspace	outbound.timed- preview-auto-dial	-1	At the next interaction.
interaction-workspace	outbound.treatment- mode	none	Immediately.
interaction-workspace	presence.evaluate- presence	true	When the application is started or restarted.
interaction-workspace	printing.use-print- preview	true	Immediately.
interaction-workspace	reporting.case.report- case-in-focus-duration	false	When the application is started or restarted.
interaction-workspace	screen- recording.client.address		When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	screen- recording.client.max- attempts	5	When the application is started or restarted.
interaction-workspace	screen- recording.client.ping- interval	10000	When the application is started or restarted.
interaction-workspace	screen- recording.client.port	443	When the application is started or restarted.
interaction-workspace	screen- recording.client.secure- connection	true	When the application is started or restarted.
interaction-workspace	screen- recording.htcc.peer_uri		When the application is started or restarted.
interaction-workspace	screen- recording.htcc.uri		When the application is started or restarted.
interaction-workspace	security.client- authentication- certificate-search-value	A string value or one of the supported field codes, Workspace uses to select a certificate.	When the application is started or restarted.
interaction-workspace	security.disable-rbac	false	When the application is started or restarted.
interaction-workspace	security.enable-debug- information	false	Immediately.
interaction-workspace	security.inactivity-force- not-ready-state	false	When the application is started or restarted.
interaction-workspace	security.inactivity-not- ready-reason		When the application is started or restarted.
interaction-workspace	security.inactivity-set- agent-not-ready	true	When the application is started or restarted.
interaction-workspace	security.inactivity- timeout	0	When the application is started or restarted.
interaction-workspace	security.session-lock- force-not-ready-state	false	When the application is started or restarted.
interaction-workspace	security.session-lock- not-ready-reason	No default value	When the application is started or restarted.
interaction-workspace	security.session-lock- set-agent-not-ready	false	When the application is started or restarted.
interaction-workspace	sip-cluster.data-center- locations		When the application is started or restarted.
interaction-workspace	sip-cluster.reconnect-timeout	10	Immediatly.
interaction-workspace	sipendpoint.authenticate- with-dn-password	false	At next Log Off operation or at next login.
interaction-workspace	sipendpoint.codecs.g729/	-	When the application is
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
	8000.fmtp		started or restarted.
interaction-workspace	sipendpoint.codecs.h264.	fnptrpfile-level-id=420028	When the application is started or restarted.
interaction-workspace	sipendpoint.core- deadlock-detection- delay	12500	When the application is started or restarted.
interaction-workspace	sipendpoint.enable-ipv6	auto	When the application is started or restarted.
interaction-workspace	sipendpoint.exit-on- voice-logoff	false	At next Log Off operation or at next login.
interaction-workspace	sipendpoint.headset- enforce-configured- usage	false	When the application is started or restarted.
interaction-workspace	sipendpoint.headset- replugged-set-ready	true	When the application is started or restarted.
interaction-workspace	sipendpoint.headset- unplugged.not-ready- reason		When the application is started or restarted.
interaction-workspace	sipendpoint.headset- unplugged-set-not- ready	true	When the application is started or restarted.
interaction-workspace	sipendpoint.init- attempt-nb	10	When the application is started or restarted.
interaction-workspace	sipendpoint.init- attempt-timer	1	When the application is started or restarted.
interaction-workspace	sipendpoint.ip-version	auto	When the application is started or restarted.
interaction-workspace	sipendpoint.log.expire	10	When the application is started or restarted.
interaction-workspace	sipendpoint.log.segment	10MB	When the application is started or restarted.
interaction-workspace	sipendpoint.log.verbose	Trace	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.device.	audio_in_device	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.device.	audio_out_device	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.device.	capture_device	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.device.	headset_name	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.device.	ude_headset	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	sipendpoint.policy.endpoi	nt 200 fer_device_release	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.endpoi	nt@nclude_mac_address	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.endpoi	Empty string which is nttplholequiddless to the \$auto value.	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.endpoi	nt3@p_inactivity_timeout	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.endpoi	nt999 <u>9</u> port_max	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.endpoi	nt9 @ port_min	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.endpoi	nt5 0β<u>0</u>port_ma x	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.endpoi	nt5 06<u>0</u>port_min	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.endpoi	nt0tcp_port_max	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.endpoi	nt@cp_port_min	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.endpoi	nt1⁄000o_max_bitrate	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.endpoi	nt0webrtc_audio_layer	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.session	.algc_mode	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.session	.auto_accept_video	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.session	.auto_answer	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.session	.dfa2f88ethod	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.session	.dtx_mode	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.session	.etho_control	Immediately.
interaction-workspace	sipendpoint.policy.session	.roise_suppression	Immediately.
interaction-workspace	sipendpoint.policy.session	.r@ject_session_when_head	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.session	.r 0 ngback_enabled	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.session	.ringback_file	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	sipendpoint.policy.session	.rQ_agc_mode	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.session	.s48_0code_when_headset_na	When the application is started or restarted.
interaction-workspace	sipendpoint.policy.session	.Vad_level	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	0.domain	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	O.Mat.ice_enabled	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	0.nat.stun_server	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	034ሺ&tun_server_port	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	0.nat.turn_password	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	O.Mat.turn_relay_type	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	0.nat.turn_server	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	0 34a ሺ & urn_server_port	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	0.nat.turn_user_name	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	030g_interval	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	0.0eg_match_received_rport	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	0.18 <u>90</u> timeout	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	1.domain	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	1.domain	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	1.Mat.ice_enabled	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	1.nat.stun_server	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	13478tun_server_port	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	1.nat.turn_password	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	1Mat.turn_relay_type	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	sipendpoint.proxies.proxy	1.nat.turn_server	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	13478urn_server_port	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	1.nat.turn_user_name	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	130g_interval	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	1.0eg_match_received_rport	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	1.18 <u>9.0</u> timeout	When the application is started or restarted.
interaction-workspace	sipendpoint.retain- volume-settings- between-sessions	false	When the application is started or restarted.
interaction-workspace	sipendpoint.sbc- register-address		When the application is started or restarted.
interaction-workspace	sipendpoint.sbc- register-address.peer		When the application is started or restarted.
interaction-workspace	sipendpoint.sbc- register-port		When the application is started or restarted.
interaction-workspace	sipendpoint.sbc- register-port.peer		When the application is started or restarted.
interaction-workspace	sipendpoint.standalone.ce search-value	ertificate-	When the application is started or restarted.
interaction-workspace	sipendpoint.standalone.pd	or8000	When the application is started or restarted.
interaction-workspace	sipendpoint.standalone.pr	otocol	When the application is started or restarted.
interaction-workspace	sipendpoint.standalone.se level	curity-	When the application is started or restarted.
interaction-workspace	sipendpoint.standalone.su criteria	bject-	At next application start.
interaction-workspace	sipendpoint.standalone.su matching-properties		When the application is started or restarted.
interaction-workspace	sipendpoint.standalone.vo detection-model		When the application is started or restarted.
interaction-workspace	sipendpoint.standalone.vo detection-use-dns	li- true	When the application is started or restarted.
interaction-workspace	sipendpoint.system.diagno	ostics.enable_logging	When the application is started or restarted.
interaction-workspace	sipendpoint.system.diagno	ostics.log_filter	When the application is started or restarted.
interaction-workspace	sipendpoint.system.diagno	o g tics.log_level	When the application is
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
			started or restarted.
interaction-workspace	sipendpoint.system.diagn	gsip=2 ostics.log options provider webrtc=(warning)	When the application is started or restarted.
interaction-workspace	sipendpoint.system.securi	ity.cert_file	When the application is started or restarted.
interaction-workspace	sipendpoint.system.securi	itØtls_enabled	When the application is started or restarted.
interaction-workspace	sipendpoint.system.securi	itoptie <u>n</u> atp	When the application is started or restarted.
interaction-workspace	sipendpoint.transport- protocol	UDP	When the application is started or restarted.
interaction-workspace	sipendpoint.video.always- on-top	true	When the application is started or restarted.
interaction-workspace	sipendpoint.video.auto- activate	true	When the application is started or restarted.
interaction-workspace	sipendpoint.video.camera frame-rate	30	When the application is started or restarted.
interaction-workspace	sipendpoint.video.camera frame-size	352x288	When the application is started or restarted.
interaction-workspace	sipendpoint.video.camera render-format	6	When the application is started or restarted.
interaction-workspace	sipendpoint.video.thumbn ratio	aij. ₂₅	When the application is started or restarted.
interaction-workspace	sms.agent.prompt-color	#FF2E6599	Immediately.
interaction-workspace	sms.agent.text-color	#FF3D464D	Immediately.
interaction-workspace	sms.auto-answer	false	At the next interaction.
interaction-workspace	sms.auto- answer.enable-reject	false	At the next interaction.
interaction-workspace	sms.auto-answer.timer	0	At the next interaction.
interaction-workspace	sms.client.prompt-color	#FFAF4F0B	Immediately.
interaction-workspace	sms.client.text-color	#FF3D464D	Immediately.
interaction-workspace	sms.default-queue		At the next interaction.
interaction-workspace	sms.from-numbers- business-attribute		At the next interaction.
interaction-workspace	sms.max-message- number	8	At the next interaction.
interaction-workspace	sms.other- agent.prompt-color	#FF295B00	Immediately.
interaction-workspace	sms.other-agent.text- color	#FF3D464D	Immediately.
interaction-workspace	sms.outbound-queue		Immediately.
interaction-workspace	sms.prompt-for-done	false	At the next interaction.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	sms.ringing-bell	Sounds\ Ring.mp3 10 -1 primary	At the next interaction.
interaction-workspace	sms.simple-transcript	false	Immediately
interaction-workspace	sms.subject-max-chars	25	At the next interaction.
interaction-workspace	sms.system.text-color	#FF8C8C8C	Immediately
interaction-workspace	sms.time-stamp	true	Immediately.
interaction-workspace	sms.transcript-enable- history-filters	false	At the next interaction.
interaction-workspace	sms.transcript-time- frame	24	At the next interaction.
interaction-workspace	sounds.preloadfiles	Sounds\Ring.mp3	When the application is started or restarted
interaction-workspace	spellchecker.chat.prompt- on-send	false	At the next interaction.
interaction-workspace	spellchecker.corporate- dictionary		When the application is started or restarted.
interaction-workspace	spellchecker.corporate- dictionary-file		When the application is started or restarted.
interaction-workspace	spellchecker.email.prompt on-send	false	At the next interaction.
interaction-workspace	spellchecker.im.prompt- on-send	false	At the next interaction.
interaction-workspace	spellchecker.sms.prompt- on-send	false	At the next interaction.
interaction-workspace	spellchecker. <media- type>.prompt-on-send</media- 	false	At the next interaction.
interaction-workspace	standard-response.auto- append-star-to-search	true	At the next search.
interaction-workspace	standard- response.categories	\$AII\$	At the next interaction.
interaction-workspace	standard- response.default- search-type	AnyKeyword	At the next interaction.
interaction-workspace	standard- response.enable-usage- feedback	true	At the next interaction.
interaction-workspace	standard- response.field. <customfie< td=""><td>eldCode></td><td>At the next interaction.</td></customfie<>	eldCode>	At the next interaction.
interaction-workspace	standard- response.languages	\$AII\$	At the next interaction.
interaction-workspace	standard- response.shortcuts. <keyw< td=""><td>No default value</td><td>At the next interaction.</td></keyw<>	No default value	At the next interaction.
interaction-workspace	standard-	50	At the next interaction.
Section	Option	Default	Changes Take Effect

	Option	Default	Changes Take Effect	
	response.suggested- responses-min- relevancy			
interaction-workspace	statistics.displayed- statistics		Immediately.	
interaction-workspace	statistics.queues		Immediately.	
interaction-workspace	statistics.refresh-time	10	When the application is started or restarted.	
interaction-workspace	statistics.routing-points		Immediately.	
interaction-workspace	system-tray.tooltip	\$Application.Title\$	When the application is started or restarted.	
interaction-workspace	teamcommunicator.add- recent-filters.voice		At next interaction event.	
interaction-workspace	teamcommunicator.alway clear-textbox-on-new- interaction	s- true	Immediately.	
interaction-workspace	teamcommunicator.contactary	Category, First Name, Last N	When the application is lame Phone Number EmailAd started or restarted.	ddress
interaction-workspace	teamcommunicator.corpor	rate-	When the application is started or restarted.	
interaction-workspace	teamcommunicator.corpor	rate-	When the application is started or restarted.	
interaction-workspace	teamcommunicator.custor favorite-fields	ⁿ Category,FirstName,LastN	When the application is lame Phone Number EmailAd started or restarted.	ddress
interaction-workspace	teamcommunicator.intera queue-presence-metrics	presence	When the application is started or restarted.	
interaction-workspace	teamcommunicator.intern favorite-fields	al Category,DisplayName	When the application is started or restarted.	
interaction-workspace	teamcommunicator.list-filter-showing	Agent,AgentGroup,Skill,Rd	When the application is puting Point Obeue Interaction started or restarted.	onQueue,Cont
interaction-workspace	teamcommunicator.list- status-reachable	NotReady	When the application is started or restarted.	
interaction-workspace	teamcommunicator.load- at-startup	true	When the application is started or restarted.	
interaction-workspace	teamcommunicator.max-favorites-size	50	When the application is started or restarted.	
interaction-workspace	teamcommunicator.max- suggestion-size	10	When the application is started or restarted.	
interaction-workspace	teamcommunicator.queue presence-metrics	queue-presence	When the application is started or restarted.	
interaction-workspace	teamcommunicator.recent max-records		When the application is started or restarted.	
interaction-workspace	teamcommunicator.reque start-timer	st 300	When the application is started or restarted.	
Section	Option	Default	Changes Take Effect	

Section	Option	Default	Changes Take Effect	
interaction-workspace	teamcommunicator.routing	^g -routing-point-presence	When the application is started or restarted.	
interaction-workspace	teamlead.agent- status.enabled-agent- group-security-mode	true	At next agent search.	
interaction-workspace	teamlead.agent- status.enabled-remote- actions	Ready, NotReady, LogOff	At the next agent search.	
interaction-workspace	teamlead.monitoring- scope	call	Immediately.	
interaction-workspace	toast.case-data.content	History,CaseData	At the next interaction.	
interaction-workspace	toast.case-data.format- business-attribute		At the next interaction	
interaction-workspace	toast.window-title	(\$Contact.FirstName\$ \$Contact.LastName\$ \$Inte - \$Window.Title\$	e rlandinædi⊠læih Party\$)	
interaction-workspace	views.CaseContactRegion order	activate. InteractionContactInforma	When the views are tionview interaction contactions are instantiated.	tHistoryView
interaction-workspace	views.CaseContactRegion.	.drteractionContactInforma	When the views are tionView interactionContactionStantiated.	tHistoryView
interaction-workspace	views.CaseViewSideButtor	n Retgicarcticah © ontainer Side B	When the views are uttonV uttonView SRLSideButtonV instantiated.	iew
interaction-workspace	views.ContactInfoHistoryNorder	<mark>lultiRegion activate-</mark> ContactinformationView,C	When the views are ontact-listory view instantiated.	
interaction-workspace	views.ContactInfoHistoryN	l LC to R tag i blin for dea tion View, C	When the views are ontact listory view instantiated.	
interaction-workspace	views.ContactTabBottomH order	istoryMultiRegion activate- ContactDetailView,Contac	When the views are thistoryNotepadView,Containstantiated.	ctHistoryCas
interaction-workspace	views.ContactTabBottomH	istont Mat Dietaj Noire wr, Contac	When the views are thistoryNotepadView,Containstantiated.	ctHistoryCas
interaction-workspace	views.InteractionDetailsRe order	e <mark>gion activate</mark> NotepadVoiceNotepadViev	When the views are w.Dispositions view instantiated.	
interaction-workspace	views.InteractionDetailsRe	<mark>gDisposiltio</mark> nsView,Notepad	When the views are VoiceNotepadView Instantiated.	
interaction-workspace	views.ToolbarWorkplaceRe order	e <mark>gion activate</mark> MyPlaceStatusView,myCa	When the views are mpaigns List View, My Contac instantiated.	tHistory,MyS
interaction-workspace	views.ToolbarWorkplaceRe	gwyPlarclesstatusView,myCa	When the views are mpaigns list view, My Contac instantiated.	tHistory,MyS
interaction-workspace	views.ToolbarWorksheetBu	utMy/MediphaoeBerttonView,I	When the views are Main foolbar workbins Contail instantiated.	nerButtonVie
interaction-workspace	views.WorkbinsTabBottom order	HistoryMultiRegion activate ContactDetailView,Contac	When the views are thistory Notepad View, Conta instantiated.	octHistoryCas
interaction-workspace	views.WorkbinsTabBottom	HCdotyMDletadyiewcCdetac	When the views are this tory Notepad View, Containstantiated.	nctHistoryCas
Section	Option	Default	Changes Take Effect	

Section	Option	Default	Changes Take Effect
interaction-workspace	voice.after-call-work- extension	untimed	Immediately
interaction-workspace	voice.auto-answer	false	At the next interaction.
interaction-workspace	voice.auto- answer.enable-reject	false	At the next interaction.
interaction-workspace	voice.auto-answer.timer	0	At the next interaction.
interaction-workspace	voice.cancel-after-call- work-on-done	false	Immediately.
interaction-workspace	voice.complete- conference-requires- connected-consultation- call	false	At the next interaction.
interaction-workspace	voice.device-type	auto	When the application is started or restarted.
interaction-workspace	voice.dtmf-inactivity- typing-timeout	500	At the next interaction.
interaction-workspace	voice.enable-agent- reservation	false	When the applicationis started or restarted.
interaction-workspace	voice.enable-init- conference	false	At the next interaction.
interaction-workspace	voice.end-consultation- method	reconnect	At the next interaction.
interaction-workspace	voice.hold-indicator- timer	30,60	At the next interaction.
interaction-workspace	voice.hot- standby.backup-retry- delay	40	When the application is started or restarted.
interaction-workspace	voice.hybrid-switch- preference	No default value	When the application is started or restarted.
interaction-workspace	voice.mark-done-on- release	false	At the next interaction.
interaction-workspace	voice.nb-max- independent-calls	0	When the application is started or restarted
interaction-workspace	voice.one-step-trsf- mode	default	When the application is started or restarted.
interaction-workspace	voice.prompt-for-end	false	At the next interaction.
interaction-workspace	voice.ringing-bell	Sounds\ Ring.mp3 10 -1 primary	At the next interaction.
interaction-workspace	voice.show-hold- duration	false	At the next interaction.
interaction-workspace	voice.show-post-call- duration	false	At the next interaction.
interaction-workspace	voice.sip-preview-bell		At the next interaction.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect	
interaction-workspace	voicemail.access- number		When the application is started or restarted.	
interaction-workspace	voicemail.notification- types	personal,public	At the next change of the counter that tracks the number of voicemail messages.	
interaction-workspace	warm- standby.reconnection- random-delay-range	2	When the application is started or restarted	
interaction-workspace	warm-standby.retry- delay	10	When the application is started or restarted	
interaction-workspace	webcallback.auto- answer	false	At the next interaction.	
interaction-workspace	webcallback.auto- answer.enable-reject	false	At the next interaction.	
interaction-workspace	webcallback.auto- answer.timer	0	At the next interaction.	
interaction-workspace	webcallback.auto-dial	false	At the next interaction.	
interaction-workspace	webcallback.callback- information.content	Subject,PhoneNumber,Typ	e AS dhechulexid Datter Actinta ctTi	me,Loca
interaction-workspace	webcallback.callback- information.frame-color	#FF17849D	At the next interaction.	
interaction-workspace	webcallback.callback- information.header- foreground-color	#FFFFFFF	At the next interaction.	
interaction-workspace	webcallback.complete- queue		Immediately.	
interaction-workspace	webcallback.park-queue		Immediately.	
interaction-workspace	webcallback.reschedule- queue		Immediately.	
interaction-workspace	webcallback.ringing-bell	Sounds\ Ring.mp3 10 -1 primary	At the next interaction.	
interaction-workspace	webproxy.address		At the next interaction.	
interaction-workspace	webproxy.password		At the next interaction.	
interaction-workspace	webproxy.username		At the next interaction.	
interaction-workspace	workbin.email.draft		When the application is started or restarted.	
interaction-workspace	workbin.email.draft.displa columns	y <mark>ed</mark> - To,Subject,Submitted	When the application is started or restarted.	
interaction-workspace	workbin.email.in- progress		When the application is started or restarted.	
interaction-workspace	workbin.email.in- progress.displayed- columns	From,Subject,Received	When the application is started or restarted.	
Section	Option	Default	Changes Take Effect	

Section	Option	Default	Changes Take Effect
interaction-workspace	workbin. <media- type>.<nick- name>.notify-property- changed</nick- </media- 	false	When the application is started or restarted.
interaction-workspace	workbin. <media- type>.<workbin- nickname></workbin- </media- 		When the application is started or restarted.
interaction-workspace	workbin. <media- type>.<workbin- nickname>.auto-update</workbin- </media- 	true	When the application is started or restarted.
interaction-workspace	workbin. <media- type>.<workbin- nickname>.displayed- columns</workbin- </media- 	From,To,Subject,Received	When the application is started or restarted.
interaction-workspace	workbin. <media- type>.<workbin- nickname>.max-results</workbin- </media- 	50	At next workbin refresh.
interaction-workspace	workbin. <media- type>.<workbin- nickname>.quick- search-attributes</workbin- </media- 		When the application is started or restarted.
interaction-workspace	workbin. <media- type>.in-progress</media- 		When the application is started or restarted.
interaction-workspace	workbin. <media- type>.in- progress.displayed- columns</media- 	From,To,Subject,Received	When the application is started or restarted.
interaction-workspace	workbin. <media_type>.in progress</media_type>	-	When the application is started or restarted.
interaction-workspace	workbin. <media_type>.in progress.displayed- columns</media_type>	- From,To,Subject,Receiv	When the application is started or restarted.
queue-presence	associated-object-ids	No default value	When the application is started or restarted
queue-presence	associated-statistic-type	No default value	When the application is started or restarted
queue-presence	error-level	10	When the application is started or restarted.
queue-presence	object-ids	No default value	When the application is started or restarted
queue-presence	statistic-name	CurrNumberWaitingCalls	When the application is started or restarted.
queue-presence	statistic-text	interaction(s) waiting.	When the application is started or restarted.
queue-presence	warning-level	5	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
routing-point-presence	associated-object-ids	No default value	When the application is started or restarted
routing-point-presence	associated-statistic-type	No default value	When the application is started or restarted
routing-point-presence	error-level	10	When the application is started or restarted.
routing-point-presence	object-ids	No default value	When the application is started or restarted
routing-point-presence	statistic-name	CurrNumberWaitingCalls	When the application is started or restarted.
routing-point-presence	statistic-text	interaction(s) waiting.	When the application is started or restarted.
routing-point-presence	warning-level	5	When the application is started or restarted.
TServer	multimedia	false	At the next interaction.
TServer	sip-signaling-chat	session	Immediately.
TServer	voice	true	At the next interaction.
Section	Option	Default	Changes Take Effect

interaction-workspace Section

These options can be configured on the following Configuration Layer objects:

- · Workspace Application object
- Tenant
- Agent Group
- User (Agent)

The options are grouped into categories. The Section interaction-workspace topic of the Workspace Deployment Guide breaks down the categories and provides a brief description of each.

The majority of Workspace configuration options are configured in the interaction-workspace section. This is a section that you create in the annex of the object to which you want to apply the option. Most of these options can be configured hierarchically at the Application, Tenant, Agent Group, or User level; some can be configured on other objects such as DNs, skills, and switches. For more information about using Workspace configuration options, refer to Introduction to Configuration Options.

The values specified for many options can also be overridden by Routing Strategies that reference Transaction objects.

Workspace options are grouped by functionality. The first word in the name of the option indicates the functional area to which the option belongs. For example, the option chat.emojis-business-attribute is part of the **chat** functionality group. It enables you to specify the name of the **business attribute** that contains the **emojis** that agents enabled for the Chat channel can use in the Chat window. The options are named to help you know quickly what the option does.

The *Workspace Deployment Guide* contains topics specific to configuring options as a group to manage each functional area. For example, you can read about setting up the Chat channel in the Chat topic.

- <media-type>.auto-answer
- <media-type>.autoanswer.enable-reject
- <media-type>.autoanswer.timer
- <media-type>.contacthistory.enable-combineinteraction-with-current
- <media-type>.contacthistory.enable-combine-ixnwith-current

- <media-type>.prompt-fordone
- <media-type>.pull-fromhistory-isenabled
- <media-type>.ringing-bell
- <media-type>.toastinformation-key
- accessibility.agent-statechange-bell
- · accessibility.disable-

hyperlinks

- accessibility.focus-oninteraction-toast
- accessibility.interaction-statechange-bell
- accessibility.visualimpairment-profile
- accessibility.warningmessage-bell
- · accessibility.<media-

- type>.focus-on-interaction-toast
- activerecording.voice.recorder-uri
- activerecording.voice.recorder-uri
- activerecording.voice.recordingtype
- agent-status.enabled-actionsby-channel
- agent-status.enabled-actionsglobal
- agent-status.not-readyreasons
- · alert.timeout
- · application.available-layouts
- application.secondary-audioout-device
- · application.wiki-help-locale
- application.wiki-helpwelcome-page
- · broadcast.color.high-priority
- broadcast.color.importantpriority
- broadcast.color.low-priority
- broadcast.color.minimalpriority
- broadcast.color.normalpriority
- broadcast.displayed-columns
- broadcast.dn
- · broadcast.enable-removal
- broadcast.enable-removalpriority
- · broadcast.mark-read-timeout
- broadcast.message-content
- broadcast.preview-timeout
- · broadcast.sound.high-priority
- broadcast.sound.importantpriority

- · broadcast.sound.low-priority
- broadcast.sound.minimalpriority
- broadcast.sound.normalpriority
- broadcast.subscribed.topics
- broadcast.system-messagesauto-mark-read
- · broadcast.toast-summary
- broadcast.value-businessattribute
- callback.callbackinformation.content
- callback.callbackinformation.frame-color
- callback.callbackinformation.headerforeground-color
- callback.callback-typesbusiness-attribute
- · callback.gms-url
- · callback.ringing-bell
- case-data.float-separator
- channel-information.windowtitle
- · chat.agent.prompt-color
- chat.agent.text-color
- chat.attachment-downloadtimeout
- · chat.auto-answer
- chat.auto-answer.enablereject
- · chat.auto-answer.timer
- chat.auto-mark-done-nonowner-agent
- chat.auto-mark-done-nonowner-agent.timer
- chat.auto-mark-done-owneragent
- chat.auto-mark-done-owneragent.timer

- chat.client.prompt-color
- chat.client.text-color
- chat.emojis-businessattribute
- · chat.enable-auto-disconnect
- · chat.historical.maximum-age
- · chat.max-attachments-files
- chat.max-attachments-size
- chat.max-file-size
- · chat.new-message-bell
- · chat.nickname
- · chat.on-hold-queue
- chat.other-agent.prompt-color
- chat.other-agent.text-color
- chat.pending-response-tocustomer
- chat.pending-response-tocustomer-bell
- · chat.prompt-for-end
- chat.reconnect-attempts
- chat.reconnect-timeout
- chat.restricted-attachmentfile-types
- · chat.rich-media-widget-width
- chat.ringing-bell
- chat.show-attachment-imagethumbnail
- chat.show-unread-notification
- chat.simple-transcript
- chat.system.text-color
- chat.time-stamp
- chat.toast-information-key
- chat.transcript-enablehistory-filters
- chat.transcript-message-textdirection
- · chat.typing-isenabled

- chat.typing-timeout
- chatserver.addp.local-timeout
- · chatserver.addp.remotetimeout
- · chatserver.addp.trace-mode
- chatserver.ip-version
- · chatserver.tls-mutual
- contact.all-interactionsdefault-time-filter-main
- contact.all-interactionsdisplayed-columns
- contact.all-interactionsdisplayed-columns-treeview
- contact.all-interactions-quicksearch-attributes
- · contact.available-directorypage-sizes
- contact.cache-timeout-delay
- contact.date-search-types
- contact.default-directorypage-size
- contact.directory-advanceddefault
- · contact.directory-autoappend-star-to-search
- contact.directory-defaultmode
- · contact.directory-displayedcolumns
- contact.directory-enabledmodes
- contact.directory-
- contact.directory-searchattributes
- contact.directory-searchtypes
- contact.displayed-attributes
- contact.editable-attributes
- contact.history-advanceddefault

- contact.history-auto-appendstar-to-search
- contact.history-customattribute-values. < attributename>
- contact.history-customattributes-search-types
- · contact.history-default-timefilter-main
- contact.history-displayedcolumns
- · contact.history-displayedcolumns-treeview
- · contact.history.filters-<attribute>
- · contact.history.highlightcurrent-interaction
- · contact.history.media-filters
- contact.history-quick-searchattributes
- contact.history-searchattribute-group. < groupname>
- contact.history-searchattributes
- contact.history.voice-detailattributes
- · contact.last-calledagent.enable
- contact.last-calledagent.<media-type>.enable
- contact.lookup.auto-assign-
- · contact.lookup.enable
- contact
- contact.lookup.voice.usedialed-phone-number
- contact.lookup.<media- type>.auto-assign-mode
- · contact.lookup.<mediatype>.enable
- · contact.lookup.<media-

- type>.enable-create-contact
- contact.mandatory-attributes
- · contact.metrics.enableinteractions-in-progress
- contact.metrics.time-framecustomer-notification
- · contact.multi-value-attributedisplay. < contact-attribute >
- · contact.multiple-valueattributes
- contact.multiple-valueattributes-enable-defaultdescription
- · contact.myhistory-defaulttime-filter-main
- · contact.myhistory-displayedcolumns
- contact.myhistory-displayedcolumns-treeview
- contact.myhistory-quicksearch-attributes
- · contact.threading-ucsinteraction enable
- contact.timeout-delay
- contact.ucsinteraction.<mediatype>.enable-create
- contact.ucsinteraction. < mediatype>.enable-lookup
- contact.ucsinteraction. < mediatype>.use-server-date
- dial-plan-rule-<name>
- disaster-recovery.auto-restore
- disaster-recovery.disablelogin-errors
- disaster-recovery.enabled
- disaster-recovery.eservicesrandom-delay-range
- disaster-recovery.eservicessite
- disaster-recovery.peer-site

- disaster-recovery.preferredsite
- disaster-recovery.restoreagent-state
- disaster-recovery.timeout
- disaster-recovery.wait-forsipphone-timeout
- display-format.acdqueue.name
- display-format.actioncode.name
- display-format.agentgroup.name
- · display-format.agent-name
- display-format.businessattribute.name
- · display-format.caller-name
- display-format.case-nameformat
- display-format.chat-agentname
- display-format.chat-customername
- display-format.contact-name
- display-format.current-agentname
- display-format.customername-format
- · display-format.field.name
- · display-format.folder.name
- display-format.interactioncallback-name
- display-format.interactionchat-name
- display-format.interactionemail-name
- display-format.interaction-imname
- display-format.interactionoutbound-pull-preview-name
- display-format.interactionoutbound-push-preview-

- name
- display-format.interactionqueue.name
- display-format.interactionsms-name
- display-format.interactionvoice-name
- display-format.interactionworkitem-name
- display-format.outboundrecord-name
- display-format.party-nameformat
- display-format.routingpoint.name
- · display-format.skill.name
- display-format.virtualqueue.name
- · display-format.workbin.name
- · editor.font-size-units
- · editor.shortcuts.prefix
- editor.user-agent-http-header
- email.attachment-downloadtimeout
- · email.auto-answer
- email.auto-answer.enablereject
- email.auto-answer.timer
- email.can-change-textdirection
- email.default-queue
- email.forward.enable-ccaddresses
- email.forward.enableinstructions
- email.forward.enablemultiple-to-addresses
- email.forward-queue
- · email.from-addresses
- email.from-addresses.forcedefault-on-reply

- email.html-format
- email.include-original-text-inreply
- email.include-standardresponse-subject-on-insert
- email.inline-forward-prefix
- email.inline-forward-queue
- · email.mandatory-subject
- email.max-attachments-size
- email.move-inbound-to-inprogress-workbin-on-reply
- email.outbound.copyeditable-case-data-ininbound
- email.outbound.editable-bccaddresses
- email.outbound.editable-ccaddresses
- email.outbound.editable-toaddresses
- email.outbound-queue
- email.prompt-for-done
- email.pull-from-historyisenabled
- email.qa-review-dispositionsbusiness-attribute
- · email.quote-char
- · email.quote-header
- email.reply-copy-category-id
- · email.reply-format
- · email.reply-prefix
- · email.resend-prefix
- email.restricted-attachmentfile-types
- email.ringing-bell
- email.set-ownerid-on-send
- · email.signature
- email.toast-information-key
- · eservices.disconnect-on-

logoff

- eservices.session-restoremediatype
- eservices.session-restoretimeout
- expression.callable-phonenumber
- expression.email-address
- expression.outboundcampaign-phone-number
- · expression.phone-number
- expression.phonenumber.supported-characters
- expression.teamcommunicator-phone-number
- expression.url
- gadget-statistics.displayedcall-center-statistics
- gadget-statistics.displayedkpis
- gadget-statistics.nb-taggedstats-per-page
- gadget-statistics.show
- gadget.window-title
- general.configuration-agentcollection-loading-method
- general.configurationbusiness-attribute-cachepreload
- general.configurationbusiness-attribute-foldercache-preload
- general.configuration-object-collection-cache-timeout
- general.configurationtransaction-cache-preload
- general.configuration-updatenotification
- · general.gad.attached-data
- general.non-unicodeconnection-encoding
- general.writable-downloaded-

- attachment-file-types
- gui.editor-zoom-range
- · gui.emoji-font-name
- · gui.magnification-factor
- · gui.themes
- · im.agent.prompt-color
- · im.agent.text-color
- im.auto-answer
- · im.new-message-bell
- · im.other-agent.prompt-color
- im.other-agent.text-color
- · im.prompt-for-end
- · im.ringing-bell
- im.simple-transcript
- im.system.text-color
- · im.time-stamp
- · im.toast-timeout
- interaction.auto-focus
- interaction.autofocus.<media-type>
- interaction-bar.allowsfloating-transparency
- interaction-bar.detailtooltip.max-height
- interaction-bar.enable-quickaccess
- interaction-bar.quick-accessauto-open
- interaction-bar.quick-accessauto-open.<media-type>
- interaction-bar.quick-accessmodes
- interaction-bar.quick-accessmodes.<media-type>
- · interaction.case-data.content
- interaction.casedata.email.mandatoryactions
- · interaction.case-data.enable-

- url-preview
- interaction.case-data.formatbusiness-attribute
- interaction.case-data.framecolor
- interaction.case-data.headerforeground-color
- interaction.case-data.is-readonly-on-idle
- interaction.casedata.<mediatype>.mandatory-actions
- · interaction.consult-user-data
- interaction.disposition.displaymode
- interaction.disposition.email.mandatoryactions
- interaction.disposition.ismandatory
- interaction.disposition.isread-only-on-idle
- interaction.disposition.keyname
- interaction.disposition.useattached-data
- interaction.disposition.useconnection-id
- interaction.disposition.valuebusiness-attribute
- interaction.disposition.<mediatype>.mandatory-actions
- interaction.evaluate-realparty-for-agent
- interaction.evaluate-realparty-for-agent.expression
- interactionmanagement.availableinteraction-page-sizes
- interactionmanagement.filters
- interactionmanagement.interactionsfilter.displayed-columns

- · interactionmanagement.snapshottimeout-delay
- interaction.override-option-
- · interaction.reject-route
- interaction.unconditionalforce-close
- interaction.window.popuptopmost-z-order
- · interaction.window.showcase-interaction-panel-button
- · interaction.window.show-intaskbar
- · interaction.window-title
- · interactions.window.allowstransparency-on-winos6
- ready-with-reason.<action-intercommunication.chat.conference.ipvite> timeout
- · intercommunication.chat.queue
- intercommunication.chat.routingbased-actions
- intercommunication.chat.routing- keyboard.hotkey.decreasebased-targets
- · intercommunication.email.queue
- based-actions
- intercommunication.email.routingbased-targets
- · intercommunication.im.routingbased-actions
- · intercommunication.im.routingbased-targets
- · intercommunication.im.routingpoints
- · intercommunication.sms.queue
- based-actions
- intercommunication.sms.routing keyboard.hotkey.toaster.accept based-targets
- · intercommunication.voice.routingbased-actions

- intercommunication.voice.routing keyboard.shortcut.campaign.getbased-targets
- points
- intercommunication.voicemail.enabledtarget-types
- intercommunication.voicemail.routingeyboard.shortcut.hamburger.open points
- · intercommunication.<mediatype>.queue
- · intercommunication.<mediatype>.routing-based-actions
- · intercommunication.<mediatype>.routing-based-targets
- · keyboard.hotkey.agent-notready
- · keyboard.hotkey.agent-not-
- keyboard.hotkey.agent-ready
- · keyboard.hotkey.decreasemicrophone-volume-activesip-call
- speaker-volume-active-sipcall
- intercommunication.email.routing- keyboard.hotkey.hold-active
 - keyboard.hotkey.increasemicrophone-volume-activesip-call
 - · keyboard.hotkey.increasespeaker-volume-active-sipcall
 - keyboard.hotkey.mutemicrophone-active-sip-call
 - · keyboard.hotkey.mutespeaker-active-sip-call
- intercommunication.sms.routing- keyboard.hotkey.releaseactive-call

 - · keyboard.hotkey.toaster.decline
 - keyboard.shortcut.action.help

- record
- intercommunication.voice.routing- keyboard.shortcut.contact.assigncontact
 - keyboard.shortcut.contact.reset
 - keyboard.shortcut.contact.save
 - keyboard.shortcut.interaction.chat.addattachments
 - keyboard.shortcut.interaction.chat.conferer
 - keyboard.shortcut.interaction.chat.end
 - keyboard.shortcut.interaction.chat.hold
 - keyboard.shortcut.interaction.chat.transfer
 - keyboard.shortcut.interaction.consult
 - keyboard.shortcut.interaction.email.addattachments
 - keyboard.shortcut.interaction.email.cancelf
 - keyboard.shortcut.interaction.email.comple
 - keyboard.shortcut.interaction.email.delete
 - keyboard.shortcut.interaction.email.forward
 - keyboard.shortcut.interaction.email.inlineforward
 - keyboard.shortcut.interaction.email.interim send
 - keyboard.shortcut.interaction.email.print
 - keyboard.shortcut.interaction.email.putback-to-origin-queue
 - keyboard.shortcut.interaction.email.reply
 - keyboard.shortcut.interaction.email.reply-
 - keyboard.shortcut.interaction.email.save
 - keyboard.shortcut.interaction.email.savein-workbin
 - keyboard.shortcut.interaction.email.send
 - keyboard.shortcut.interaction.email.transfe
 - keyboard.shortcut.interaction.im.release
 - · keyboard.shortcut.interaction.markdone
 - keyboard.shortcut.interaction.preview.callrecord

- keyboard.shortcut.interaction.previewbaanketd-origin-queue
 - keyboard.shortcut.interaction.workitem.transfer
- keyboard.shortcut.interaction.preview.mark keyboard.shortcut.state.logout
- keyboard.shortcut.interaction.preview.exappard.shortcut.state.notdone-get-next
- keyboard.shortcut.interaction.preview.eyboard.shortcut.state.not-record ready-after-call-work record
- keyboard.shortcut.interaction.pull keyboard.shortcut.state.ready preview.mark-done
- · keyboard.shortcut.interaction.pullpreview.mark-done-get-next
- keyboard.shortcut.team-
- communicator.focus
- · login.email.can-unactivate-
- login.email.is-auto-ready keyboard.shortcut.teamlead.chat.bargein
- keyboard.shortcut.interaction.sms.deleteboard.shortcut.teamlead.chat.stoPchannel login.enable-login-without-
- keyboard.shortcut.interaction.sms.tramseritoring
- keyboard.shortcut.interaction.voice.akewboard.shortcut.teamlead.stopmonitorina call
- place keyboard.shortcut.interaction.voice.hbearboard.shortcut.teamlead.voice.bargein login.im.auto-not-ready keyboard.shortcut.teamlead.voice.coachingh call
- keyboard.shortcut.interaction.voice.pause. Reyboard.shortcut.teamlead.voice.mqកូម៉ូកា.im.available-queues
- keyboard.shortcut.interaction.voice.reconnectmonitoring channel channel call
- keyboard.shortcut.interaction.voice.release
 - call keyboard.shortcut.toaster.decline
- keyboard.shortcut.interaction.voice.requirdisplayed-kpis kpi.refresh-time
- keyboard.shortcut.interaction.voice.resume-kpi.show-agent-groups recording-call
- keyboard.shortcut.interaction.voice.slifenese.lrm-enabled step-conference log.default-filter-type
- keyboard.shortcut.interaction.voice.singleSDK step-transfer
- keyboard.shortcut.interaction.voice.startrecording-call log.filter-data.
- keyboard.shortcut.interaction.voice.stog.max-age recording-call
- log.PSDK keyboard.shortcut.interaction.webcallback.call-contact
 log.PSDK.SwitchPolicy contact
- keyboard.shortcut.interaction.webcal backenant done · log.Trace
- keyboard.shortcut.interaction.workitem.move-log.verbose to-workbin
- keyboard.shortcut.interaction.workitem.put-

reason login.chat.can-unactivate-

login.chat.auto-not-ready-

- channel login.chat.is-auto-ready
- login.default-place
- · login.email.auto-not-readyreason
- channel
- login.enable-place-completion
- login.enable-same-agent-
- - - · login.im.is-auto-ready
 - login.im.prompt-agent-login-
 - login.im.prompt-dn-password
 - login.im.prompt-queue
 - · login.place-location-source
 - login.place-selection-type
 - login.place-state-timeout
 - login.prompt-place
 - login.sip-cluster.phonenumber
 - · login.sip-cluster.store-recentphone-number
 - login.sms.auto-not-readyreason
 - login.sms.can-unactivatechannel
 - login.sms.is-auto-ready
 - login.store-recent-place

- login.store-username
- login.voice.auto-not-readyreason
- login.voice.available-queues
- login.voice.can-unactivatechannel
- · login.voice.force-relogin
- login.voice.is-auto-ready
- login.voice.prompt-agentlogin-id
- login.voice.prompt-dn-lessphone-number
- login.voice.prompt-dnpassword
- login.voice.prompt-queue
- login.voice.restore-dn-lessphone-number-on-logout
- login.voice.use-dn-less-loginextension
- login.webcallback.auto-notready-reason
- login.webcallback.canunactivate-channel
- login.webcallback.is-autoready
- login.workmode
- login.<media-type>.auto-notready-reason
- login.<media-type>.canunactivate-channel
- login.<media-type>.is-autoready
- logout.enable-exit-on-logofferror
- logout.voice.use-login-queueon-logout
- main-window.auto-hidedisplay-delay
- main-window.bypass-autohide-conditions
- · main-window.window-title

- · openmedia.bundle.sms
- openmedia.workitemchannels
- options.clean-up-formerrecord-location
- options.record-location
- options.record-option-locallyonly
- outbound.assuredconnection.allow-releaseengaging-call-timeout
- outbound.call-resultautomatically-selected
- outbound.call-result-ismandatory
- · outbound.call-result-values
- outbound-callback.ringinghell
- outbound.callback-types
- outbound.campaign-staletimeout
- outbound.complete-recordbefore-transfer
- outbound.fields.floatseparator-in-db
- outbound.load-at-startup
- outbound.push-preview.autoanswer
- outbound.push-preview.autoanswer.enable-reject
- outbound.push-preview.autoanswer.timer
- outbound.pushpreview.media-types
- outbound.push-preview.usecombined-channel
- outbound.recordinformation.frame-color
- outbound.recordinformation.headerforeground-color
- outbound.reschedule-inheritparent-availability-interval

- outbound.sound.campaignupdated
- outbound.timed-previewauto-dial
- outbound.treatment-mode
- presence.evaluate-presence
- · printing.use-print-preview
- reporting.case.report-case-infocus-duration
- screenrecording.client.address
- screen-recording.client.maxattempts
- screen-recording.client.pinginterval
- · screen-recording.client.port
- screenrecording.client.secureconnection
- screenrecording.htcc.peer_uri
- · screen-recording.htcc.uri
- security.client-authenticationcertificate-search-value
- · security.disable-rbac
- security.enable-debuginformation
- security.inactivity-force-notready-state
- security.inactivity-not-readyreason
- security.inactivity-set-agentnot-ready
- security.inactivity-timeout
- security.session-lock-forcenot-ready-state
- security.session-lock-notready-reason
- security.session-lock-setagent-not-ready
- sip-cluster.data-centerlocations

- sip-cluster.reconnect-timeout
- sipendpoint.authenticatewith-dn-password
- sipendpoint.codecs.g729/ 8000.fmtp
- sipendpoint.codecs.h264.fmtp
- · sipendpoint.core-deadlockdetection-delay
- sipendpoint.enable-ipv6
- sipendpoint.exit-on-voicelogoff
- · sipendpoint.headset-enforceconfigured-usage
- sipendpoint.headsetreplugged-set-ready
- · sipendpoint.headsetunplugged.not-ready-reason
- · sipendpoint.headsetunplugged-set-not-ready
- · sipendpoint.init-attempt-nb
- · sipendpoint.init-attempt-timer
- sipendpoint.ip-version
- sipendpoint.log.expire
- · sipendpoint.log.segment
- · sipendpoint.log.verbose

- sipendpoint.policy.endpoint.tcp port singendpoint.proxies.proxy1.nat.stun server
- sipendpoint.policy.endpoint.tcp port sniprendpoint.proxies.proxy1.nat.turn passwo
- sipendpoint.policy.endpoint.video maxipleitateint.proxies.proxy1.nat.turn relay t
- sipendpoint.policy.endpoint.webrtc•asipenlageint.proxies.proxy1.nat.turn_server
- sipendpoint.policy.session.agc mode sipendpoint.proxies.proxy1.nat.turn server
- sipendpoint.policy.session.auto acceptipeidepoint.proxies.proxy1.nat.turn user na
- sipendpoint.policy.session.auto answeipendpoint.proxies.proxy1.reg interval
- sipendpoint.policy.session.dtmf methsidendpoint.proxies.proxy1.reg match rece
- sipendpoint.policy.session.dtx_mode sipendpoint.proxies.proxy1.reg_timeout
- sipendpoint.policy.session.echo contrsibendpoint.retain-volume-
- settings-between-sessions
 sipendpoint.policy.session.noise_suppression
- sipendpoint.policy.session.reject_session_wegen_headset_na
- sipendpoint.policy.session.ringback_egabledpoint.sbc-register-
- sipendpoint.policy.session.ringback_fileddress.peer
- sipendpoint.policy.session.rx_agc_moaipendpoint.sbc-register-port
- sipendpoint.policy.session.sip_code wile in heads et braregisterport.peer
- sipendpoint.policy.session.vad level
- sipendpoint.standalone.certificatesearch-value sipendpoint.proxies.proxy0.domain
- sipendpoint.proxies.proxy0.nat.ice ersibeedpoint.standalone.port
- sipendpoint.proxies.proxy0.nat.stun sipendpoint.standalone.protocol
- sipendpoint.proxies.proxy0.nat.stun sipendpoint.standalone.security-
- level sipendpoint.proxies.proxy0.nat.turn password
- sipendpoint.policy.device.audio_in_device sipendpoint.proxies.proxy0.nat.turn_relate_type sipendpoint.standalone.subject-
- sipendpoint.policy.device.audio_out_device sipendpoint.proxies.proxy0.nat.turn_sgpendpoint.standalone.subject-
- sipendpoint.policy.device.capture_device sipendpoint.proxies.proxy0.nat.turn_server_port
- sipendpoint.policy.device.headset_name_sipendpoint.proxies.proxy0.nat.turn_user_name_detection-model

- sipendpoint.policy.endpoint.defer_device_ralease sipendpoint.proxies.proxy0.reg_matchdetectionuuspedns
- sipendpoint.policy.endpoint.include mac address proxies.proxy0.reg_timeosipendpoint.system.diagnostics.enable_logo
- sipendpoint.policy.endpoint.public_address Sipendpoint.proxies.proxy1.domain
 sipendpoint.system.diagnostics.log_filter
- sipendpoint.policy.endpoint.rtp_inactivity_timeout_sipendpoint.proxies.proxy1.domain
 sipendpoint.system.diagnostics.log_level
- sipendpoint.policy.endpoint.rtp_port_max_-sipendpoint.proxies.proxy1.domain
 sipendpoint.system.diagnostics.log_options
- sipendpoint.policy.endpoint.rtp_port_min_ sipendpoint.proxies.proxy1.domain* sipendpoint.system.security.cert_file
- sipendpoint.policy.endpoint.sip_port_max ndpoint.proxies.proxy1.nat.ice_erவ்று point.system.security.tls_enabled
- sipendpoint.policy.endpoint.sip_port_min_sipendpoint.proxies.proxy1.nat.stun_sependpoint.system.security.use_srtp

- sipendpoint.transportprotocol
- sipendpoint.video.always-ontop
- sipendpoint.video.autoactivate
- sipendpoint.video.cameraframe-rate
- sipendpoint.video.cameraframe-size
- sipendpoint.video.camerarender-format
- sipendpoint.video.thumbnailratio
- · sms.agent.prompt-color
- sms.agent.text-color
- sms.auto-answer
- sms.auto-answer.enablereject
- · sms.auto-answer.timer
- · sms.client.prompt-color
- · sms.client.text-color
- · sms.default-queue
- sms.from-numbers-businessattribute
- sms.max-message-number
- · sms.other-agent.prompt-color
- · sms.other-agent.text-color
- sms.outbound-queue
- sms.prompt-for-done
- sms.ringing-bell
- sms.simple-transcript
- · sms.subject-max-chars
- sms.system.text-color
- sms.time-stamp
- sms.transcript-enable-historyfilters
- · sms.transcript-time-frame
- sounds.preloadfiles

- spellchecker.chat.prompt-onsend
- spellchecker.corporatedictionary
- spellchecker.corporatedictionary-file
- spellchecker.email.prompt-onsend
- spellchecker.im.prompt-onsend
- spellchecker.sms.prompt-onsend
- spellchecker.<mediatype>.prompt-on-send
- standard-response.autoappend-star-to-search
- standard-response.categories
- standard-response.defaultsearch-type
- standard-response.enableusage-feedback
- standardresponse.field.<CustomFieldCode>
- standard-response.languages
- standardresponse.shortcuts.
- standardresponse.suggestedresponses-min-relevancy
- statistics.displayed-statistics
- statistics.queues
- · statistics.refresh-time
- statistics.routing-points
- system-tray.tooltip
- teamcommunicator.addrecent-filters.voice
- teamcommunicator.alwaysclear-textbox-on-newinteraction
- teamcommunicator.contactfavorite-fields
- · teamcommunicator.corporate-

favorites

- teamcommunicator.corporatefavorites-file
- teamcommunicator.customfavorite-fields
- teamcommunicator.interactionqueue-presence-metrics
- teamcommunicator.internalfavorite-fields
- teamcommunicator.list-filtershowing
- teamcommunicator.liststatus-reachable
- teamcommunicator.load-atstartup
- teamcommunicator.maxfavorites-size
- teamcommunicator.maxsuggestion-size
- teamcommunicator.queuepresence-metrics
- teamcommunicator.recent-max-records
- teamcommunicator.requeststart-timer
- teamcommunicator.routingpoint-presence-metrics
- teamlead.agentstatus.enabled-agent-groupsecurity-mode
- teamlead.agentstatus.enabled-remoteactions
- · teamlead.monitoring-scope
- toast.case-data.content
- toast.case-data.formatbusiness-attribute
- toast.window-title
- views.CaseContactRegion.activateorder
- · views.CaseContactRegion.order
- views.CaseViewSideButtonRegion.order

- views.ContactInfoHistoryMultiRegion.aotoabet-standby.backupretry-delay
- views.ContactInfoHistoryMultiRegion.voiler.hybrid-switch-
- views.ContactTabBottomHistoryMultiRegion.activate- voice.mark-done-on-release order
- views.ContactTabBottomHistoryMultiRedicennordearx-independent-
- views.InteractionDetailsRegion.activate-
 - · voice.one-step-trsf-mode order
- · views.InteractionDetailsRegion.order voice.prompt-for-end
- views.ToolbarWorkplaceRegion.activateice.ringing-bell
- voice.show-hold-duration
- views.ToolbarWorkplaceRegion.order
 voice.show-post-call-duration views.ToolbarWorksheetButtonRegion.order
 voice.sip-preview-bell
- views.WorkbinsTabBottomHistoryMultiRegion.activate-order
 voicemail.access-number
- views.WorkbinsTabBottomHistoryMultYReign ាកូរ៉ូកាខ្ពង់ត្រែcation-types
- · voice.after-call-workextension
- voice.auto-answer
- voice.auto-answer.enablereject
- voice.auto-answer.timer
- voice.cancel-after-call-workon-done
- · voice.complete-conferencerequires-connectedconsultation-call
- voice.device-type
- · voice.dtmf-inactivity-typingtimeout
- voice.enable-agentreservation
- voice.enable-init-conference
- voice.end-consultationmethod
- voice.hold-indicator-timer

- · warm-standby.reconnectionrandom-delay-range
- · warm-standby.retry-delay
- webcallback.auto-answer
- · webcallback.autoanswer.enable-reject
- · webcallback.autoanswer.timer
- · webcallback.auto-dial
- webcallback.callbackinformation.content
- webcallback.callbackinformation.frame-color
- · webcallback.callbackinformation.headerforeground-color
- · webcallback.complete-queue
- · webcallback.park-queue
- · webcallback.reschedulequeue

- webcallback.ringing-bell
- webproxy.address
- webproxy.password
- webproxy.username
- · workbin.email.draft
- workbin.email.draft.displayedcolumns
- · workbin.email.in-progress
- · workbin.email.inprogress.displayed-columns
- workbin.<media type>.inprogress
- workbin.<media type>.inprogress.displayed-columns
- · workbin.<mediatype>.<nick-name>.notifyproperty-changed
- · workbin.<mediatype>.<workbin-nickname>
- workbin.<mediatype>.<workbinnickname>.auto-update
- workbin.<media- type>.<workbinnickname>.displayedcolumns
- · workbin.<mediatype>.<workbinnickname>.max-results
- · workbin.<mediatype>.<workbinnickname>.quick-searchattributes
- workbin.<media-type>.inprogress
- workbin.<media-type>.inprogress.displayed-columns

For information about how to use these options to configure Genesys Web Services functionality and behavior, refer to the *Workspace Desktop Edition Deployment Guide*.

Tip

The following descriptions were generated by dynamic query and include cached results that may be up to one day old. Click here to refresh the query.

<media-type>.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether a workitem interaction of the specified type is accepted automatically when an Interaction Server Invite event is received. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

<media-type>.auto-answer.enable-reject

Default Value: false **Valid Values:** true. false

Changes Take Effect: At the next interaction.

Dependencies: <media-type>.auto-answer, <media-type>.auto-answer.timer

Introduced: 8.5.105.12

When the <media-type>.auto-answer option with matching media type is set to true and <media-type>.auto-answer.timer is greater than 0, this option specifies if the reject button should be enabled when the corresponding privilege is granted. Privilege
InteractionWorkspace.Voice.canRejectCall, or InteractionWorkspace.<media-type>.canDecline for open media. Note that for outbound push-preview interactions, the applicable option is 'outbound.push-preview.auto-answer.enable-reject'. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

<media-type>.auto-answer.timer

Default Value: 0

Valid Values: any integer greater or equal to 0 **Changes Take Effect:** At the next interaction. **Dependencies:** <media-type>.auto-answer

Introduced: 8.5.105.12

Related Options: outbound.push-preview.auto-answer.timer

When the <media-type>.auto-answer option with matching media type is set to true, this option specifies the time in seconds after which the incoming interactions of this type is automatically answered. A value of 0 means immediate auto-answer. Note that for outbound push-preview interactions, the applicable option is outbound.push-preview.auto-answer.timer. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

<media-type>.contact-history.enable-combineinteraction-with-current

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Introduced: 8.5.142.05 **Discontinued:** 8.5.143.08

If an agent is already handling an interaction with a contact, this option specifies whether an inprogress interaction of the given media type, opened from the **Contact History** tab, is displayed in the current interaction view or in a separate case view. **Note:** you cannot display more than one Email interaction in the same view. This option has been replaced by <media-type>.contacthistory.enable-combine-ixn-with-current due to GAX maximum character length for option names.

>> Back to Top

<media-type>.contact-history.enable-combine-ixn-withcurrent

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Introduced: 8.5.143.08

Specifies whether an interaction of the given media type opened from the **Contact History** tab is displayed in the current interaction view or in a separate case view. **Note**: you cannot display more than one Email interaction in the same view. This option replaces <media-type>.contact-history.enable-combine-interaction-with-current due to GAX maximum character length for option names.

<media-type>.prompt-for-done

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies if the application prompts a confirmation message when a user clicks Done. This option is only available for interaction open media. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

<media-type>.pull-from-history-isenabled

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediately.

Specifies whether it is possible to pull an interaction of the specified media type from Contact History. This option is applicable only if at least one of the following privileges has been granted to the agent: "Contact - Can Pull From Queue", "Contact - Can Pull Interactions In Shared Workbins", "Contact - Can Pull Interactions In Workbins Not Owned By The User".

Before enabling this function for a given workitem media type, ensure with your plug-in vendor that this feature is correctly supported.

>> Back to Top

<media-type>.ringing-bell

Default Value: Sounds\Ring.mp3|10|-1|primary

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric

/alues.

Changes Take Effect: At the next interaction.

Dependencies: application.secondary-audio-out-device

Specifies the path of the sound file that is played when interaction of type <media-type> is ringing. For example: "Sounds\Ring.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority. The higher the integer the higher the priority.
- 3. The duration:
 - a. -1 means play and repeat until an explicit message stops it. For example, the established event stops the ringing sound.
 - b. 0 means play the whole sound one time.

- c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

<media-type>.toast-information-key

Default Value: Subject

Valid Values: Any valid attached data key name. **Changes Take Effect:** At the next interaction.

Specifies whether the information area is displayed in the specified workitem channel interaction notification. This option provides the name of the attached data key that contains the information. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

accessibility.agent-state-change-bell

Default Value:

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric

Changes Take Effect: At the next interaction.

Dependencies: application.secondary-audio-out-device

Specifies the sound configuration string used when the agent state changes. For example: "Sounds\ bell.mp3|7|0|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, mp3 and other sound file formats cannot be rendered by DirectShow filters. In this scenario, use DirectShow-compatible formats such as .wav.
- 2. The priority—The higher the integer the higher the priority.
- 3. The duration:
 - a. 0 means play the sound one time.
 - b. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device

- secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
- both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

accessibility.disable-hyperlinks

Default Value: false **Valid Values:** true, false

Changes Take Effect: The next time an interaction containing a hyperlink is displayed.

Introduced: 8.5.124.08

Related Options: accessibility.visual-impairment-profile

Specifies whether processing and presenting hyperlinks in email, chat, SMS, and MMS as active elements should be disabled or enabled. Some screen readers cause Workspace to become unresponsive when processing active hyperlinks.

>> Back to Top

accessibility.focus-on-interaction-toast

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.101.14

Specifies that all Interaction Notification views receive the focus when they are displayed. This option does not rely on the accessibility.visual-impairment-profile option; therefore, it applies to all configured agents, not just visually impaired agents.

>> Back to Top

accessibility.interaction-state-change-bell

Default Value:

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric values.

Changes Take Effect: At the next interaction.

Dependencies: application.secondary-audio-out-device

Specifies the interaction state change sound-configuration string. For example: "Sounds\ chord.mp3|5|0|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority. The higher the integer the higher the priority.

- 3. The duration:
 - a. 0 means play the whole sound one time.
 - b. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

accessibility.visual-impairment-profile

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.113.11 Modified: 8.5.124.08

Related Options: accessibility.disable-hyperlinks

Specifies whether the profile for visually impaired users is active. This option enables more interface elements to be focusable (accessible from keyboard navigation and mouse-over) so that they can be navigated from Screen Reader applications. Beginning with version 8.5.113.11, Workspace enables agents to enter TABs in the email composition area of outgoing email interactions by pressing the **TAB** key if the value of this option is set to false; to use the **TAB** key to step to the next control or field, agents must first press **Ctrl-TAB** to step out of the text composition area. To disable this feature, set the value of this option to true; agents will not be able to enter TABS in the email composition area, but they can use the **TAB** key to move to the next control in the tab order.

>> Back to Top

accessibility.warning-message-bell

Default Value:

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric

values.

Changes Take Effect: At the next interaction.

Dependencies: application.secondary-audio-out-device

Specifies the warning message sound-configuration string. For example: "Sounds\ warning.mp3|10|0|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority -- The higher the integer the higher the priority.

- 3. The duration:
 - a. 0 means play the whole sound one time.
 - b. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

accessibility. < media-type > . focus-on-interaction-toast

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.101.14

Related Options: accessibility.focus-on-interaction-toast

Specifies that all Interaction Notification views for the <media-type> receives the focus when they are displayed. When a value for this option is set, this option overrides the accessibility.focus-on-interaction-toast option. This option does not rely on the accessibility.visual-impairment-profile option; therefore, it applies to all configured agents, not just visually impaired agents.

>> Back to Top

active-recording.voice.recorder-uri

Default Value:

Valid Values: A string in format sip:host:port **Changes Take Effect:** At application restart.

Specifies the URI of the voice recorder. Use this option if you will use a voice recorder other than the one that is configured in GVP.

>> Back to Top

active-recording.voice.recorder-uri

Default Value:

Valid Values: A string in format sip:host:port **Changes Take Effect:** At application restart.

Specifies the URI of the voice recorder. Use this option if you will use a voice recorder other than the one that is configured in GVP.

>> Back to Top

active-recording.voice.recording-type

Default Value: NETANN

Valid Values: NETANN or MSML

Changes Take Effect: At application restart.

Specifies the type of voice recording to be used. NETANN and MSML are supported.

- NETANN: Legacy call recording using NETANN can be provided by Stream Manager or Genesys Media Server.
- MSML (Active Recording): Call recording through Media Server Markup Language (MSML) is provided through Genesys Media Server only. For details about this type of recording, refer to "Call Recording—MSML-based" in the SIP Server Deployment Guide.

>> Back to Top

agent-status.enabled-actions-by-channel

Default Value: Ready, NotReady, NotReady Reason, After Call Work, Dnd, Logon, LogOff

Valid Values: Comma-separated list of action names from the following list: Ready, NotReady,

NotReadyReason, AfterCallWork, Dnd, LogOn, LogOff.

Changes Take Effect: Immediately.

Defines the available agent state actions in "My Channels" contextual menu. The actions are displayed in the order in which they appear in the list.

>> Back to Top

agent-status.enabled-actions-global

Default Value: Ready, NotReady, NotReadyReason, After Call Work, Dnd, Logon, LogOff **Valid Values:** Ready, NotReady, Dnd, After Call Work, NotReady Reason, LogOn, LogOff

Changes Take Effect: Immediately.

Defines the available agent states in the global Status menu. The agent state commands are displayed in the order in which they appear in the list.

agent-status.not-ready-reasons

Default Value:

Valid Values: Comma-separated list of Action Code names of type "Not Ready"; empty means all not

ready action codes are considered **Changes Take Effect:** Immediately.

Defines the available reasons in the Agent Status menus (global and My Channels). The reason commands are displayed in the order in which they appear in the list.

>> Back to Top

alert.timeout

Default Value: 10

Valid Values: An integer value greater than or equal to 0.

Changes Take Effect: When the application is started or restarted.

Specifies the duration, in seconds, of the contextual warning messages that are displayed in the windows of the application. The value 0 means that message notifications are not automatically closed and must be closed manually.

>> Back to Top

application.available-layouts

Default Value: main-window **Valid Values:** main-window

Changes Take Effect: When the application is started or restarted.

Specifies which views are available, and which view is displayed on login. If the option is empty, the Main window is not accessible, and Interaction Worskspace starts in the system tray.

>> Back to Top

application.secondary-audio-out-device

>> Back to Top

application.wiki-help-locale

Default Value:

Valid Values: A locale name based on format LanguageCode-CountryCode (ex: 'en-US').

Changes Take Effect: At next request to the online help.

Introduced: 8.5.100.05

Specifies the locale of the Workspace online help. When this option is left empty, Workspace tries to find the online help that corresponds with the current language selected by the agent. If set to a valid locale (LanguageCode-CountryCode, for example: en-US), Workspace accesses the online help of the specified language.

>> Back to Top

application.wiki-help-welcome-page

Default Value:

Valid Values: A valid web page URL.

Changes Take Effect: At next request to on-line help.

Specifies the URL of the Workspace help home page. When this option is specified, all access requests to the on-line help are redirected to this page.

>> Back to Top

broadcast.color.high-priority

Default Value: #FF5E99FF

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain

color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Specifies the color of the border of the Message view frames for high priority messages. Examples: #FFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color.

>> Back to Top

broadcast.color.important-priority

Default Value: #FFE81100

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain

color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Specifies the color of the border of the Message view frames for important priority messages. Examples: #FFFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color.

>> Back to Top

broadcast.color.low-priority

Default Value: #FF7EC0C2

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain

color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Specifies the color of the border of the Message view frames for low priority messages. Examples: #FFFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color.

>> Back to Top

broadcast.color.minimal-priority

Default Value: #FFC7C7C7

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain

color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Specifies the color of the border of the Message view frames for minimal priority messages. Examples: #FFFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color.

>> Back to Top

broadcast.color.normal-priority

Default Value: #FFC48C88

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain

color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Specifies the color of the border of the Message view frames for normal priority messages. Examples: #FFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color.

>> Back to Top

broadcast.displayed-columns

Default Value: MessageTypelcon, MessageType, Sender, Subject, Priority, Date, Topic

Valid Values: A comma-separated list of valid object types from the following: MessageTypeIcon,

MessageType, Sender, Subject, Priority, Date, Topic, Id, any key of custom data

Changes Take Effect: When the application is started or restarted.

Specifies the names of the columns that are displayed in the MyMessage view.

>> Back to Top

broadcast.dn

Default Value:

Valid Values: A comma-separated list of DN and switch names in the following format:

dn name@switch

Changes Take Effect: When the application is started or restarted.

Specifies the list of Communication DNs that are used for Broadcasting.

Workspace registers to the specified DNs when a corresponding TServer connection is configured in the application and then considers all messages sent on these connections.

>> Back to Top

broadcast.enable-removal

Default Value: all

Valid Values: A comma separated list of message types. **Changes Take Effect:** At next access to a message.

Specifies a comma separated list of message types, including custom message types, that an Agent is allowed to delete from the Message View.

There are three pre-defined types:

- · system internal system messages
- public any type other than system messages
- all all messages

>> Back to Top

broadcast.enable-removal-priority

Default Value: Important

Valid Values: Select from the list Highest priority level enabled for removal

Changes Take Effect: At next access to a message.

Specifies the highest message priority level that an agent is allowed to delete from the Message View.

>> Back to Top

broadcast.mark-read-timeout

Default Value: 5

Valid Values: from 0 to MAXINT

Changes Take Effect: When the application is started or restarted.

Specifies the duration, in seconds, that the broadcast message tooltip is displayed before the

message is marked as read. If the duration is 0, this feature is not applied; then, the message is not considered to be read until the agent selects it for reading.

>> Back to Top

broadcast.message-content

Default Value: Subject, Sender, Priority, Date, Topic, Body

Valid Values: A comma-separated list of valid object types from the following: Subject, Sender,

Priority, Date, Topic, Body, MessageType, Id, any key of custom data

Changes Take Effect: At the next message.

Specifies the attributes that are displayed in the Broadcast Message window and in the item tooltip of the MyMessages view.

>> Back to Top

broadcast.preview-timeout

Default Value: 10

Valid Values: from 0 to MAXINT

Changes Take Effect: At the next message.

Defines the duration, in seconds, that the preview of the broadcast message is displayed in the Information area of the Main Window. The value 0 means the Preview is not displayed.

>> Back to Top

broadcast.sound.high-priority

Default Value:

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric

Changes Take Effect: At the next interaction.

Dependencies: application.secondary-audio-out-device **Related Options:** application.secondary-audio-out-device

Specifies the sound configuration string of messages of type important. For example: "Sounds\ HighMessage.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority -- The higher the integer the higher the priority.
 - a. -1 means play the whole sound and repeat the sound until the Interactive Notification is closed.
 - b. 0 means play the whole sound one time.

- c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 3. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

broadcast.sound.important-priority

Default Value:

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric values

Changes Take Effect: At the next interaction.

Dependencies: application.secondary-audio-out-device **Related Options:** application.secondary-audio-out-device

Specifies the sound-configuration string of a message of type important. For example: "Sounds\ ImportantMessage.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority -- The higher the integer the higher the priority.
- 3. The duration:
 - a. -1 means play the whole sound and repeat the sound until the Interactive Notification is closed.
 - b. 0 means play the whole sound one time.
 - c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

broadcast.sound.low-priority

Default Value:

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric

values.

Changes Take Effect: At the next interaction.

Dependencies: application.secondary-audio-out-device **Related Options:** application.secondary-audio-out-device

Specifies the sound configuration string of messages of type important. For example: "Sounds\
LowMessage.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority"The higher the integer the higher the priority.
- 3. The duration:
 - a. -1 means play the whole sound and repeat the sound until the Interactive Notification is closed.
 - b. 0 means play the whole sound one time.
 - c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

>> Back to Top

broadcast.sound.minimal-priority

Default Value:

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric values

Changes Take Effect: At the next interaction.

Dependencies: application.secondary-audio-out-device **Related Options:** application.secondary-audio-out-device

Specifies the sound configuration string of messages of type important. For example: "Sounds\ MinimalMessage.mp3|10|-1|primary" The value has four components that are separated by the character '|':

1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.

- 2. The priority. The higher the integer, the higher the priority.
- 3. The duration:
 - a. -1 means play the whole sound and repeat the sound until the Interactive Notification is closed.
 - b. 0 means play the whole sound one time.
 - c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

broadcast.sound.normal-priority

Default Value:

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric values

Changes Take Effect: At the next interaction.

Dependencies: application.secondary-audio-out-device **Related Options:** application.secondary-audio-out-device

Specifies the sound configuration string of messages of type important. For example: "Sounds\ NormalMessage.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority -- The higher the integer the higher the priority.
- 3. The duration:
 - a. -1 means play the whole sound and repeat the sound until the Interactive Notification is closed.
 - b. 0 means play the whole sound one time.
 - c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

broadcast.subscribed.topics

Default Value: All,\$Agent\$,\$AgentGroup\$ **Valid Values:** A comma-separated list of string

Changes Take Effect: When the application is started or restarted.

Specifies the list of topics to which agents can be subscribed. The key \$Agent\$ defines the username of the agent. The key \$AgentGroup\$ defines all agent groups of which the agent is a member.

>> Back to Top

broadcast.system-messages-auto-mark-read

Default Value: true **Valid Values:** boolean

Changes Take Effect: At next change of counter value.

Specifies that system messages are marked as "read" immediately after the interactive notification is displayed to prevent the Main Menu button from including them in the notification bullet counter.

>> Back to Top

broadcast.toast-summary

Default Value: Sender, Priority, Subject, Few Words

Valid Values: A comma-separated of valid object types from the following: Sender, Priority, Subject,

FewWords, Topic, MessageType, any key of custom **Changes Take Effect:** At the next message.

Determines the attributes display in the broadcast message notification.

>> Back to Top

broadcast.value-business-attribute

Default Value:

Valid Values: A valid Business Attribute name.

Changes Take Effect: When the application is started or restarted.

A character string that specifies the name of the Business Attribute that contains the Attribute Values that are used as an enumerated value for custom attribute of message.

callback.callback-information.content

Default Value: DesiredTime, Type, Number, Instructions

Valid Values: A comma separated list of items within the following list: DesiredTime, Type, Number,

Instructions.

Changes Take Effect: At the next interaction.

Introduced: 8.5.111.21

Defines the Callback data that is displayed in the Callback Information Area. The Callback data entries are displayed in the order in which they appear in the list.

>> Back to Top

callback.callback-information.frame-color

Default Value:

1. FF17849D

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: At the next interaction.

Introduced: 8.5.111.21

Specifies the background color of the Callback Information view header of Callback interactions. Examples: #FFFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

callback.callback-information.header-foreground-color

Default Value: #FFFFFFF

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: At the next interaction.

Introduced: 8.5.111.21

Specifies the color of the text of the Callback Information view header of Callback interactions. Example #FFFFFFF for white color. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

callback.callback-types-business-attribute

Default Value:

Valid Values: A valid Business Attribute Name. **Changes Take Effect:** At the next interaction.

Introduced: 8.5.111.21

A character string that specifies the name of the Business Attribute that contains the Attribute Values that are used as available "Callback Types" when scheduling a Callback.

>> Back to Top

callback.gms-url

Default Value:

Valid Values: A valid URL in the following format: http://<gms-host>:<gms-port>/

Changes Take Effect: At next callback request.

Introduced: 8.5.111.21

Specifies the URL of the Genesys Mobile Server (GMS) that will be used for Callback requests.

>> Back to Top

callback.ringing-bell

Default Value: Sounds\Ring.mp3|10|-1|primary

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric

/alues.

Changes Take Effect: At the next interaction.

Introduced: 8.5.115.17

Specifies the path of the sound file that is played when a Callback Preview Invitation is delivered to the agent. For example: "Sounds\ Ring.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1) The file name and folder relative to the application folder. It may happen that on some virtual desktop, MP3 or other sounds format cannot be rendered by Direct Show filters. Files format that can be played (.wav, ...) with Direct Show must be used here.
- 2) The priority. The higher the integer the higher the priority.
- 3) The duration:
 - a) -1 means plays and repeats until an explicit message stops it (I.e.: the established event stops the ringing sound).
 - b) 0 means play the whole sound one time.
 - c) An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4) The output devices:
 - a) primary means plays on the default output device.
 - b) secondary means plays on the output device specified by the application.secondary-audio-out-device option.
 - c) both means plays on both default output device and the output device specified by the application.secondary-audio-out-device option.

case-data.float-separator

Default Value:

Valid Values: A valid float separator. Typical float separators are: '.' (period), ',' (comma), and '\'

(backslash).

Changes Take Effect: Immediately.

Specifies the float separator that is used for Case Information. This option should be used when the decimal symbol in the regional settings of the agent workstation is different from the one provided by the database.

>> Back to Top

channel-information.window-title

Default Value: \$Window.Title\$

Valid Values:

\$Window.Title\$,\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$

Changes Take Effect: Immediately.

Defines the title of the window that prompts for place and media login data that appears in the Windows Task Bar by specifying a string that contains the following field codes:\$Window.Title\$,\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.Employeeld\$. If all field codes are empty, the following field codes are used: \$Window.Title\$.

>> Back to Top

chat.agent.prompt-color

Default Value: #FF2E6599

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain

color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the prompt for the messages entered by the agent in the Chat view.

>> Back to Top

chat.agent.text-color

Default Value: #FF3D464D

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain

color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the text of the messages entered by the agent in the Chat view.

>> Back to Top

chat.attachment-download-timeout

Default Value: 20

Valid Values: An integer value between -1 and 3600.

Changes Take Effect: Immediately.

Defines the maximum duration, in seconds, of the download of an attachment. The value -1 means that there is no maximum time.

>> Back to Top

chat.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether a chat interaction is automatically accepted and joined when a Interaction Server Invite event is received. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

chat.auto-answer.enable-reject

Default Value: false **Valid Values:** true. false

Changes Take Effect: At the next interaction.

Introduced: 8.5.105.12

Specifies whether the **Reject** button is available in the interaction notification when the value of chat.auto-answer is set to true and the value of chat.auto-answer.timer is greater than 0. The privilege to reject interactions must be granted. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

chat.auto-answer.timer

Default Value: 0

Valid Values: Any integer greater than or equal to 0 **Changes Take Effect:** At the next interaction.

Introduced: 8.5.105.12

Specifies the time, in seconds, after which an incoming interaction is automatically answered if the value of chat.auto-answer is set to true. If the value 0 is specified, interactions are immediately auto-answered. If any positive integer value is specified, then an interaction notification is displayed to the agent and a timer counts down the seconds until the interactions is auto-answered. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

chat.auto-mark-done-non-owner-agent

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediately

Dependencies: interaction.disposition.is-mandatory

Introduced: 8.5.128.07

Related Options: chat.auto-mark-done-owner-agent, chat.auto-mark-done-non-owner-agent.timer

Specifies whether chat interactions are automatically closed and marked done when the contact disconnects if the agent is not the owner (not the last agent remaining connected to the interaction) of the chat interaction; this includes chat consultation agents and supervisors who are monitoring or coaching the chat interaction.

>> Back to Top

chat.auto-mark-done-non-owner-agent.timer

Default Value: 0

Valid Values: 0 to MAXINT

Changes Take Effect: Immediately

Dependencies: interaction.disposition.is-mandatory, chat.auto-mark-done-non-owner-agent

Introduced: 8.5.128.07

Related Options: chat.auto-mark-done-non-owner-agent, chat.auto-mark-done-owner-agent.timer

Specifies the time, in seconds, before a chat interaction auto closes if the agent is not the owner (not the last agent remaining connected to the interaction) of the chat interaction; this includes chat consultation agents and supervisors who are monitoring or coaching the chat interaction.

>> Back to Top

chat.auto-mark-done-owner-agent

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediately

Dependencies: interaction.disposition.is-mandatory

Introduced: 8.5.128.07

Related Options: chat.auto-mark-done-non-owner-agent, chat.auto-mark-done-owner-agent.timer

Specifies whether chat interactions are automatically closed and marked done when the contact disconnects if the agent is the owner (the last agent remaining connected to the interaction) of the

chat interaction.

>> Back to Top

chat.auto-mark-done-owner-agent.timer

Default Value: 0

Valid Values: 0 to MAXINT

Changes Take Effect: Immediately

Dependencies: interaction.disposition.is-mandatory, chat.auto-mark-done-owner-agent

Introduced: 8.5.128.07

Related Options: chat.auto-mark-done-owner-agent, chat.auto-mark-done-non-owner-agent.timer

Specifies the time, in seconds, before a chat interaction auto closes if the agent is the owner (the last agent remaining connected to the interaction) of the chat interaction.

>> Back to Top

chat.client.prompt-color

Default Value: #FFAF4F0B

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain

color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the text of the messages entered by the target client in the Chat view.

>> Back to Top

chat.client.text-color

Default Value: #FF3D464D

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain

color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Color of the client text in the Chat view. The HTML format is used to set the value. I.e.: #FFFF0000 for

a red color.

>> Back to Top

chat.emojis-business-attribute

Default Value:

Valid Values: Valid Name of Business Attribute. **Changes Take Effect:** At the next interaction.

Introduced: 8.5.115.17

Specify Name of Business Attribute contained Emojis definition.

>> Back to Top

chat.enable-auto-disconnect

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the chat session is automatically disconnected if the agent is the last party remaining in the chat session.

>> Back to Top

chat.historical.maximum-age

Default Value: 0

Valid Values: 0 or any positive integer. **Changes Take Effect:** At the next interaction.

Introduced: 8.5.122.08

Specifies the number of days of previous chat sessions with the current contact are to be displayed in the Chat interaction view before the current chat session. The value 0 means that no previous chat sessions are displayed. A maximum of 3000 messages can be displayed.

>> Back to Top

chat.max-attachments-files

Default Value: 0

Valid Values: Any valid positive integer between 0 and 100. 0 means no limits.

Changes Take Effect: At the next interaction.

Introduced: 8.5.115.17

The total maximum number of files that agents can attach to chat interaction. An error message is displayed to the agent if the total number of attached files exceeds this value. The value 0 means that there is no restriction.

>> Back to Top

chat.max-attachments-size

Default Value: 0

Valid Values: Any valid positive integer between 0 and 1000. 0 means no maximum.

Changes Take Effect: At the next interaction.

Introduced: 8.5.115.17

The total maximum number of megabytes of files that agents can attach to chat interaction. An error

message is displayed to the agent if the total number of megabytes for all attached files exceeds this value. The value 0 means that there is no restriction.

>> Back to Top

chat.max-file-size

Default Value: 0

Valid Values: Any valid positive integer between 0 and 1000000. 0 means no maximum.

Changes Take Effect: At the next interaction.

Introduced: 8.5.115.17

The maximum file size in kilobytes that agents can attach to chat interaction. An error message is displayed to the agent if the file size exceeds this value. The value 0 means that there is no restriction.

>> Back to Top

chat.new-message-bell

Default Value:

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric

Changes Take Effect: Immediately

Specifies the configuration string for the new Chat Message sound. For example: "Sounds\bell.mp3|7|0|primary" The value has four components that are separated by the character '|':

- 1) The file name and folder relative to the application folder. It may happen that on some virtual desktop, MP3 or other sounds format cannot be rendered by Direct Show filters. Files format that can be played (.wav, ...) with Direct Show must be used here.
- 2) The priority. The higher the integer the higher the priority.
- 3) The duration:
 - a) 0 means play the whole sound one time.
 - b) An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4) The output devices:
 - a) primary means plays on the default output device.
 - b) secondary means plays on the output device specified by the application.secondary-audio-out-device option.
 - c) both means plays on both default output device and the output device specified by the application.secondary-audio-out-device option.

chat.nickname

Default Value: \$Agent.UserName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list:

Agent.UserName, Agent.LastName, Agent.FirstName, Agent.FullName, Agent.EmployeeId, AttachedData Agent.EmployeeId

(Y: attached data key name).

Changes Take Effect: At the next interaction.

Specifies the nickname that is used to join the chat session (presented to the customer) by a string that can contain regular characters and the following field codes:

\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.FullName\$,\$Agent.EmployeeId\$,\$AttachedData (Y: attached data key name). This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

chat.on-hold-queue

Default Value: No default value

Valid Values: Any valid Script name of type 'Interaction Queue'. **Changes Take Effect:** At the next attempt to put a chat in a queue.

Introduced: 8.5.128.07

Specifies the Interaction Queue where the chat interaction is placed when the agent clicks **Place chat on hold**. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

chat.other-agent.prompt-color

Default Value: #FF295B00

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain

color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the text of the messages entered by the target agent in the Chat view.

>> Back to Top

chat.other-agent.text-color

Default Value: #FF3D464D

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain

color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Color of the other agent text in the Chat view. The HTML format is used to set the value. I.e.: #FFFF0000 for a red color.

>> Back to Top

chat.pending-response-to-customer

Default Value: 30,50

Valid Values: A comma-separated list value: warning time, maximum time

Changes Take Effect: At the next interaction.

Defines two alarm thresholds, in seconds, that warn agents that they have a pending response to a chat from a customer. Three levels are displayed: before the warning time, between the warning time and the maximum time, and after the maximum time.

>> Back to Top

chat.pending-response-to-customer-bell

Default Value:

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric

/alues.

Changes Take Effect: Immediately

Introduced: 8.5.122.08

Related Options: application.secondary-audio-out-device

Specifies the configuration string for the chat pending response sound. For example: "Sounds\ chord.mp3|7|0|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. It may happen that on some virtual desktop, MP3 or other sounds format cannot be rendered by Direct Show filters. Files format that can be played (.wav, ...) with Direct Show must be used here.
- 2. The priority. The higher the integer the higher the priority.
- 3. The duration:
 - 1. 0 means play the whole sound one time.
 - 2. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. The output devices:
 - 1. primary means plays on the default output device.
 - secondary means plays on the output device specified by the application.secondary-audio-outdevice option.
 - 3. both means plays on both default output device and the output device specified by the application.secondary-audio-out-device option.

chat.prompt-for-end

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies if application prompts a confirmation message when a user clicks the 'end' button. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

chat.reconnect-attempts

Default Value: 5

Valid Values: from 0 to MAXINT

Changes Take Effect: At the next interaction.

Defines the number of reconnection attemps to the chat session to make in the case of a connection loss.

>> Back to Top

chat.reconnect-timeout

Default Value: 10

Valid Values: from 0 to MAXINT

Changes Take Effect: At the next interaction.

Specifies the duration, in seconds, between each attemp to reconnect to the chat session in the case of a connection loss.

>> Back to Top

chat.restricted-attachment-file-types

Default Value:

Valid Values: A comma-separated list of file extensions to be restricted.

Changes Take Effect: At the next interaction.

Introduced: 8.5.115.17

Specifies the list of file types (for example: exe, bat, and so on) that agents cannot attach to a chat interaction. An error message is displayed to the agent if the file type is restricted. The corresponding file does not appear in the attachment list.

chat.rich-media-widget-width

Default Value: 300

Valid Values: An integer value between 100 and 500.

Changes Take Effect: At the next interaction.

Introduced: 8.5.150.06

Specifies the width, in pixels, of Rich Media in a chat interaction. The value of this option affects the minimum width of the Chat transcript view.

>> Back to Top

chat.ringing-bell

Default Value: Sounds\Ring.mp3|10|-1|primary

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric

values.

Changes Take Effect: At the next interaction.

Specifies the path of the sound file that is played when Chat interaction is ringing. For example: "Sounds\Ring.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1) The file name and folder relative to the application folder. It may happen that on some virtual desktop, MP3 or other sounds format cannot be rendered by Direct Show filters. Files format that can be played (.wav, ...) with Direct Show must be used here.
- 2) The priority. The higher the integer the higher the priority.
- 3) The duration:
 - a) -1 means plays and repeats until an explicit message stops it (I.e.: the established event stops the ringing sound).
 - b) 0 means play the whole sound one time.
 - c) An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4) The output devices:
 - a) primary means plays on the default output device.
 - b) secondary means plays on the output device specified by the application.secondary-audio-out-device option.
 - c) both means plays on both default output device and the output device specified by the application.secondary-audio-out-device option.

>> Back to Top

chat.show-attachment-image-thumbnail

Default Value: never

Valid Values: A value from the following list: never, always, online, history

Changes Take Effect: At the next interaction.

Introduced: 8.5.115.17

Specifies whether to display the icon of an attached image file in chat transcript as image thumbnail (or as generic file) in the online session, the interaction history, or both.

>> Back to Top

chat.show-unread-notification

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next sent message.

Introduced: 8.5.122.08

Specifies whether the unread message notification is displayed in the chat transcript. When the message is read, the notification icon disappears. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

chat.simple-transcript

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.122.08

Specifies whether the chat transcript is displayed as simple lines of text lines instead of text blocks.

>> Back to Top

chat.system.text-color

Default Value: #FF8C8C8C

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain

color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range)...

Changes Take Effect: Immediately.

Specifies the color of the text for system messages in the Chat view.

>> Back to Top

chat.time-stamp

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Specifies whether the time stamp is displayed in the Chat transcript area.

>> Back to Top

chat.toast-information-key

Default Value: Subject

Valid Values:

Changes Take Effect: At the next interaction.

Specifies whether the Information area is displayed in the Chat interaction notification. The option specifies the name of the attached data key that contains the information. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

chat.transcript-enable-history-filters

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.132.05

Specifies that the value specified for the contact.history.filters-<attribute> option is used to filter the history-based part of the chat transcript.

>> Back to Top

chat.transcript-message-text-direction

Default Value: Itr **Valid Values:** Itr or rtl

Changes Take Effect: At the next interaction.

Introduced: 8.5.140.08

Related Options: accessibility.visual-impairment-profile, chat.simple-transcript

Specifies whether messages in the chat transcript are displayed with a left-to-right (default) or a right-to-left reading layout. Use this option for chat interactions where contacts are using a right-to-left reading language. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy. This option has no effect if the value of the accessibility.visual-impairment-profile option and/or the value of the chat.simple-transcript is set to true.

>> Back to Top

chat.typing-isenabled

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Modified: 8.5.108.11

Specifies whether typing notification is enabled. It should be disabled for Chat Server lower than 8.0.1.

Warning

If the Chat - Can Preview Customer Typing privilege is also granted, and you have configured eServices to hide sensitive personal information that is entered by the contact during the chat, agents will be able to see the information as it is entered, but not after then contact sends it.

Added: 8.5.108.11

>> Back to Top

chat.typing-timeout

Default Value: 10

Valid Values: from 0 to MAXINT

Changes Take Effect: At the next interaction.

Defines the duration, in seconds, that the typing notification is displayed after the last keystroke and before the agent or contact sends their message.

>> Back to Top

chatserver.addp.local-timeout

Default Value: 0

Valid Values: 0 to MAXINT

Changes Take Effect: At the next interaction.

Introduced: 8.5.104.15

Specifies the duration, in seconds, that Workspace sends polling signals to the Chat Server. The value 0 means this functionality is disabled. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

chatserver.addp.remote-timeout

Default Value: 0

Valid Values: from 0 to MAXINT

Changes Take Effect: At the next interaction.

Introduced: 8.5.104.15

Specifies the duration, in seconds, that Chat Server sends polling signals to Workspace. The value 0 means this functionality is disabled. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

chatserver.addp.trace-mode

Default Value: off

Valid Values: One value from this list: client,remote,full,off

Changes Take Effect: At the next interaction.

Introduced: 8.5.104.15

Specifies the level of logging for ADDP.

- client: Select Trace On Client Side to turn on ADDP at the client. The client application will generate ADDP-related messages in its logs.
- remote: Select Trace On Server Side to turn on ADDP at the server. The application will generate ADDPrelated messages in its logs.
- full: Select Trace On Both Sides to turn on ADDP at both the client and server. The Client and server applications will both generate ADDP-related messages in their logs.
- off: Select Trace Is Turned Off to turn off ADDP tracing altogether. ADDP-related messages will not be generated.

This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

chatserver.ip-version

Default Value: auto

Valid Values: One value from this list; auto. '4.6'. '6.4'

Changes Take Effect: At the next interaction.

Introduced: 8.5.104.15

Specifies Internet Protocol version preference for the connection to the Chat Server.

- auto: Internet Protocol Version preference is specified in environment variable GCTI_CONN_IP_VERSION
 or key 'ip-version' in interactionworkspace.exe.config. If not specified in any of those 2 sources the
 value '4,6' is used.
- · 4,6: Force Internet Protocol Version to IPv4
- 6.4: Force Internet Protocol Version to IPv6

This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

chatserver.tls-mutual

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.148.04

Specifies whether Workspace is required to provide a certificate key in environments where Chat Server works in Mutual TLS mode.

>> Back to Top

contact.all-interactions-default-time-filter-main

Default Value: 1W

Valid Values: A value from the following list: All, 1M, 1W, 1D **Changes Take Effect:** When the application is started or restarted.

Introduced: 8.5.104.15

Specifies which Time Filter is selected by default in the Interaction Search view.

- All All interactions from Main UCS Data Base.
- 1M Interactions from Main UCS Data Base that were created less than 1 month ago.
- 1W interactions from Main UCS Data Base that were created less than 1 week ago.
- 1D interactions from Main UCS Data Base that were created less than 1 day ago.

>> Back to Top

contact.all-interactions-displayed-columns

Default Value: Status, Subject, Start Date, End Date

Valid Values: A comma-separated value list of interaction attribute names from the following list:

Subject, Status, ContactId, StartDate, Ownerld, EndDate, and custom attributes.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.104.15

Specifies the list of interaction attributes that are displayed in the result list of the Interaction Search view, for example: Status, Subject, StartDate, EndDate

>> Back to Top

contact.all-interactions-displayed-columns-treeview

Default Value: Status, Subject, Start Date

Valid Values: A comma-separated value list of interaction attribute names.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.126.07

Specifies the list of interaction attributes that are displayed in the tree view of the **Interaction Search** view, for example: Status, Subject, StartDate, EndDate

>> Back to Top

contact.all-interactions-quick-search-attributes

Default Value: Subject

Valid Values: A comma-separated value list of valid interaction attribute names.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.104.15

Specifies the interaction attributes that are used to search interactions in the quick search mode of the 'Interaction Search' view. Refer to Deployment Guide to get the definition of interaction attributes.

>> Back to Top

contact.available-directory-page-sizes

Default Value: 5,10,25,50

Valid Values: A comma-separated list of numbers that define the number of rows per result page

from which the agent can make selections.

Changes Take Effect: When the application is started or restarted.

The possible values for number of rows per page in the Contact Directory search result view.

>> Back to Top

contact.cache-timeout-delay

Default Value: 600

Valid Values: An integer from 1 through 3600.

Changes Take Effect: When the application is started or restarted.

The delay, in seconds, before the cache of the result of a Universal Contact Server request is cleared.

>> Back to Top

contact.date-search-types

Default Value: On,OnOrAfter,Before,Between **Valid Values:** Select at least one from the list.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.104.15

The list of search types that are available for the agent to use to search the contact database by date.

>> Back to Top

contact.default-directory-page-size

Default Value: 10

Valid Values: An integer from 1 through 50.

Changes Take Effect: When the application is started or restarted.

Dependencies: contact.available-directory-page-size

The default value for the number of rows per page in the Contact Directory search result view. The value must be defined in the contact.available-directory-page-size option.

>> Back to Top

contact.directory-advanced-default

Default Value: LastName,PhoneNumber

Valid Values: A comma-separated value list of Attribute Value names that correspond to searchable

contact field names.

Changes Take Effect: When the application is started or restarted.

Modified: 8.5.112.08

Specifies the list of contact attributes that are presented by default in the advanced search form of the Contact Directory view. Once an agent has personalized the list of advanced search attributes the personalized list of attributes takes precedence over this option in the subsequent sessions (8.5.112.08 and higher).

>> Back to Top

contact.directory-auto-append-star-to-search

Default Value: true **Valid Values:** true, false **Changes Take Effect: Introduced:** 8.5.117.18

Specifies whether an asterisk ("*") character is automatically appended to a Contact Directory keyword search to force a starts with search. When searching in languages, such as Chinese or Japanese, set this option to false and set up a CJK Analyzer in Universal Contact Server.

>> Back to Top

contact.directory-default-mode

Default Value: ListView

Valid Values: A value from the following list: ListView. GridView

Changes Take Effect: Immediately.

Specifies which view of the Contact Directory is displayed by default.

- · ListView: Quicker search performance and tokenized search items, but no sort on the result.
- GridView: Results are sortable result, but the search is less powerful, and the search items are nontokenized.

>> Back to Top

contact.directory-displayed-columns

Default Value: LastName,FirstName,PhoneNumber,EmailAddress

Valid Values: A comma-separated value list of Attribute Value names corresponding to contact field

names, for example: LastName, FirstName, PhoneNumber, EmailAddress. **Changes Take Effect:** When the application is started or restarted.

The list of contact fields displayed when the results of a contact search is rendered.

>> Back to Top

contact.directory-enabled-modes

Default Value: ListView, GridView

Valid Values: A comma-separated value list of views from the following list: ListView, GridView.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.105.12

Specifies which view of the Contact Directory can be selected.

- ListView: Quicker search performance and tokenized search items, but no sort on the result. This view can be enabled only if the 'Contact' index is activated in UCS.
- GridView: Results are sortable result, but the search is less powerful, and the search items are nontokenized.

>> Back to Top

contact.directory-permissions.<ContactAttributeName>

Default Value:

Valid Values: In a key, a valid searchable contact attribute name. In a value, a comma-separated list of strings applicable to the specified contact attribute.

Changes Take Effect: At the next contact search.

This option can be used as a template to specify a contact attribute name (in a key) and the associated values (in a value) that is used to restrict the access of specific agents to the Contact Directory view. Modifies the search logic whenever the Application, Tenant, Agent Group, or Agent makes a contact search request based on a set of attribute values that are configured for contacts in your Universal Contact Server database. Refer to the Restricted Access section for information about

how to configure this option.

>> Back to Top

contact.directory-search-attributes

Default Value: LastName,FirstName,PhoneNumber,EmailAddress

Valid Values: A comma-separated value list of Attribute Value names that correspond to searchable

contact field names.

Changes Take Effect: When the application is started or restarted.

The list of Contact fields that can be used as search parameters

>> Back to Top

contact.directory-search-types

Default Value: begins-with, is

Valid Values: A comma separated list of values of strings from this list: contains, begins-with, is.

Changes Take Effect: When the application is started or restarted.

Modified: 8.5.110.13

The list of search types that are available for the agent to use to search the contact database in advanced mode. Specifying the value 'contains' may have a performance impact on Universal Contact Server.

>> Back to Top

contact.displayed-attributes

Default Value: Title,FirstName,LastName,PhoneNumber,EmailAddress

Valid Values: A comma-separated value list of Attribute Value names that correspond to contact

field names, for example: LastName, FirstName, PhoneNumber, EmailAddress.

Changes Take Effect: When the application is started or restarted.

The list of Contact fields that are displayed when a Contact record is rendered.

>> Back to Top

contact.editable-attributes

Default Value: \$All\$

Valid Values: A comma-separated value list of Attribute Value names that correspond to contact

field names, for example: LastName, FirstName, PhoneNumber, EmailAddress.

Changes Take Effect: When the application is started or restarted.

Dependencies: contact.displayed-attributes

Introduced: 8.5.101.14

The list of Contact attributes that can be changed by Agent. 'Contact - Can Edit Contact' privilege must be granted. A comma-separated value list of Attribute Value names that correspond to contact field names: either \$All\$ or one or more of the values that are defined by the contact.displayed-attributes option. If this option is left blank (""), no fields are editable.

>> Back to Top

contact.history-advanced-default

Default Value: Status, Start Date

Valid Values: A comma-separated value list of interaction attributes. **Changes Take Effect:** When the application is started or restarted.

Modified: 8.5.104.15, 8.5.112.08

Specifies the list of interaction attributes that are presented by default in the advanced search form of the **Contact History**, **My History** and **Interaction Search** views. Once an agent has personalized the list of advanced search attributes, the personalized list of attributes takes precedence over this option in subsequent sessions (8.5.112.08 and higher).

>> Back to Top

contact.history-auto-append-star-to-search

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next search

Introduced: 8.5.117.18

Specifies whether an asterisk ("*") character is automatically appended to a History keyword search to force a starts with search. When searching in languages, such as Chinese or Japanese, set this option to false and set up a CJK Analyzer in Universal Contact Server.

>> Back to Top

contact.history-custom-attribute-values.<attribute-name>

Default Value:

Valid Values: A comma-separated value list of interaction attributes. **Changes Take Effect:** When the application is started or restarted.

Introduced: 8.5.104.15

Specifies a list of attribute value names that are used to create a drop-down menu that contains valid values of custom interaction attributes in the Advanced Search mode of **Contact History**, **My History**, and **Interaction Search** views. Use this option as a template, modifying its name by replacing attribute-name by the name of an interaction attribute configured to be displayed in the **Advanced Search** view. You can define a display name that can be localized to each of the possible values of this interaction attribute by creating the key

Contacts.ContactDirectoryView.CustomAttribute.<custom-attribute-name>.<attribute-value-name> in any dictionary file of the corresponding language and assigning it a "Content"

attribute that contains the display name.

>> Back to Top

contact.history-custom-attributes-search-types

Default Value: is

Valid Values: is, begins-with

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.136.07

Specifies whether an 'exact match' (is) or a 'starts with' (begins-with) mode is applied when an agent makes an interaction search with a custom attribute.

>> Back to Top

contact.history-default-time-filter-main

Default Value: 1M

Valid Values: A value from the following list: All, 1M, 1W, 1D

Changes Take Effect: When the application is started or restarted, or at the next interaction.

Specifies which Time Filter is selected by default in the 'Contact History' view when an agent accesses the main history data source.

- · All: all interactions from Main UCS Data Base.
- 1M: interactions from Main UCS Data Base that were created less than 1 month ago.
- 1W: interactions from Main UCS Data Base that were created less than 1 week ago.
- 1D: interactions from Main UCS Data Base that were created less than 1 day ago.

>> Back to Top

contact.history-displayed-columns

Default Value: Status, Subject, Start Date, End Date, OwnerId

Valid Values: A comma-separated value list of contact history items to display in the Interaction

Search view -- for example: Status, Subject, Start Date, End Date, Ownerld. **Changes Take Effect:** When the application is started or restarted.

Specifies the list of contact history items that are displayed in the Interaction Search view.

contact.history-displayed-columns-treeview

Default Value: Status, Subject, Start Date

Valid Values: A comma-separated value list of contact history items to display in the threaded view

of interactions, for example: Status, Subject, StartDate, EndDate, Ownerld **Changes Take Effect:** When the application is started or restarted.

Specifies the list of contact history items that are displayed in the threaded view of interactions.

>> Back to Top

contact.history.filters-<attribute>

Default Value:

Valid Values: In the key, a valid searchable interaction attribute name. In the value, a commaseparated list of strings applicable to the specified interaction attribute. Use the \$All\$ and \$0ther\$ keywords to enable filtering on "all" or "other" values for this attribute.

Changes Take Effect: At the next contact search.

Modified: 8.5.104.15

This option can be used as a template to specify an interaction attribute name (in a key) and the associated values (in a value) that is used to automatically filter any list of interactions displayed in **Contact History**, **My History**, and **Interaction Search** views. Refer to Managing Contacts for more information. In a key, a valid searchable interaction attribute name. In the value, a comma-separated list of strings applicable to the specified interaction attribute. Use the \$All\$ and \$0ther\$ keywords to enable filtering on "all" or "other" values for this attribute.

>> Back to Top

contact.history.highlight-current-interaction

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction

Introduced: 8.5.117.18

Specifies whether the current interaction is highlighted in the interactions list or tree of the Contact History view.

>> Back to Top

contact.history.media-filters

Default Value: voice, email, chat, sms

Valid Values: A comma-separated value of valid media type names including:

voice, email, chat, sms, facebook, facebooksession, facebook privatemessage, twitter, twitter direct

Changes Take Effect: When the application is started or restarted.

Modified: 8.5.104.15, Social Media Plugin 9.0.002.05

Specifies the list of media types that can be used to filter the 'Contact History', 'My History', and the result list of 'Interaction Search'.

>> Back to Top

contact.history-quick-search-attributes

Default Value: Subject

Valid Values: A comma-separated value list of valid interaction attribute names.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.104.15

Specifies the interaction attributes that are used to search interactions in the quick search mode of the 'Contact History' view. Refer to Deployment Guide to get the definition of interaction attributes.

>> Back to Top

contact.history-search-attribute-group.<group-name>

Default Value:

Valid Values: A comma-separated value list of interaction attributes. **Changes Take Effect:** When the application is started or restarted.

Introduced: 8.5.104.15

Specifies a group of History search attributes.

Use this option as a template and modify its name by replacing the <group-name> by an actual name of group that will appear in Advanced Search mode of 'Contact History', 'My History' and 'Interaction Search' views.

You can define a localizable display name to this group by creating the key

'Contacts.InteractionSearchView.Group.<group-name>' in any dictionary file of the corresponding language and assigning it a 'String' attribute containing the display name.

>> Back to Top

contact.history-search-attributes

Default Value: Status, Start Date, End Date, Subject

Valid Values: A comma-separated value list of Interaction attributes. **Changes Take Effect:** When the application is started or restarted.

Modified: 8.5.104.15

Specifies the list of interaction attributes that an agent can use in the 'Advanced Search' mode of 'Contact History', 'My History' and 'Interaction Search' views.

>> Back to Top

contact.history.voice-detail-attributes

Default Value: Date, Contact, Phone Number, Duration

Valid Values: A comma-separated value list of Attribute Value names that correspond to voice calls:

Date, Contact, PhoneNumber, Duration.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.144.05

Specifies the list of voice call attributes that are displayed History Details view.

>> Back to Top

contact.last-called-agent.enable

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

When set to true, the the attributes LastCalledAgent_EmployeeID, LastCalledAgent_TimeStamp, LCA_EmplID_<interaction-media-type> and LCA_TimeStamp_<interaction-media-type> of the contact are set in contact profile when an interaction is presented to the Agent.

This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

Note: This option is taken into account only when the option 'contact.last-called-agent.<media-type>.enable' is not defined for the applicable media type.

>> Back to Top

contact.last-called-agent.<media-type>.enable

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

This option can be used as a template to a create a media specific option. When set to true, the attributes LastCalledAgent_EmployeeID, LastCalledAgent_TimeStamp, LCA_EmplID_<interaction-media-type> and LCA_TimeStamp_<interaction-media-type> of the contact are set in contact profile when an interaction of the given media type is presented to the Agent.

This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

Note: This option overwrites the contact.last-called-agent.enable option.

Use the 'voice-campaign' media-type to define the lookup behavior in the context of outbound campaign interactions.

>> Back to Top

contact.lookup.auto-assign-mode

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction

Dependencies: contact.lookup.enable

Introduced: 8.5.117.18

Specifies contact lookup behavior if the value of contact.lookup.enable is set to true.

- true: If there is only one contact in the UCS database, that contact is assigned automatically. If there are two or more contact in the UCS database, the first one is assigned to the interaction automatically.
- false: If there is only one contact in the UCS database, that contact is assigned automatically. If there
 are two or more contacts, these are displayed in the Contact view of the interaction and the agent must
 either select one, search for a different contact, or create a new contact.
 This option can be overridden by a routing strategy, as described in Overriding Options by Using a
 Routing Strategy.

>> Back to Top

contact.lookup.enable

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Activates the Workspace features that rely on the Universal Contact Server (UCS) for contact lookup when an interaction is presented to the Agent. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

This option is taken into account only when attached data 'IdentifyCreateContact' is not set in the interaction and the contact.lookup.<media-type>.enable option is not defined for the applicable media type.

>> Back to Top

contact.lookup.enable-create-contact

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Dependencies: contact.lookup.enable

When option contact.lookup.enable is set to true, this option specifies that the Universal Contact Server (UCS) can create a contact if the initial search cannot find any existing contact.

This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

Note: This option is taken into account only when attached data 'IdentifyCreateContact' is not set in the interaction and the contact.lookup.-media-type-zenable-create-contact option is not defined for the applicable media type.

contact.lookup.voice.use-dialed-phone-number

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

When the value of this option is set to true, Workspace executes the Universal Contact Server (UCS) Contact Look-up request using the normalized value of the number that was manually dialed by the agent.

Note: The normalized phone number is the string that results from the execution of the logic that is configured by the expression.phone-number.supported-characters option and before the dialplan-rule-<name> is applied. When the value is set to false, Workspace applies the Contact Lookup with the phone number that is returned by the T-Server in the EventDialing, which can contain the string transformed by the execution of the dialing rules.

>> Back to Top

contact.lookup.<media-type>.auto-assign-mode

Default Value: true **Valid Values:** true, false **Changes Take Effect:**

Dependencies: contact.lookup.<media-type>.enable

Introduced: 8.5.117.18

Specifies contact lookup behavior if Contact lookup is enabled for the specified media type.

- true: If there is only one contact in the UCS database, that contact is assigned automatically. If there are two or more contact in the UCS database, the first one is assigned to the interaction automatically.
- false: If there is only one contact in the UCS database, that contact is assigned automatically. If there
 are two or more contacts, these are displayed in the Contact view of the interaction and the agent must
 either select one, search for a different contact, or create a new contact.
 This option can be overridden by a routing strategy, as described in Overriding Options by Using a
 Routing Strategy.

>> Back to Top

contact.lookup.<media-type>.enable

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Activates the Workspace features that rely on Universal Contact Server (UCS) for contact lookup when an interaction of the given media type is presented to the Agent.

This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

Note: This option overwrites the contact.lookup.enable option. It is not taken into account when the

attached data 'IdentifyCreateContact' is set in the interaction.
Use the 'voice-campaign' media-type to define the lookup behavior in the context of outbound campaign interactions.

>> Back to Top

contact.lookup.<media-type>.enable-create-contact

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

When contact lookup is enabled in the context of the current interaction, this option specifies that the Universal Contact Server (UCS) can create a contact if the initial search cannot find any existing contact.

This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

Note: This option overwrites the contact.lookup.enable-create-contact option. It is not taken into account when the attached data 'IdentifyCreateContact' is set in the interaction.

Use the 'voice-campaign' media-type to define the lookup and create behavior in the context of outbound campaign interactions.

>> Back to Top

contact.mandatory-attributes

Default Value: FirstName, LastName

Valid Values: A comma-separated value list of Attribute Value names that correspond to contact

field names, for example: LastName, FirstName, PhoneNumber, EmailAddress.

Changes Take Effect: When the application is started or restarted.

The list of Contact fields that must be completed for a contact.

>> Back to Top

contact.metrics.enable-interactions-in-progress

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Activates the Workspace features that display the number of eServices interaction that are in progress in the current contact history.

contact.metrics.time-frame-customer-notification

Default Value: 1

Valid Values: An integer value meaning a number of days. If set to 0, no metrics area.

Changes Take Effect: When the application is started or restarted.

Specifies the search timeframe, in days, from which existing open and closed interactions are to be reported. If the value is set to 0, the feature is disabled. If the value is set to a number that is greater than 0, the feature that displays in the **Interaction Search** view the number of interactions that were sent or received by the contact for the specified number of days is activated.

>> Back to Top

contact.multi-value-attribute-display. < contact-attribute >

Default Value: Value, Description

Valid Values: A comma-separated list of fields from the following list: Value, Description.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.144.05

Specifies the list of fields that are used to display the Contact Attributes that can have multiple values in user interface areas such as **Team Communicator**, **Contact Directory**, and the interaction **Party** contextual menus. The <contact-attribute> placeholder represents the name of the contact attribute. At this time, only the **PhoneNumber** attribute is supported.

>> Back to Top

contact.multiple-value-attributes

Default Value: EmailAddress.PhoneNumber

Valid Values: A comma separated value list of Attribute Value names that correspond to contact

field names.

Changes Take Effect: When the application is started or restarted.

A list of contact attributes that can support multiple values.

>> Back to Top

contact.multiple-value-attributes-enable-default-description

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.141.04

Specifies whether the default Business Attribute value of a drop-down list is automatically populated in the associated contact attribute field of the Contact Information tab. If set to true, the default value

is set. If set to false, no value is set by default.

>> Back to Top

contact.myhistory-default-time-filter-main

Default Value: 1W

Valid Values: A value from the following list: All, 1M, 1W, 1D **Changes Take Effect:** When the application is started or restarted.

Specifies which Time Filter is selected by default in the 'My History' view when an agent accesses the main history data source.

- · All: all interactions from Main UCS Data Base.
- 1M: interactions from Main UCS Data Base that were created less than 1 month ago.
- 1W: interactions from Main UCS Data Base that were created less than 1 week ago.
- 1D: interactions from Main UCS Data Base that were created less than 1 day ago.

>> Back to Top

contact.myhistory-displayed-columns

Default Value: Status, Subject, Start Date, End Date

Valid Values: A comma-separated value list of interaction attribute names.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.104.15

Specifies the list of interaction attributes that are displayed in the 'My History' view, for example: Status, Subject, StartDate, EndDate.

>> Back to Top

contact.myhistory-displayed-columns-treeview

Default Value: Status, Subject, Start Date

Valid Values: A comma-separated value list of interaction attribute names.

Changes Take Effect: When the application is started or restarted.

Modified: 8.5.110.13

Specifies the list of interaction attributes that are displayed in the tree view of the **My History** view, for example: Status, Subject, StartDate, EndDate.

contact.myhistory-quick-search-attributes

Default Value: Subject

Valid Values: A comma-separated value list of valid interaction attribute names.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.104.15

Specifies the interaction attributes that are used to search interactions in the quick search mode of the **My History** view. Refer to Deployment Guide for the list of interaction attributes

>> Back to Top

contact.threading-ucs-interaction.enable

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Activates the Workspace feature that associates interactions that are submitted during multi-channel contact communication, such as smssession, in threads in Universal Contact Server history.

>> Back to Top

contact.timeout-delay

Default Value: 60

Valid Values: An integer from 1 through 3600.

Changes Take Effect: When the application is started or restarted.

The delay, in seconds, before a UCS request times out.

>> Back to Top

contact.ucs-interaction.<media-type>.enable-create

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Activates the Workspace feature that generates the interaction history in Universal Contact Server (UCS) based on the inbound and outbound interactions of type <media-type> handled by Workspace. Note: The option is forced to the value false for the media-types email, chat, and smssession, as Media Server is responsible for submitting those interactions in UCS.

This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

This option replaces contact.ucs-interaction.enable

>> Back to Top

contact.ucs-interaction.<media-type>.enable-lookup

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Activates the Workspace feature that looks up the history of existing interactions of the given <media-type> in Universal Contact Server (UCS) in order to update their content and status according to live interaction lifecycle.

Note: For the media type 'email', the value of this option is forced to true.

This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

contact.ucs-interaction.<media-type>.use-server-date

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies for the specified <media-type> whether Workspace sets the start and end dates of interactions by using the time of the local agent workstation, or uses the date and time specified by Universal Contact Server (UCS) when it creates or updates an interaction record in UCS.

Use this option as a template and modify its name by replacing the <media-type> by an actual media type defined in Management Framework.

Note: Depending on which UCS version you are using, setting this option to 'true' might generate an additional request to UCS when 'mark done' is set.

>> Back to Top

dial-plan-rule-<name>

Default Value:

Valid Values: pattern => digit translation # comment

Changes Take Effect: When the application is started or restarted.

Specifies a dial plan rule. This dial plan rules allows IW to transform the received digits into the actual digits that it uses to make the call. See description in deployment guide chapter XXX

Sample:

5XXX = >4351707 \$DIGITS} # This rule matches any 4-digit number starting with 5 and translates it to the number 43517075XXX'

'5002=>43517075002 # This rule matches the dialed number 5002' and translates it to the number 43517075002'

>> Back to Top

disaster-recovery.auto-restore

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted

Specifies whether agent should be relogged into the Preferred site as soon as it is available.

>> Back to Top

disaster-recovery.disable-login-errors

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether Workspace should display media voice login errors in the Login window.

>> Back to Top

disaster-recovery.enabled

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted

Modified: 8.5.106.19

Specifies whether Business Continuity (Disaster Recovery) functionality is activated for SIP Server, Configuration Server, and Statistic Server connections. Disaster Recovery is fully enabled on a particular connection only if the interaction-workspace/disaster-recovery.preferred-site option is configured in the annex of the corresponding server Application so that it matches the site names configured in the interaction-workspace/disaster-recovery.preferred-site or interaction-workspace/disaster-recovery.peer-site Workspace options.

>> Back to Top

disaster-recovery.eservices-random-delay-range

Default Value: 5

Valid Values: valid integer

Changes Take Effect: When the application is started or restarted

Introduced: 8.5.106.19

Related Options: disaster-recovery.eservices-site

Specifies the maximum time interval, in seconds, between the Disaster Recovery e-Services site update notification (through option 'disaster-recovery.eservices-site') and the actual connection attempt to the Interaction Server (Proxy) and Universal Contact Server (Proxy) of the new site.

The actual interval is a random value between 0 and this maximum time.

>> Back to Top

disaster-recovery.eservices-site

Default Value: No default value

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore, @ and space

characters.

Changes Take Effect:

Related Options: disaster-recovery.eservices-random-delay-range

Specifies the name of the the site that is to be used when connecting to Interaction Server (Proxy) and Universal Contact Server (Proxy) in a Disaster Recovery environment. The administrator must update this option to notify the system of the Disaster Recovery site switch-over. The actual reconnection to the new Interaction Server (Proxy) and Universal Contact Server (Proxy) occurs after a random time between 0 and the value specified by the option disaster-recovery.eservices-random-delay-range.

>> Back to Top

disaster-recovery.peer-site

Default Value: DRPeer

Valid Values: A unique symbolic name of the site or location to be used as the preferred login site.

Symbolic name of the site or location. Letters A to Z and a to z. Numbers 0 through 9. The

underscore, @ and space characters.

Changes Take Effect: When the application is started or restarted

Modified: 8.5.106.19

Related Options: disaster-recovery.preferred-site

Specifies the name of the site that is to be the secondary (Business Continuity peer) when connecting to SIP Server, Configuration Server or Statistic Server in a Disaster Recovery environment for the site that is specified by the <code>disaster-recovery.preferred-site</code> option. There must be a connection to this site in the Connections tab of the corresponding server.

>> Back to Top

disaster-recovery.preferred-site

Default Value: Preferred

Valid Values: A unique symbolic name of the site or location to be used as the preferred login site.

Letters A to Z and a to z. Numbers 0 through 9. The underscore, @ and space characters.

Changes Take Effect: When the application is started or restarted

Modified: 8.5.106.19

Related Options: disaster-recovery.peer-site

Specifies the site name to be used as preferred when connecting to SIP Server, Configuration Server or Statistic Server in a Disaster Recovery environment. That is, it specifies the name of the preferred connection site for the application, tenant, agent Group, or agent. There must be a connection to this site in the Connections tab of the corresponding server. This option should match the name specified by the disaster-recovery peer-site option that is configured on the server object.

>> Back to Top

disaster-recovery.restore-agent-state

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Modified: 8.5.106.19

Specifies whether Workspace should restore last agent state after logging on to the reserved SIP Server HA pair after the current SIP Server HA pair fails.

>> Back to Top

disaster-recovery.timeout

Default Value: 60

Valid Values: A valid positive integer.

Changes Take Effect: When the application is started or restarted

Modified: 8.5.106.19

Specifies the time in seconds to wait after the detection of the disconnection from current site of SIP Server, Configuration Server or Statistic Server before switching to the corresponding Disaster Recovery site.

>> Back to Top

disaster-recovery.wait-for-sipphone-timeout

Default Value: 0

Valid Values: 0 or a valid positive integer.

Changes Take Effect: When the application is started or restarted

Specifies time in seconds during which an agent should wait for SipEndpoint before a disaster is considered. A value of 0 means no limit.

display-format.acd-queue.name

Default Value:

\$ACDQueue.AnnexValue\$|\$ACDQueue.DictionaryValue\$|\$ACDQueue.Alias\$|\$ACDQueue.Number\$@\$ACDQueue.Lo Valid Values: A string that contains a compilation of characters and field codes from the following list:

\$ACDQueue. Number \$, \$ACDQueue. Alias \$, \$ACDQueue. Location \$, \$ACDQueue. Dictionary Value \$, \$ACDQueue. Annex Value \$,

Changes Take Effect: Immediately.

Modified: 8.5.101.14. 8.5.109.16, 8.5.117.18

Defines the display format of ACD Queues by specifying a string that contains the following field codes:

\$ACDQueue.Number\$,\$ACDQueue.Alias\$,\$ACDQueue.Location\$,\$ACDQueue.DictionaryValue\$,\$ACDQueue.Annex If all field codes are empty, the following field codes are used:

\$ACDQueue.Number\$@\$ACDQueue.Location\$.

>> Back to Top

display-format.action-code.name

Default Value: \$ActionCode.AnnexValue\$|\$ActionCode.DictionaryValue\$|\$ActionCode.Name\$ **Valid Values:** A string that contains a compilation of characters and field codes from the following

list: \$ActionCode.Name\$, \$ActionCode.DictionaryValue\$, \$ActionCode.AnnexValue\$.

Changes Take Effect: Immediately.

Introduced: 8.5.101.14 Modified: 8.5.109.16

Specifies the display format of the action codes that are displayed in Global Agent Status Control and My Channels view by specifying a string that contains a combination of string and field codes.

The \$ActionCode.AnnexValue\$ field code represents the display name of the object.

>> Back to Top

display-format.agent-group.name

Default Value: \$AgentGroup.AnnexValue\$|\$AgentGroup.DictionaryValue\$|\$AgentGroup.Name\$ **Valid Values:** A string that contains a compilation of characters and field codes from the following list: \$AgentGroup.Name\$, \$AgentGroup.DictionaryValue\$, \$AgentGroup.AnnexValue\$.

Changes Take Effect: Immediately.

Introduced: 8.5.101.14 Modified: 8.5.109.16

Specifies the display format of the skills that are displayed in Team Communicator, My Statistics, and Voice Mail by specifying a string that contains a combination of string and field codes.

The \$AgentGroup.AnnexValue\$ field code represents the display name of the object.

display-format.agent-name

Default Value: \$Agent.FullName\$|\$Agent.UserName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list:

\$Agent.FullName\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.Employeeld\$.

Changes Take Effect: Immediately.

Defines the display format of other agents tby specifying a string that contains the following field codes: \$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$.

>> Back to Top

display-format.business-attribute.name

Default Value:

\$BusinessAttribute.AnnexValue\$|\$BusinessAttribute.DictionaryValue\$|\$BusinessAttribute.DisplayName\$ **Valid Values:** A string that contains a compilation of characters and field codes from the following list: \$BusinessAttribute.Name\$, \$BusinessAttribute.DisplayName\$, \$BusinessAttribute.Description\$, \$BusinessAttribute.DictionaryValue\$, \$BusinessAttribute.AnnexValue\$. The

\$BusinessAttribute.AnnexValue\$ field code represents the display name of the object.

Changes Take Effect: Immediately.

Introduced: 8.5.101.14 Modified: 8.5.109.16

Specifies the display format of the business attributes that are displayed in Interaction View, Contact Directory, Contact Profile, Contact History, Media type, etc by specifying a string that contains a combination of string and field codes.

>> Back to Top

display-format.caller-name

Default Value: \$Contact.FirstName\$ \$Contact.LastName\$|\$Interaction.MainParty\$ **Valid Values:** A string that contains a composition of characters and field codes from the following list: \$Interaction.CaseId\$, \$Interaction.MainParty\$, \$Contact.X\$, \$AttachedData.Y\$, \$OutboundRecord.PhoneType\$, \$OutboundRecord.PhoneNumber\$, \$OutboundRecordField.Z\$ (where X: name of contact attribute, Y: attached data key name, Z: name of custom outbound field).

Changes Take Effect: Immediately.

Dependencies: interaction.case-data.content, toast.case-data.content

Modified: 8.5.143.08

Specifies the content of the 'Origin; field of the Case Information area. This option is enabled when the value of the interaction.case-data.content or toast.case-data.content option contains the **History** key. This content is typically used when placing an outbound call where the origin contains a string such as 'outbound call to xxx'.

The content is populated based on contact attributes, attached data keys, or outbound record fields that are defined by a string that contains at least one of the following field codes: \$Interaction.CaseId\$, \$Interaction.MainParty\$, \$Contact.X\$, \$AttachedData.Y\$, \$OutboundRecord.PhoneType\$, \$OutboundRecord.PhoneNumber\$, \$OutboundRecordField.Z\$ (where

X: name of contact attribute, Y: attached data key name, Z: name of custom outbound field). If the values of the default field codes are empty, the following field code is used: \$Interaction.MainParty\$.

>> Back to Top

display-format.case-name-format

Default Value: \$Contact.FirstName\$ \$Contact.LastName\$|\$Interaction.MainParty\$

Valid Values: A string that contains a compilation of characters and field codes from the following list: \$Case.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X: name of contact attribute,

Y: attached data key name)

Changes Take Effect: Immediately

Modified: 8.5.106.19

Defines the display format of the case label that is currently used by the application by specifying a string that contains the following field codes:

\$Case.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X: name of contact attribute, Y: attached data key name). This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

display-format.chat-agent-name

Default Value: \$ChatAgent.FullName\$|\$ChatAgent.Nickname\$|\$ChatAgent.UserName\$

Valid Values: A string that contains a compilation of characters and field codes from the following liet:

ChatAgent.FullName, ChatAgent.Nickname, ChatAgent.UserName, ChatAgent.LastName, ChatAgent.FirstName, ChatAgent.F

Changes Take Effect: Immediately.

Related Options: Documentation: Options: IW: WDE-interaction-workspace

Specifies the display format of chat nicknames for agents by specifying a string that can contain regular characters as well as the following field codes: \$ChatAgent.FullName\$, \$ChatAgent.Nickname\$,

\$ChatAgent.UserName\$,\$ChatAgent.LastName\$,\$ChatAgent.FirstName\$,\$ChatAgent.EmployeeId\$. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

display-format.chat-customer-name

Default Value: \$Contact.FirstName\$ \$Contact.LastName\$|\$Party.DisplayName\$

Valid Values: A string that contains a compilation of characters and field codes from the following list: \$ChatCustomer.Nickname\$, \$Contact.X\$, \$AttachedData.Y\$ (X: name of contact attribute, Y:

attached data key name)

Changes Take Effect: Immediately.

Introduced: 8.5.145.06

Specifies the display format of the party name using a string that can contain regular characters as well as the following field codes: \$ChatCustomer.Nickname\$, \$Contact.X\$, \$AttachedData.Y\$,

where X is the name of contact attribute and Y is the attached data key name. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

display-format.contact-name

Default Value: \$Contact.FullName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list:

\$Contact.FirstName\$,\$Contact.LastName\$,\$Contact.FullName\$,\$Contact.PhoneNumber\$,\$Contact.EmailAddress\$,

(x: name of custom contact business attribute)

Changes Take Effect: Immediately.

Introduced: 8.5.100.05

Specifies the display format of the contacts that are displayed in the Team Communicator and Contact Directory list views by specifying a string that contains a combination of string and field codes. The '|' character can be used to specify that fallback display rules are used in case the field codes do not contain any non-empty strings. Note: the FullName attribute is defined as a string of the string dictionary ('Display.Contact.Name.Format.FullName') which can be localized.

>> Back to Top

display-format.current-agent-name

Default Value: \$Agent.FullName\$|\$Agent.UserName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list:

\$Agent.FullName\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$.

Changes Take Effect: Immediately.

Defines the display format of the agent that is currently using the application by specifying a string that contains the following field codes:

\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$. If all field codes are empty, the following field codes are used: \$Agent.UserName\$.

>> Back to Top

display-format.customer-name-format

Default Value: \$Contact.FirstName\$ \$Contact.LastName\$|\$Party.DisplayName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list: \$Contact.X\$ (where X is the name of the contact attribute.)

Changes Take Effect: Immediately

Specifies the content of the text that represents the contact in the call participants area of the voice interaction interface. This option is applicable when a UCS Contact has been assigned either automatically or manually to the interaction. The content is populated based on contact attributes and attached data keys that are defined by a string that contains the following field codes:

\$Contact.X\$,\$AttachedData.Y\$ (where X is the name of the contact attribute, and Y is the attached data key name). This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

display-format.field.name

Default Value: \$Field.AnnexValue\$|\$Field.DictionaryValue\$|\$Field.Name\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list: \$Field.Name\$, \$Field.DictionaryValue\$, \$Field.AnnexValue\$

Changes Take Effect: Immediately

Introduced: 8.5.117.18

Specifies the display format of the fields that are displayed in the Record Information view.

>> Back to Top

display-format.folder.name

Default Value: \$Folder.AnnexValue\$|\$Folder.DictionaryValue\$|\$Folder.Name\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list: \$Folder.Name\$, \$Folder.DictionaryValue\$, \$Folder.AnnexValue\$.

Changes Take Effect: Immediately

Specifies the display format of the folders that are displayed in Disposition Code view and Case Data view.

>> Back to Top

display-format.interaction-callback-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$

\$Contact.LastName\$|\$Interaction.MainParty\$)

Valid Values: A string that contains a compilation of characters and field codes from the following list: \$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$

(where X is the name of contact attribute and Y is the attached data key name).

Changes Take Effect: Immediately.

If the main interaction is a Callback, this option defines the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by specifying a string of field codes:

\$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$At Where X is the name of the contact attribute and Y is the name of the attached data key.

display-format.interaction-chat-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$

\$Contact.LastName\$|\$Interaction.MainParty\$)

Valid Values: A string that contains a compilation of characters and field codes from the following list: \$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$

(where X is the name of contact attribute and Y is the attached data key name).

Changes Take Effect: Immediately.

If the main interaction is a Chat, this option defines the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by specifying a string of field codes:

\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ Where X is the name of the contact attribute and Y is the name of the attached data key.

>> Back to Top

display-format.interaction-email-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$

\$Contact.LastName\$|\$Interaction.MainParty\$)

Valid Values: A string that contains a compilation of characters and field codes from the following list: \$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$

(where X is the name of contact attribute and Y is the attached data key name).

Changes Take Effect: Immediately.

If the main interaction is an email, this option defines the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by specifying a string of field codes:

\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ Where X is the name of the contact attribute and Y is the name of the attached data key.

>> Back to Top

display-format.interaction-im-name

Default Value: \$Interaction.Type\$ \$Interaction.MainParty\$

Valid Values: A string that contains a compilation of characters and field codes from the following list: \$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.MainParty\$,\$AttachedData.Y\$ (where Y is the attached data key name).

Changes Take Effect: Immediately.

Modified: 8.5.106.19

If the main interaction is an Instant Message, this option defines the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by specifying a string of field codes:

\$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.MainParty\$,\$AttachedData.Y\$ Where Y is the name of the attached data key.

>> Back to Top

display-format.interaction-outbound-pull-preview-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$

\$Contact.LastName\$|\$Interaction.MainParty\$)

Valid Values: A string that contains a compilation of characters and field codes from the following list: \$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (where X is the name of contact attribute and Y is the attached data key name).

Changes Take Effect: Immediately.

If the main interaction is an Outbound Pull Preview, this option defines the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by specifying a string of field codes. Where X is the name of contact attribute, and Y is the attached data key name.

>> Back to Top

display-format.interaction-outbound-push-preview-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$

\$Contact.LastName\$|\$Interaction.MainParty\$)

Valid Values: A string that contains a compilation of characters and field codes from the following list: \$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (where X is the name of contact attribute and Y is the attached data key name).

Changes Take Effect: Immediately.

If the main interaction is an Outbound Push Preview, this option defines the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by specifying a string of field codes. Where X name of contact attribute, and Y is the attached data key name.

>> Back to Top

display-format.interaction-queue.name

Default Value:

\$InteractionQueue.AnnexValue\$|\$InteractionQueue.DictionaryValue\$|\$InteractionQueue.DisplayName\$ **Valid Values:** A string that contains a compilation of characters and field codes from the following list:

\$InteractionQueue.DisplayName\$,\$InteractionQueue.Name\$,\$InteractionQueue.Media\$,\$InteractionQueue.DictionChanges Take Effect: When the application is started or restarted.

Modified: 8.5.101.14, 8.5.109.16

Defines the display format of Interaction Queues by specifying a string that contains the following field codes:

\$InteractionQueue.Name\$,\$InteractionQueue.Media\$,\$InteractionQueue.DictionaryValue\$,\$InteractionQueue.Anno If all field codes are empty, the following field codes are used:

\$InteractionQueue.Media\$@\$InteractionQueue.Name\$.

>> Back to Top

display-format.interaction-sms-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$

\$Contact.LastName\$|\$Interaction.MainParty\$)

Valid Values: A string that contains a compilation of characters and field codes from the following list: \$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$

(where X is the name of contact attribute and Y is the attached data key name).

Changes Take Effect: Immediately.

If the main interaction is an SMS, this option defines the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by specifying a string of field codes:

\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$. Where X is the name of the contact attribute and Y is the name of the attached data key.

>> Back to Top

display-format.interaction-voice-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$

\$Contact.LastName\$|\$Interaction.MainParty\$)

Valid Values: A string that contains a compilation of characters and field codes from the following list: \$Interaction.Type\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (where X is the name of contact attribute and Y is the attached data key name).

Changes Take Effect: Immediately.

Modified: 8.5.106.19

If the main interaction media type is voice, this option defines the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by specifying a string of field codes:

\$Interaction.Type\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$. Where X is the name of the contact attribute and Y is the name of the attached data key.

>> Back to Top

display-format.interaction-workitem-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$

\$Contact.LastName\$|\$Interaction.MainParty\$)

Valid Values: A string that contains a compilation of characters and field codes from the following list: \$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (where X is the name of contact attribute and Y is the attached data key name).

Changes Take Effect: Immediately.

If the main interaction is a workitem, this option defines the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by specifying a string of field codes:

\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$. Where X is the name of the contact attribute and Y is the name of the attached data key.

>> Back to Top

display-format.outbound-record-name

Default Value: \$OutboundRecord.PhoneType\$ - \$OutboundRecord.PhoneNumber\$

Valid Values: A string that contains the following field codes:

\$OutboundRecord.PhoneType\$,\$OutboundRecord.PhoneNumber\$,\$OutboundRecordField.X\$ (where X

is the name of the custom outbound field). **Changes Take Effect:** At the next interaction.

Introduced: 8.5.143.08

Specifies how an outbound record from a record chain is displayed to an agent. The record is populated by a string of attributes that contains one or more of the following field codes: \$OutboundRecord.PhoneType\$, \$OutboundRecord.PhoneNumber\$, and \$OutboundRecordField.X\$, where X is the name of the custom outbound field.

>> Back to Top

display-format.party-name-format

Default Value: \$Party.DisplayName\$

Valid Values: A string that contains a compilation of characters or field codes from the following list:

\$Party.DisplayName\$,\$AttachedData.Y\$ **Changes Take Effect:** Immediately.

Specifies the display format of parties which have not been identified as a customer or an agent, by specifying a string that contains either the name or the following field codes: \$Party.DisplayName\$ (the party phone number) or \$AttachedData.Y\$ (Y is the attached data key name where the value will be used as party name). This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

display-format.routing-point.name

Default Value:

\$RoutingPoint.AnnexValue\$|\$RoutingPoint.DictionaryValue\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Number\$@\$RoutingValue\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Number\$@\$RoutingValue\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Number\$@\$RoutingValue\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Number\$@\$RoutingPoint.Alias\$|\$RoutingPoint.Number\$@\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Number\$@\$RoutingPoint.Alias\$|\$RoutingPoint.Number\$@\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Number\$@\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Number\$@\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Number\$@\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$RoutingPoint.Alias\$|\$R

\$RoutingPoint.Number\$,\$RoutingPoint.Alias\$,\$RoutingPoint.Location\$,\$RoutingPoint.DictionaryValue\$,\$RoutingPoint.Changes Take Effect: Immediately.

Modified: 8.5.101.14, 8.5.109.16

Defines the display format of Routing Points by specifying a string that contains the following field codes:

\$RoutingPoint.Number\$,\$RoutingPoint.Alias\$,\$RoutingPoint.Location\$,\$RoutingPoint.DictionaryValue\$,\$RoutingPoint all field codes are empty, the following field codes are used:

\$RoutingPoint.Number\$@\$RoutingPoint.Location\$.

>> Back to Top

display-format.skill.name

Default Value: \$Skill.AnnexValue\$|\$Skill.DictionaryValue\$|\$Skill.Name\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list: \$Skill.Name\$, \$Skill.DictionaryValue\$, \$Skill.AnnexValue\$.

Changes Take Effect: Immediately.

Introduced: 8.5.101.14 Modified: 8.5.109.16

Specifies the display format of the skills that are displayed in Team Communicator by specifying a string that contains a combination of string and field codes. The \$Skill.AnnexValue\$ field code represents the display name of the object.

>> Back to Top

display-format.virtual-queue.name

Default Value:

\$VirtualQueue.AnnexValue\$|\$VirtualQueue.DictionaryValue\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Number\$@\$VirtualQueue.Alias\$|\$VirtualQueue.Number\$@\$VirtualQueue.Alias\$|\$VirtualQueue.Number\$@\$VirtualQueue.Alias\$|\$VirtualQueue.Number\$@\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQueue.Alias\$|\$VirtualQue

\$Virtual Queue. Number \$, \$Virtual Queue. Alias \$, \$Virtual Queue. Location \$, \$Virtual Queue. Dictionary Value \$, \$Virtual Queue. Alias Alias

Changes Take Effect: Immediately. Modified: 8.5.101.14, 8.5.109.16

Specifies the display format of Virtual Queues by specifying a string that contains the following field codes:

\$VirtualQueue.Number\$,\$VirtualQueue.Alias\$,\$VirtualQueue.Location\$,\$VirtualQueue.DictionaryValue\$,\$VirtualQueue.If all field codes are empty, the following field codes are used:

\$VirtualQueue.Number\$@\$VirtualQueue.Location\$.

>> Back to Top

display-format.workbin.name

Default Value: \$Workbin.AnnexValue\$|\$Workbin.DictionaryValue\$|\$Workbin.DisplayName\$ **Valid Values:** A string that contains a compilation of characters and field codes from the following list: \$Workbin.Name\$, \$Workbin.DisplayName\$, \$Workbin.DictionaryValue\$, \$Workbin.AnnexValue\$.

Changes Take Effect: Immediately.

Introduced: 8.5.101.14 Modified: 8.5.109.16

Specifies the display format of the workbins that are displayed in Workbins view by specifying a string that contains a combination of string and field codes. The \$Workbin.AnnexValue\$ field code represents the display name of the object.

>> Back to Top

editor.font-size-units

Default Value: point

Valid Values: A valid font size unit. The following units are supported: pixel, point.

Changes Take Effect: At the next interaction.

Specifies whether points or pixels are used for the units of font size in the Rich Editor (HTML) view for email and other rich text/HTML based interactions.

>> Back to Top

editor.shortcuts.prefix

Default Value: #

Valid Values: Any valid string. Changes Take Effect: Immediately

Introduced: 8.5.118.10

Specifies the prefix to be entered before a standard response keyword. Standard response keywords can be used to automatically add standard responses to an editor view.

>> Back to Top

editor.user-agent-http-header

Default Value: Mozilla/4.0 (compatible; MSIE 7.0)

Valid Values: A string representing a valid 'User-Agent' HTTP header according to RFC 1945.

Changes Take Effect: At next interaction.

Introduced: 8.5.112.12

Specifies the 'User-Agent' HTTP header value set in the HTTP requests used by rich text/HTML editor to download external images.

>> Back to Top

email.attachment-download-timeout

Default Value: 20

Valid Values: An integer value between -1 and 3600.

Changes Take Effect: Immediately.

Defines the maximum duration, in seconds, of the download of an attachment. The value -1 means that there is no maximum time.

email.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether an e-mail interaction is automatically accepted when a Interaction Server Invite event is received. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

email.auto-answer.enable-reject

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction

Dependencies: email.auto-answer

Introduced: 8.5.105.12

Specifies whether the **Reject** button is available in the interaction notification when the value of email.auto-answer is set to true and the value of email.auto-answer.timer is greater than 0. The privilege to reject interactions must be granted. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

email.auto-answer.timer

Default Value: 0

Valid Values: Any integer greater than or equal to 0. **Changes Take Effect:** At the next interaction.

Dependencies: email.auto-answer

Introduced: 8.5.105.12

Specifies the time, in seconds, after which an incoming interaction is automatically answered if the value of email.auto-answer is set to true. If the value 0 is specified, interactions are immediately auto-answered. If any positive integer value is specified, then an interaction notification is displayed to the agent and a timer counts down the seconds until the interactions is auto-answered. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

email.can-change-text-direction

Default Value: false **Valid Values:** true, false **Changes Take Effect:** Specifies whether the **Right-to-left Text Direction** and **Left-to-right Text Direction** buttons are enabled in the outbound email editor. Agents can use these buttons to change the text field to left-to-right (LTR) script or right-to-left (RTL) script. This means that an email can have a mix of both LTR and RTL scripts. Enabling the option is not mandatory if agents are working exclusively in LTR or RTL scripts.

>> Back to Top

email.default-queue

Default Value:

Valid Values: Name of a valid Script object of type InteractionQueue

Changes Take Effect: At the next interaction.

Specifies the Interaction queue in which new or reply outbound e-mails are submitted.

>> Back to Top

email.forward.enable-cc-addresses

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.104.15

Specifies whether it is possible to add cc addresses when forwarding an inbound email as an attachment to an external resource.

>> Back to Top

email.forward.enable-instructions

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.104.15

Specifies whether it is possible for agents to add instructions when forwarding an inbound email as an attachment to an external resource.

>> Back to Top

email.forward.enable-multiple-to-addresses

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.104.15

Specifies whether it is possible to forward an inbound email as an attachment to multiple external resources.

>> Back to Top

email.forward-queue

Default Value:

Valid Values: Name of a valid Script object of type InteractionQueue

Changes Take Effect: Immediately.

Specifies the Interaction Queue in which inbound email interactions are placed when an agent forwards an inbound email interaction as an attachment to an external resource.

>> Back to Top

email.from-addresses

Default Value: \$EMAILSERVER\$

Valid Values: A valid Business Attribute name or \$EMAILSERVER\$. **Changes Take Effect:** When the application is started or restarted.

Modified: 8.5.115.17

A character string that specifies the name of the Business Attribute that contains the Attribute Values that are used as available from addresses of Email interactions. The value \$EMAILSERVER\$ specifies that from addresses are populated from the POP client sections of Email Server applications. The \$EMAILSERVER\$ value is applicable only if the Workspace Application object has a connection configured to an Interaction Server to which the Email Server is also connected. Note that this is not the case when Workspace connects to Interaction Server Proxies dedicated to Agents. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

email.from-addresses.force-default-on-reply

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Dependencies: email.from-addresses

Introduced: 8.5.143.08

In environments where the option email.from-addresses is set to a valid Business Attribute name, this option specifies whether the default From address of a reply email interaction is the default value configured in the Business Attribute (true) or the target inbound mailbox of the parent inbound email interaction (false).

email.html-format

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether or not the format of a new outbound email is html or plain text. When set to true, new email will be formatted in HTML.

>> Back to Top

email.include-original-text-in-reply

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the text of the original inbound email is included in the outbound reply email. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

email.include-standard-response-subject-on-insert

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.100.05

Specifies whether the subject of the Standard Response that is selected by the agent is included in the email subject when an agent inserts the Standard Response in the email interaction.

>> Back to Top

email.inline-forward-prefix

Default Value: Fwd:

Valid Values: Any valid character string. **Changes Take Effect:** Immediately.

Introduced: 8.5.113.11

Specifies the prefix, if any, that is added at the beginning of the subject of the original email to be forwarded. Does not apply to emails forwarded as an attachment. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

email.inline-forward-queue

Default Value:

Valid Values: Name of a valid Script object of type InteractionQueue

Changes Take Effect: Immediately.

Introduced: 8.5.113.11

Specifies the Interaction Queue in which outbound emails created for in-line forwarding are placed when agents clicks **Complete Forward**.

>> Back to Top

email.mandatory-subject

Default Value: false **Valid Values:** true, false

Changes Take Effect: At next attempt to send an email.

Introduced: 8.5.119.05

Specifies whether the subject of an outbound email must be specified to enable the Send operation.

- false: No control is applied on the content of the subject field.
- true: Email sending cannot be completed until the subject field is not empty. An error message is displayed.
- prompt: If the subject is empty, a confirmation box is displayed to prompt the agent to add a subject or proceed with sending without a subject.

>> Back to Top

email.max-attachments-size

Default Value: 0

Valid Values: Any valid positive integer. 0 means no maximum.

Changes Take Effect: At the next interaction.

The total maximum number of megabytes of files that agents can attach to an outbound e-mail interaction. An error message is displayed to the agent if the total number of megabytes for all attached files exceeds this value. The value 0 means that there is no restriction.

>> Back to Top

email.move-inbound-to-in-progress-workbin-on-reply

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction. Related Options: workbin.email.in-progress

Specifies where the parent inbound email resides after an agent clicks Reply.

- If the value is true, whenever an agent replies or replies-all to an inbound email interaction stored either in a personal in-progress, a shared workbin, or in Contact History, the inbound email interaction is moved to the workbin configured as the in-progress workbin (refer to the workbin.email.in-progress option).
- If the value is false, the behavior depends on the reply type. If the reply is done while the email is
 opened on the agent's desktop, the inbound email is moved to the workbin that is configured as the inprogress workbin. If the reply is done directly from a workbin or from history without opening the
 inbound email first, the inbound email remains in the personal or shared workbin, or in the queue.

Subsequent operations like Delete Draft, followed by 'Put back inbound email in workbin' or Interim Send followed by 'Put back inbound email in workbin' do not change the storage location of the inbound email.

>> Back to Top

email.outbound.copy-editable-case-data-in-inbound

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.141.04

Specifies whether editable case data is copied back to the original inbound email from an outgoing reply email interaction when it is sent. This option does not affect interim-send email interactions. If set to false, the original inbound email case data is not updated.

>> Back to Top

email.outbound.editable-bcc-addresses

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.114.08

Specifies if an agent can add Bcc addresses to a new or reply or forward outbound e-mail or edit the list of existing Bcc addresses that would have been added by another agent in a former draft edition of the new or reply or forward outbound e-mail. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

email.outbound.editable-cc-addresses

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.114.08

Specifies if an agent can add Cc addresses to a new or reply or forward outbound e-mail or edit the list of existing Cc addresses of a reply outbound e-mail populated by Workspace at the time the agent clicked 'reply all'. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

email.outbound.editable-to-addresses

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.114.08

Specifies if an agent can edit the list of 'To' addresses of a Reply Outbound E-Mail that is populated by Workspace at the time the agent clicked 'reply' or 'reply all'. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

email.outbound-queue

Default Value:

Valid Values: Name of a valid Script object of type InteractionQueue

Changes Take Effect: Immediately.

Specifies the Interaction Queue in which outbound emails are placed when agents click Send or Send Interim. This option is used only when Interaction Workflow does not set Queue for New Interactions, when it is routing inbound emails to agents.

>> Back to Top

email.prompt-for-done

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies if application prompts a confirmation message when a user clicks the 'done' button. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

email.pull-from-history-isenabled

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Specifies whether it is possible to pull an Email interaction from Contact History. This option is applicable only if at least one of the following privileges has been granted to the agent: Contact - Can Pull From Queue, Contact - Can Pull Interactions In Shared Workbins, and Contact - Can Pull Interactions In Workbins Not Owned By The User.

>> Back to Top

email.qa-review-dispositions-business-attribute

Default Value:

Valid Values: A valid name of a Business Attribute. **Changes Take Effect:** At the next interaction.

A character string that specifies the name of the Business Attribute that contains the Attribute Values that are used to populate the E-Mail QA Review Dispositions drop-down button (on the reviewer's desktop). This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

email.quote-char

Default Value: >

Valid Values: Any valid character string. **Changes Take Effect:** Immediately.

For outbound email that is formatted as plain text, specifies the characters that are used to quote the contents of the inbound email interaction in the outbound email interaction body.

>> Back to Top

email.quote-header

Default Value: On <date>, <contact> wrote: **Valid Values:** Any valid character string. **Changes Take Effect:** Immediately.

Specifies the character string that is used to introduce the quoted inbound email content in the body of the outbound email. The following tags can be used: <contact>, <date>. These tags are replaced respectively by the contact name and the date and time of the interaction when they appear in the outbound email.

email.reply-copy-category-id

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.132.05

Specifies whether the Category ID of the reply outbound email is copied to the parent inbound email. Note: the Categoryld of the outbound email is typically specified based on the Category of the standard response that an agent inserts in the email.

>> Back to Top

email.reply-format

Default Value: auto

Valid Values: Select a value from the following list: auto, html, plain-text.

Changes Take Effect: At the next interaction.

Specifies the format of an outbound email reply.

- auto—Outbound email reply format is the same as corresponding inbound email.
- html—Outbound email reply format is forced to HTML.
- plain-text—Outbound email reply format is forced to plain text.

>> Back to Top

email.reply-prefix

Default Value: Re:<SPACE>

Valid Values: Any valid character string. **Changes Take Effect:** Immediately.

Modified: 8.5.116.10

Specifies the reply-prefix that is added to subject of the inbound email. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy. The routing strategy can be used to identify the language of the email interaction and the reply prefix used by customers, and then to apply the same prefix to contact center replies in the email thread [Added: 8.5.116.10].

- Workspace removes multiple reply prefixes and appends either the prefix specified by the routing strategy, the prefix specified by this option, or the default prefix if no prefix is configured [Added: 8.5.116.10].
- Workspace only adds the reply prefix at the beginning of the subject if one does not already exist [**Added:** 8.5.116.10].
- Agents can manually edit the subject prefix of a reply email interaction.

email.resend-prefix

Default Value: No default value

Valid Values: Any valid character string. **Changes Take Effect:** Immediately

Introduced: 8.5.141.04

Specifies the resend-prefix that is added to the subject of the outgoing email interaction that is created when an agent resends an outgoing or reply email from the History. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

email.restricted-attachment-file-types

Default Value:

Valid Values: A comma-separated list of file extensions that represent file types that are to be restricted. For example, use txt to restrict plain-text files, htm to restrict HTML files, and so on.

Changes Take Effect: At the next interaction.

Specifies the list of file extensions that represent file types that are to be prevented from being used as attachments. An error message is displayed to an agent who tries to attach a file of a restricted type.

>> Back to Top

email.ringing-bell

Default Value: Sounds\Ring.mp3|10|-1|primary

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric

values.

Changes Take Effect: At the next interaction.

Related Options: application.secondary-audio-out-device, application.secondary-audio-out-device

Specifies the path of the sound file that is played when E-Mail interaction is ringing. For example: "Sounds\Ring.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority. The higher the integer the higher the priority.
- 3. The duration:
 - a. -1 means plays and repeats until an explicit message stops it. For example, the established event stops the ringing sound.
 - b. 0 means play the whole sound one time.

- c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

>> Back to Top

email.set-ownerid-on-send

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the owner id of the interaction should be updated with the dbid of the agent when the email is sent. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

email.signature

Default Value:

Valid Values: file: followed by the file name and path, or response: followed by the full response path in the Standard Response Library (refer to standard-response.categories).

Changes Take Effect: At the next interaction.
Related Options: standard-response.categories

Specifies the type and the location of the signature template, defined in eServices Manager, that is to be added to outbound emails.

The value has two components that are separated by the character ':', the type (file or response) and the location (path).

- 1. The type of signature file:
 - a. file to specify a file
 - b. response to specify a response from the Standard Response Library
- 2. The location of the signature template:
 - a. The file name and folder relative to the application folder
 - b. The response name and full path of the parent category in the Standard Response Library

For example:

- file:Signatures\Signature.txt
- response:RootCategoryl/CategoryLevel1/CategoryLevel2/CategorySpecifiedAsRoot/ SignatureTemplate

The specified Standard Response can contain the following field codes:

- <\$Agent.FirstName\$>
- <\$Agent.LastName\$>
- <\$Agent.FullName\$>

This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

email.toast-information-key

Default Value: Subject

Valid Values: Any valid character string.
Changes Take Effect: At the next interaction.

Specifies whether the Information area is displayed in the email interaction notification. This option provides the name of the attached data key that contains the information. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

eservices.disconnect-on-logoff

Default Value: false Valid Values: true,false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.108.11

Specifies whether eServices license use optimization is used or the legacy mode is used.

When the value is set to true, Workspace ensures that:

- The connection to Interaction Server is not opened when no eServices media channel is selected at login time
- The connection to Interaction Server is closed when all eServices media channel are logged off during the session

This does not affect supervisors that have Queue or Team Workbin Management privileges.

This ensures that an eServices seat license is checked out only when a media is logged on by the agent or when a supervisor privilege is granted to the user.

Consequently, when no media are logged on, agents cannot see the content of their workbins.

When the value of this option is set to false (legacy behavior), Workspace connects to Interaction Server and logs the agent on the place as soon as an eServices media privilege is granted to the agent.

>> Back to Top

eservices.session-restore-mediatype

Default Value: chat.email.sms

Valid Values: A comma-separated list of valid eServices/Digital Media Types from the following list: chat, email, sms, and

configured workitem media types (for example: pdf or fax)

Changes Take Effect: At the next interaction.

Introduced: 8.5.109.16

Related Options: eservices.session-restore-timeout

Specifies the media types that are allowed to reconnect when a lost connection to Interaction Server is restored, as specified by the eservices.session-restore-timeout option. Workspace will not try to reconnect any media types that are not specified by this option. **Note**: Social Media Types supported by WDE plugins are not supported by this option.

>> Back to Top

eservices.session-restore-timeout

Default Value: 0

Valid Values: any integer greater or equal to 0 **Changes Take Effect:** At the next interaction.

Related Options: eservices.session-restore-mediatype, agent-session-restore-timeout

Specifies the time, in seconds, after reconnection to Interaction Server to retrieve the ownership of interactions of media types that are specified by the value of the eservices.session-restore-mediatype option.

- If the value 0 is specified, the interaction is automatically closed when connection to Interaction Server is lost.
- The value of this option is dependent on the value of the Interaction Server agent-session-restore-timeout option.

>> Back to Top

expression.callable-phone-number

Default Value: No default value **Valid Values:** A regular expression

Changes Take Effect: When the application is started or restarted

Introduced: 8.5.117.18

Applies to a switch or DN. Specifies the pattern of phone numbers that can be dialed from a DN of this switch. This option applies to hybrid environments where agents are configured to work with Places that contain Voice DNs from two different switches. Empty means that there is no restriction to accepted phone numbers. Example: To call only numbers starting with 555, use: ^555[0-9]+

>> Back to Top

expression.email-address

Default Value: $\w+([-+.]\w+)*@\w+([-.]\w+)*\.\w+([-.]\w+)*$

Valid Values: A regular expression

Changes Take Effect: At the next interaction.

Specifies the regular expression to identify an e-mail address in the chat or SMS transcript. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

expression.outbound-campaign-phone-number

Default Value: ^[\(\)\-\.\+\d\s*#]*[\d]+[\(\)\-\.\+\d\s*#/]*\$

Valid Values: A regular expression

Changes Take Effect: At the next interaction.

Introduced: 8.5.115.17

Specifies the regular expression used to identify if an agent has entered a valid phone in the **New Phone Number** dialog to manually dial an Outbound Preview Record using a new phone number. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

expression.phone-number

Default Value: (?:(?:[\+]?([\d]{1,3}(?:[]*[\-.])))?([(\d]{1,3})[\-/)]?(?:[]+[\-.])?)?([\d]{5,})

Valid Values: A regular expression

Changes Take Effect: At the next interaction.

Related Options: expression.phone-number.supported-characters, dial-plan-rule-<name>

Specifies the regular expression used to recognize a phone number of a target entered in the Team Communicator when it is used to start a call, a transfer, or a conference. If the number entered by the agent in the Team Communicator edit box matches this expression, the 'Call' or 'Start Voice Consultation' or 'Instant Transfer' or 'Instant Conference' action is enabled for this number. When the agent executes the action, the entered phone number is modified by the logic specified by the expression.phonenumber.supported-characters and dial-plan-rule-<name> options before the telephony operation is executed. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

expression.phone-number.supported-characters

Default Value: 0123456789#*

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. All special characters that are valid Windows file names.

Changes Take Effect: At the next interaction.

Specifies the characters that are considered when building a request to the T-Server that relies on a phone number. Any other characters from the original string coming from the User Interface are removed. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

expression.team-communicator-phone-number

Default Value: ^[\(\)\-\.\+\d\s*#]*[\d]+[\(\)\-\.\+\d\s*#/]*\$

Valid Values: A regular expression

Changes Take Effect: At the next use of Team Communicator.

Related Options: expression.phone-number.supported-characters, dial-plan-rule-<name>

Specifies the regular expression used to recognize a phone number of a target entered in the Team Communicator when it is used to start a call, a transfer, or a conference. If the number entered by the agent in the Team Communicator edit box matches this expression, the 'Call' or 'Start Voice Consultation' or 'Instant Transfer' or 'Instant Conference' action is enabled for this number. When the agent executes the action, the entered phone number is modified by the logic specified by the expression.phone-number.supported-characters and dial-plan-rule-<name> options before the telephony operation is executed.

>> Back to Top

expression.url

Default Value: See description.

Valid Values: A regular expression representing a URL.

Changes Take Effect: At the next interaction.

Modified: 8.5.124.08

Specifies the regular expression to identify an URL in Case Information area. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

gadget-statistics.displayed-call-center-statistics

Default Value:

Valid Values: A comma-separated list of Statistic names.

Changes Take Effect: Immediately.

Modified: 8.5.109.16

Specifies the statistics that are displayed in the Statistic Gadget. The statistics name refers to the names of the Application Options Sections that define the statistics.

>> Back to Top

gadget-statistics.displayed-kpis

Default Value:

Valid Values: A comma-separated list of KPI names.

Changes Take Effect: Immediately.

Modified: 8.5.109.16

Specifies the KPIs that are displayed to the agent in the Statistic Gadget. The KPI names refer to the names of the Application Option Sections that are defining the KPIs.

>> Back to Top

gadget-statistics.nb-tagged-stats-per-page

Default Value: 5

Valid Values: An integer from 1 to 10.

Changes Take Effect: When the application is started or restarted.

Specifies the number of tagged statistics that are displayed as individual gadget pages with the Gadget. If the number of tagged statistics is exceeded, paging buttons are displayed on the Gadget Statistics page area. The agent tags and untags statistics for display on statistics pages by clicking the Tag and Untag buttons. Untagged statistics are displayed only in the Statistics Ticking area of the Statistics Gadget.

>> Back to Top

gadget-statistics.show

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether or not the Statistics Gadget is displayed when the application is launched.

>> Back to Top

gadget.window-title

Default Value: \$Window.Title\$

Valid Values:

\$Window. Title\$, \$Application. Title\$, \$Application. Name\$, \$Agent. UserName\$, \$Agent. LastName\$, \$Agent. FirstName\$, \$Agent. EmployeeId\$.

Changes Take Effect: Immediately.

Defines the title of the window in which the Gadget is rendered by specifying a string that contains the following field codes:\$Window.Title\$,\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$. If all field codes are empty, the default string is \$Window.Title\$. This title is visible in the Task Bar only.

>> Back to Top

general.configuration-agent-collection-loading-method

Default Value: read-objects

Valid Values: One value from this list:read-objects, brief-info Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.101.14

Related Options: display-format.agent-name, teamcommunicator.list-filter-showing

Specifies the method that Workspace uses to retrieve the collection of agents from Configuration Server. This retrieval happens when the teamcommunicator.list-filter-showing option contains the value Agent. Choose the method that best meets your business requirements, system environment, and scale constraints:

- read-objects—This is the legacy agent-retrieval method. This method returns the list of agents according to the "read" permission of the current agent. For each retrieved agent this method returns the full agent data from Configuration Server, including annex structure, in an uncompressed format. The bandwidth consumed can be much larger than the other retrieval methods.
- brief-info—For each retrieved agent, this method returns only a subset of the agent data. This can result in significant network bandwidth optimization, as well as a decrease of the load on Configuration Server. Configuration Server ignores the "read" permissions of the current agent when returning the list of object; therefore, the Team Communicator provides access to all the agents of the Tenant. This methods does not provide access to the field EmployeeID; therefore, when displaying search results in Team Communicator, the value \$Agent.EmployeeID\$ is ignored when it is specified in the display-format.agent-name option.

>> Back to Top

general.configuration-business-attribute-cache-preload

Default Value: No default value

Valid Values: A comma-separated value list of valid Business Attribute object names or \$All\$.

Changes Take Effect: When the application is started or restarted.

Specifies the list of Business Attribute objects that are loaded and cached at login time.

- If \$All\$ is configured, all the Business Attribute objects that are contained in the Agent's Tenant and on which the Agent has Read Access, are pre-loaded at login time.
- Pre-loading these objects means that dynamic access to Configuration Server during the critical phase of interaction notification is not required.

>> Back to Top

general.configuration-business-attribute-folder-cache-preload

Default Value: No default value

Valid Values: A comma-separated value list of valid Business Attribute object names.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.141.04

Specifies the list of Business Attributes containing a list of folders in the Business Attribute Values area to be loaded and cached at agent login. Folders are used for tree structures in areas such as the Disposition tab and Case Data. The Business Attributes

containing folders must also be specified by the general.configuration-business-attribute-cache-preload option or the Business Attribute containing folders will not be preloaded.

>> Back to Top

general.configuration-object-collection-cache-timeout

Default Value: 0

Valid Values: Any positive integer value.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.101.14

Related Options: teamcommunicator.list-filter-showing

Specifies the amount of time, in hours, to keep the list of objects in a local cache file before requesting it again from Configuration Server. Once the timeout is expired, Workspace request the objects from Configuration Server the next time that Team Communicator is initialized, such as at the next session login if Team Communicator is already initialized for the current session. The value 0 means that no local cache is created. This list of objects is loaded and cached based on the value of the teamcommunicator.list-filter-showing option.

>> Back to Top

general.configuration-transaction-cache-preload

Default Value:

Valid Values: A comma-separated value list of valid Transaction object names or \$All\$ **Changes Take Effect:** When the application is started or restarted.

Specifies the list of Transaction objects of type 'List' that are loaded and cached at login time.

- If \$All\$ is configured, all the Transaction objects of type 'List' that are contained in the Agent's Tenant and on which the Agent has Read Access, are pre-loaded at login time.
- Pre-loading these objects means that dynamic access to Configuration Server during the critical phase of interaction notification is not required.

>> Back to Top

general.configuration-update-notification

Default Value: All

Valid Values: A comma-separated value list of one or more items that are to be notifed: None, All, ThisAgent, ThisApplication, ThisTenant, Transactions, Persons, Skills, AgentGroups, DN, BusinessAttributes, BusinessAttributeValues, Script **Changes Take Effect:** When the application is started or restarted.

Specifies the list of Configuration Server objects that require notification when there is an update.

Note: for legacy purposes, the value ThisAplication is also supported. This value was introduced erroneously in Workspace 8.1.

>> Back to Top

general.gad.attached-data

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether attached data keys are added. If this option is set to true, Workspace adds to the attached data the equivalent of GAD Keys. In the case in which routing base is used, Workspace adds the following keys: GD_TransferTargetType, GD TransferTargetId

>> Back to Top

general.non-unicode-connection-encoding

Default Value:

Valid Values: .Net Name of Code Page Identifier

Changes Take Effect: When the application is started or restarted

Specifies the code page encoding that is used to connect to back-end servers that do not rely on Unicode communication (all back-end servers except UCS). The possible values can be obtained from the ".Net Name" column of the Code Page Identifier that is defined in the following document: http://msdn.microsoft.com/en-us/library/windows/desktop/dd317756(v=vs.85).aspx

When this option is empty, the applied encoding corresponds to the language for non-unicode programs, which is also known as the system-locale of the agent Workstation.

>> Back to Top

general.writable-downloaded-attachment-file-types

Default Value: No default value

Valid Values: A comma separated list of valid file extensions, such as xlsx, png, and so on.

Changes Take Effect: At next attachment download.

Introduced: 8.5.118.10

Specifies the list of attachment file types that when they are opened are writable on the hard drive of the agent workstation once they are downloaded from UCS.

>> Back to Top

gui.editor-zoom-range

Default Value: 100

Valid Values: Blank, a single zoom value, or two comma separated values that represent the minimum and maximum percent zoom. Values must be greater than or equal to 10 and less than or equal to 300.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.109.16

Defines the zoom value(s) for editor fields and transcripts in text based interaction views such as email, chat, SMS, and IM. Several values are supported:

- Comma separated minimum and maximum values where the values are not equal. These specify the zoom range and the zoom UI controls are enabled in the Main Menu.
- Comma separated minimum maximum values where the values are equal. The zoom level is set to this single value and the zoom UI controls are not displayed in the Main Menu.
- A single value. The zoom level is set to this single value and the zoom UI controls are not displayed in the Main Menu.
- Blank. The zoom level is set to 100%, and the zoom UI controls are not displayed in the Main Menu.

>> Back to Top

gui.emoji-font-name

Default Value: Segoe UI

Valid Values: A valid name of a font available on the agent workstation.

Changes Take Effect: At the next interaction.

Introduced: 8.5.115.17

Specifies the font to be used to represent emoji symbols in chat interactions. The default Workspace font does not support all emojis.

>> Back to Top

gui.magnification-factor

Default Value: normal

Valid Values: normal, medium, large, xlarge

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.102.06

Specifies the ratio of the display size of interface elements in the Workspace interface to enable agents to view these interface elements at larger sizes. The following ratios are supported:

normal: 1.00 (legacy)

medium: 1.25large: 1.50xlarge: 1.75

This feature functions only with the default Workspace 8.5 GUI themes, and to custom themes that are developed according to the documentation and samples of the *Workspace Developer's Guide*. If the blue, royale, and fancy legacy themes are used, the magnification is forced to normal.

>> Back to Top

gui.themes

Default Value: Default, HighContrast, Blue, Royale, Fancy **Valid Values:** A comma-separated of theme names.

Changes Take Effect: When the application is started or restarted.

Specifies the list of themes that are displayed in the **Change Theme** menu. If this option contains only one theme, that theme is applied by default, and the theme selection menu will not be included in the agent interface. The HighContrast theme is meant primarily for accessibility.

>> Back to Top

im.agent.prompt-color

Default Value: #FF2E6599

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB

hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the prompt for the messages entered by the agent in the IM view.

>> Back to Top

im.agent.text-color

Default Value: #FF3D464D

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB

hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the text of the messages entered by the agent in the IM view.

>> Back to Top

im.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specify whether an IM interaction is automatically answered when a TServer Ringing event is received. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

im.new-message-bell

Default Value:

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric values.

Changes Take Effect: Immediately

Related Options: application.secondary-audio-out-device, application.secondary-audio-out-device

Specifies the sound configuration string for a new Instant Message. For example: "Sounds\bell.mp3|7|0|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority -- The higher the integer the higher the priority.
- 3. The duration:
 - a. 0 means play the whole sound one time.
 - b. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

>> Back to Top

im.other-agent.prompt-color

Default Value: #FF295B00

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB

hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the text of the messages entered by the target agent in the IM view.

im.other-agent.text-color

Default Value: #FF3D464D

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB

hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the other agent text in the IM view. The HTML format is used to set the value. I.e.: #FFFF0000 for a red color.

>> Back to Top

im.prompt-for-end

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether Workspace displays a confirmation message when the agent clicks End during an Instant Messaging session. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

im.ringing-bell

Default Value: Sounds\Ring.mp3|10|-1|primary

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric values.

Changes Take Effect: At the next interaction.

Related Options: application.secondary-audio-out-device, application.secondary-audio-out-device

Specifies the im channel ringing sound-configuration string. For example: "Sounds\Ring.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority -- The higher the integer the higher the priority.
- 3. The duration:
 - a. 0 means play the whole sound one time.
 - b. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value |primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

im.simple-transcript

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediately

Introduced: 8.5.122.08

Specifies whether the IM transcript is displayed as simple lines of text lines instead of text blocks.

>> Back to Top

im.system.text-color

Default Value: #FF8C8C8C

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB

hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Specifies the color of the text for the system messages in the IM view.

>> Back to Top

im.time-stamp

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Specify whether the time stamp is displayed in the transcript area.

>> Back to Top

im.toast-timeout

Default Value: 10

Valid Values: from 0 to MAXINT

Changes Take Effect: At the next interaction.

Defines the duration, in seconds, that the IM interaction notification is displayed in the Information area of the Main Window before the IM is rejected. The value 0 means the interaction notification is displayed until the agent accepts the interaction.

>> Back to Top

interaction.auto-focus

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.116.10

Specifies whether the inbound interaction should be in focus automatically when it is accepted.

interaction.auto-focus.<media-type>

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.116.10

Related Options: interaction.auto-focus

Specifies whether a new inbound interaction of the specified media type should be in focus automatically when is accepted. When this option is defined it overrides the interaction.auto-focus option.

>> Back to Top

interaction-bar.allows-floating-transparency

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the floating interaction window is displayed in a transparent style. Setting this option to false is necessary in some video hardware environments to properly render the Team Communicator control when it is displayed from the floating interaction window—typically to select an email address. The value false might result in a slight degradation of the appearance of the floating window.

>> Back to Top

interaction-bar.detail-tooltip.max-height

Default Value: 164

Valid Values: An integer value greater than or equal to 0.

Changes Take Effect: Immediately.

Sets the maximum height, in pixels, of the tooltip for interaction details of Interaction Bar items. The tooltip can contain the chat transcript, the body of an email, and so on.

>> Back to Top

interaction-bar.enable-quick-access

Default Value: true **Valid Values:** true, false

Changes Take Effect: When application is started or restarted.

Specifies whether interaction windows are docked or undocked.

- true: Interaction windows are docked to the interaction bar. Use the interaction-bar.quick-accessmodes option to specify pinned or floating mode.
- false: Interaction windows are undocked from the interaction bar (pre-8.5.0 legacy mode).

Note: In legacy mode, the Main Window layout is the same as when Quick Access is enabled: the interaction bar is located on the right of the Team Communicator control (instead of below it, as in the 8.1.4 release), and the Supporting Views are accessible from the 'hamburger' menu (instead of the toolbar buttons, as in the 8.1.4 release).

interaction-bar.quick-access-auto-open

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Dependencies: interaction-bar.enable-quick-access

Introduced: 8.5.106.19

Specifies whether the interaction floating or pinned view is opened automatically when an interaction is added to the interaction bar (when an incoming interaction is accepted or when an outgoing one is created). This option is not applicable if the value of the interaction-bar.enable-quick-access option is set to false. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

interaction-bar.quick-access-auto-open.<media-type>

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.106.19

Related Options: interaction-bar.enable-quick-access, interaction-bar.quick-access-auto-open

Specifies whether the interaction floating or pinned view for the specified media type is opened automatically when an interaction is added to the interaction bar (when an incoming interaction is accepted or when an outgoing one is created). This option is not applicable if the value of the interaction-bar.enable-quick-access option is set to false. When this option is specified for a media type, it overrides the specification of the interaction-bar.quick-access-auto-open option.

>> Back to Top

interaction-bar.quick-access-modes

Default Value: Pinned, Floating

Valid Values:

Changes Take Effect: At the next interaction.

Related Options: interaction-bar.enable-quick-access, interaction-bar.quick-access-modes.<media-type>

Specifies the list of modes that are available when interactions are displayed in "quick access" mode. The available modes are:

- Pinned The interaction view occupies the full available size and is shared with Supporting Views such as Contact and My Channels.
- Floating The interaction view is contained in a floating window that is displayed above any other kind of content and that fits to the size of the content. This view cannot display content such as the Contact Profile or Responses views.
- Pinned, Floating The agent can switch from one mode to the other by using a dedicated control.
 This option is not applicable if the value of the interaction-bar.enable-quick-access is set to false. For a given media type, this option can be overridden by option the interaction-bar.quick-access-modes.

>> Back to Top

interaction-bar.quick-access-modes.<media-type>

Default Value: Pinned, Floating

Valid Values:

Changes Take Effect: At the next interaction.

Dependencies: interaction-bar.enable-quick-access

Use this option as a template to specify the list of modes that are available when interactions are displayed in "quick access" mode. The available modes are:

- Pinned The interaction view occupies the full available size and is shared with Supporting Views such as **Contact** and **My Channels**.
- Floating The interaction view is contained in a floating window that is displayed above any other kind of content and that fits to the size of the content. This view cannot display content such as the Contact Profile or Responses views.
- Pinned, Floating The agent can switch from one mode to the other by using a dedicated control.
 This option is not applicable if the value of the interaction-bar.enable-quick-access is set to
 false.

>> Back to Top

interaction.case-data.content

Default Value: History, CaseData **Valid Values:** History, CaseData

Changes Take Effect: At the next interaction.

Modified: 8.5.106.19

Related Options: toast.case-data.content, display-format.caller-name

Specifies the content of the Case Information area in the interaction preview.

- The CaseData key enables the display of the attached data that is defined by the interaction.casedata.format-business-attribute option; the relative order of case data keys can be specified in the configured Business Attribute object as described in that option.
- The History key enables the display of interaction history information such as 'origin', 'queue', 'call type'. The content displayed in the 'history' block is controlled by the application and the list of keys depends on the context. Administrators do not have control over this content.
- The order of the values in the option defines the order of the Case Data (as a block) and History (as another block) information in the Case Information area of the interaction preview
- This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy. Starting from the 8.1.1 release, this option no longer controls the display of case information in the toast view. Please refer to the toast.case-data.content option for this purpose.

>> Back to Top

interaction.case-data.email.mandatory-actions

Default Value: Transfer, Forward

Valid Values: A comma separated list of actions from the following list: Transfer, Forward **Changes Take Effect:** The next time an agent transfers and/or forwards an e-mail interaction.

Introduced: 8.5.150.06

Some email interaction actions, such as 'Transfer' and 'Forward as an attachment', have an uncertain final status. This option enables you to specify whether the agent must complete the mandatory case data before applying a 'Transfer' or 'Forward as an attachment' action. If Transfer and/or Forward are specified for this option, agents must complete the case data that is configured as mandatory before completing one of these actions. This option can be overridden by a routing strategy as described in Overriding Options by Using a Routing Strategy.

To specify whether the agent must complete the mandatory case data before applying a Transfer and/or Conference action for any Digital Channel interaction other than email, configure https://docs.genesys.com/Documentation/Options/Current/IW/WDE-interaction-workspace#interaction-case-data-zmedia-type-zmandatory-actions

interaction.case-data.enable-url-preview

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Related Options: expression.url

Enables the display of a preview of the web page that is linked from the Case Information if the value is set to true. Also see expression.url. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing

Strategy.

>> Back to Top

interaction.case-data.format-business-attribute

Default Value:

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters.

Changes Take Effect: At the next interaction

Related Options: interaction.case-data.order, toast.case-data.format-business-attribute

Specifies the name of the Business Attribute that contains the Attribute Values that are used to filter and render attached data. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

You can define the display order of Business Attribute Values by creating an interaction-workspace section in the annex of the Business Attribute, then add the interaction.case-data.order option. This option is a comma-separated list of Business Attributes Value Names that specifies the order of the Business Attribute Values. The Attributes Values that are not listed in the interaction.case-data.order option are put at the bottom of the list.

Starting with the 8.1.1 release this option no longer controls the display of case information in the toast view. Refer to the toast.case-data.format-business-attribute option for this purpose.

>> Back to Top

interaction.case-data.frame-color

Default Value: #FF17849D

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: At the next interaction.

Modified: 8.5.106.19

Specifies the background color of the Case Information view header. Examples: #FFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

interaction.case-data.header-foreground-color

Default Value: #FFFFFFFF

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: At the next interaction.

Modified: 8.5.106.19

Specifies the color of the text of the Case Information view header. Example #FFFFFFF for white color. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

interaction.case-data.is-read-only-on-idle

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.132.05

If the value of this option is true, changes are prevented to the case data after a voice or chat interaction has ended. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

interaction.case-data.<media-type>.mandatory-actions

Default Value:

Valid Values: A comma separated list of actions from the following list: Transfer, Conference **Changes Take Effect:** At the next interaction.

Changes lake Effect: At the next interaction

Introduced: 8.5.150.06

Some actions, such as 'Transfer' and/or 'Conference', have an uncertain final status. This option enables you to specify whether the agent must complete the mandatory case data before applying a Transfer and/or Conference action for any Digital Channel interaction other than email. If Transfer and/or Conference are specified for this option, agents must complete the case data that is configured as mandatory before completing one of these actions. This option can be overridden by a routing strategy as described in Overriding Options by Using a Routing Strategy.

To specify whether the agent must complete the mandatory case data before applying a 'Transfer' or 'Forward as an attachment' action on an email interaction, configure https://docs.genesys.com/Documentation/Options/Current/IW/WDE-interaction-workspace#interaction-case-data-email-mandatory-actions

Note: Agents can apply the Conference action only for the media types that support the functionality.

>> Back to Top

interaction.consult-user-data

Default Value: public

Valid Values: Select a value from the following list: public, private, none

Changes Take Effect: Immediately.

Specifies if and how the business data (original interaction user data, contact identifier, and so on) of the customer interaction is shared in a consultation interaction and how. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

- none No data is shared in the consultation.
- public User data of the customer interaction is shared in the consultation. The user data is
 copied at the root level of the consultation user data. Keys that start with an underscore are not
 copied into the consultation leg.
- private User data of the customer interaction is shared in the consultation. The user data is copied in a sub-list of the consultation user data, named SharedInformation. Keys that start with an underscore are not copied into the consultation leg. This is Interaction Workspace 8.1.0 compatibility mode.

>> Back to Top

interaction.disposition.display-mode

Default Value: tree-view

Valid Values: Select one value from the following list: tree-view,radio-buttons

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.108.11

Specifies the display mode of the Disposition tab in the interaction view.

- tree-view—Disposition codes are contained within a hierarchy of folders. Agent can search for disposition codes.
- radio-buttons—The disposition codes are presented in a flat radio-button list (legacy mode).

>> Back to Top

interaction.disposition.email.mandatory-actions

Default Value:

Valid Values: A comma separated list of actions from the following list: Transfer, Forward

Changes Take Effect: At the next interaction.

Introduced: 8.5.103.10 Modified: 8.5.117.18

Related Options: interaction.disposition.is-mandatory

Some email interaction actions, such as 'Transfer' and 'Forward as an attachment', have an uncertain final status. This option enables you to specify whether the mandatory disposition code must be completed by the agent before applying a 'Transfer' or 'Forward as an attachment' action. If Transfer and/or Forward are specified for this option, agents must complete the disposition code that is configured as mandatory before completing one of these actions. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

interaction.disposition.is-mandatory

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediately.

Specify whether it is mandatory for the agent to set a disposition code before Marking Done an interaction. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

interaction.disposition.is-read-only-on-idle

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediately.

Prevents changes to the disposition code after a voice interation has been released. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

interaction.disposition.key-name

Default Value: DispositionCode

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters.

Changes Take Effect: Immediately.

The key that is used to populate attached data or a user event when a disposition code is submitted to the back-end system, such as T-Server, Interaction Server, and Contact Server. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

interaction.disposition.use-attached-data

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediately.

Enables the adding of attached data from the interaction in UserEvent. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

interaction.disposition.use-connection-id

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Specifies whether the connection id is sent as part of the user event that is sent for disposition code. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

interaction.disposition.value-business-attribute

Default Value: DispositionCode

Valid Values: A valid name of a Business Attribute.

Changes Take Effect: Immediately.

A character string that specifies the name of the Business Attribute that contains the Attribute Values that are used as an enumerated value for a disposition code.

Beginning with release 8.5, you can specify the display order of Business Attribute Values by creating an interaction-workspace section in the annex of the Business Attribute, and then add the interaction.disposition.order option.

This option contains a comma-separated list of Business Attributes Value Names that specifies the order of the Business Attribute Values. The Attributes Values that are not specified by the interaction disposition order option are put at the bottom of the list, except for the value None, which it is always the first item. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

interaction.disposition.<media-type>.mandatory-actions

Default Value:

Valid Values: A comma separated list of actions from the following list: Transfer, Conference

Changes Take Effect: At the next interaction.

Introduced: 8.5.150.06

Related Options: interaction.disposition.is-mandatory

Some actions, such as 'Transfer' and/or 'Conference', have an uncertain final status. This option enables you to specify whether the mandatory disposition code must be completed by the agent before applying a 'Transfer' and/or 'Conference' action for interactions of any given media type that is different from email. If Transfer and/or Conference are specified for this option, agents must complete the disposition code that is configured as mandatory before completing one of these actions. This option can be overridden by a routing strategy as described in Overriding Options by Using a Routing Strategy.

Note: Agents can apply the Conference action only for the media types that support the functionality.

>> Back to Top

interaction.evaluate-real-party-for-agent

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.
Related Options: interaction.evaluate-real-party-for-agent.expression

Specifies whether Workspace attempts to transform the name of the party DN into an Agent name during a voice interaction.

If the value of this option is set to true, the names of all the parties on a call are displayed, if possible. This includes the contact party. In general, agent DNs are defined using a dialing rule, the interaction.evaluate-real-party-for-agent.expression option can be used to define a regular expression that recognizes internal parties on a call and displays the agent name instead of the DN.

>> Back to Top

interaction.evaluate-real-party-for-agent.expression

Default Value: .*

Valid Values: A regular expression

Changes Take Effect: When the application is started or restarted.

Dependencies: interaction.evaluate-real-party-for-agent

Introduced: 8.5.110.13

When the value of the interaction.evaluate-real-party-for-agent option is set to true, this option specifies a regular expression that is used to match the parties in a voice call that should be evaluated and transformed into a real agent name. For example, in environments where agent DNs are defined by a 7-digit number starting with a 7 or 8, the value of this option would be set to the following value: "^[78]\d{6}".

>> Back to Top

interaction-management.available-interaction-page-sizes

Default Value: 5,10,25,50

Valid Values: A comma-separated list of numbers that define the number of rows per result page from which the agent can

make selections.

Changes Take Effect: When the application is started or restarted.

The possible values for the number of rows per page in the Interaction Management content view. Values grater than 100 are not recommended due to performance impact. The maximum value depends on the content of interactions and the robustness of your network. If you specify a value that is too high, the request to get a snapshot will fail and an error message is displayed.

>> Back to Top

interaction-management.filters

Default Value:

Valid Values: A comma-separated list of Filter names.

Changes Take Effect: When the application is started or restarted.

Defines the filters that are displayed to the supervisor for interaction management. The filter names refer to the names of the Application Option sections that are defining the Filters. Refer to the following topic for more information: Creating Interaction Filters for Team Leads.

interaction-management.interactions-filter.displayed-columns

Default Value: From, To, Subject, Received

Valid Values: A comma-separated list of interaction data keys, for example: From, Subject, Received

Changes Take Effect: When the application is started or restarted.

The list of interaction fields that are displayed as columns in the Interaction Queue view.

>> Back to Top

interaction-management.snapshot-timeout-delay

Default Value: 10

Valid Values: An integer from 1 through 3600.

Changes Take Effect: Immediately

Introduced: 8.5.119.05

The delay, in seconds, before a snapshot request to get interaction queue content times out.

>> Back to Top

interaction.override-option-key

Default Value: IW_OverrideOptions

Valid Values: An attached data key name (string). Changes Take Effect: At the next interaction.

Enables overriding of certain application options by using one or several transaction objects. This option provides the key name of the attached data that contains the list of transaction objects. **Note**: the key named in this option will not be copied into any interaction that is created from the current interaction, such as consultations, reply emails, and so on. Refer to Modifying a Routing Strategy to Override Workspace Options, Based on Attached Data

>> Back to Top

interaction.reject-route

Default Value:

Valid Values: A string that represents an attached data key.

Changes Take Effect: At the next interaction.

Workspace enables the **Reject** voice call operation in SIP Server environments that use multi-site routing. The reject route mechanism has been extended to accommodate different types of 'reject' implementations, depending on the context. Use the interaction.reject-route to enable the reject route mechanism by specifying a string as a key to be used at run-time to retrieve the behavior description from the interaction user data. It is the responsibility of the administrator to define the multi-site reject criteria.

The reject route is specified in the interaction user-data in the following format: <reject-method>:<dn>@<switch>.

Note: In releases 8.1.2 and earlier, the format was defined by <dn>@<switch> only.

 $The < \!\!\! \text{reject-method} \!\!\!> \text{attribute is optional to maintain backward-compatibility with pre-} 8.1.3 \ configurations.$

When <reject-method> is specified, ensure that the following characters are also specified: ':', '@', and the <switch> field.

The following are the possible values for the <reject-method> attribute:

 pullback — Reject applies the following action: SingleStepTransfer(OtherDN='', Location=<switch>,extensions contains *pullback*). This is the legacy behavior for multi-site reject. This approach works only when the value of the TServer/divert-on-ringing SIP Server configuration option is set to true.

- sst Reject applies the following action: SingleStepTransfer(OtherDN=<dn>,
 Location=<switch>). Warning, if the value of dn@switch corresponds to the same routing point as
 the one that is handling the call that is being delivered to the agent, the action will succeed only if
 the value of the TServer/divert-on-ringing SIP Server configuration option is set to true
- release Reject applies the following action: releaseCall. This value must be applied when the value of the TServer/divert-on-ringing SIP Server option is set to false.

>> Back to Top

interaction.unconditional-force-close

Default Value: false Valid Values: true, false

Changes Take Effect: Immediately

Introduced: 8.5.118.10

Specifies whether the Force Close This Case contextual menu is always enabled (true) or is available only if specific conditions are met where the current interaction/case can no longer be closed by the agent through standard interaction handling procedures.

>> Back to Top

interaction.window.popup-topmost-z-order

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction if the value is changed to 'true', or when the application is started or restarted if the value is changed to 'false'.

Indicates whether the interaction window can steal focus from other active applications when auto-answer in enabled. When set to false, the Interaction Window tries to gracefully get the focus; however, due to certain Windows Operating System settings, this might not result in moving the interaction window to the front.

>> Back to Top

interaction.window.show-case-interaction-panel-button

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the collapse/expand button on interaction windows is enabled. If the value of this option is set to true, the button is enabled, and agents can collapse and expand the interaction view (left panel). The interaction view contains the controls and content of the interaction. If this view is collapsed, only the right panel is displayed. This is typically the Contact Information and Contact History view or Standard Responses view or any available customized view. If the value of this option is set to false, the button is not enabled, and the interaction view cannot be collapsed.

>> Back to Top

interaction.window.show-in-taskbar

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Indicates whether the interaction window has a Windows taskbar button. If not, when minimized the window can be restored from the Interaction Bar. Enables the minimizing of Interaction windows to the Interaction bar of the Main Window instead of the Windows taskbar.

>> Back to Top

interaction.window-title

Default Value: See the Description. **Valid Values:** See the Description.

Changes Take Effect: When the application is started or restarted.

Modified: 8.5.124.08

Defines the title of the interaction window that appears in the Windows Task Bar by specifying a string that contains the valid field codes. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

- Default Value: (\$Contact.FirstName\$ \$Contact.LastName\$|\$Interaction.MainParty\$) -\$Interaction.Type\$ - \$Window.Title\$
- Valid Values: \$Window.Title\$, \$Application.Title\$, \$Application.Name\$, \$Agent.UserName\$, \$Agent.LastName\$, \$Agent.FirstName\$, \$Agent.EmployeeId\$, \$Contact.FirstName\$, \$Contact.LastName\$, \$Interaction.MainParty\$, \$Interaction.Type\$

>> Back to Top

interactions.window.allows-transparency-on-winos6

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the interaction window is presented in transparent style on Windows OS version 6 or higher. Unmanaged controls, such as web browsers, are not able to function in Windows Vista and Windows 7 if non-transparent windows are used. Set the value to false to permit the display of unmanaged controls.

>> Back to Top

intercommunication.chat.conference.invite-timeout

Default Value: 30

Valid Values: from 30 to MAXINT

Changes Take Effect: At the next interaction.

Specifies the time-out interval for a chat conference or chat consultation invitation to a skill, agent group, or interaction queue.

>> Back to Top

intercommunication.chat.queue

Default Value:

Valid Values: Name of a valid Script object of type InteractionQueue

Changes Take Effect: At the next interaction.

Specifies the name of the Interaction Queue that is used by the 'routing based' feature for Chat. The following attached data are added by Interaction Worskpace:

IW RoutingBasedOriginalEmployeeId,IW RoutingBasedTargetId,IW RoutingBasedTargetType,IW RoutingBasedRequestType.

intercommunication.chat.routing-based-actions

Default Value:

Valid Values: A comma-separated list of valid operation names from the following list: OneStepTransfer.

Changes Take Effect: At the next interaction.

Specifies the list of 'routing based' actions that an agent is allowed to perform.

>> Back to Top

intercommunication.chat.routing-based-targets

Default Value:

Valid Values: A comma-separated list of valid object types from the following list: Agent, InteractionQueue

Changes Take Effect: At the next interaction.

Dependencies: intercommunication.chat.routing-based-actions

Specifies the list of targets that are contacted through the routing based mechanism for requests that are defined by the following option: intercommunication.chat.routing-based-actions

Warning: The AgentGroup and Skill targets are always addressed through routing; therefore, these are not affected by this option.

>> Back to Top

intercommunication.email.queue

Default Value:

Valid Values: Name of a valid Script object of type InteractionQueue

Changes Take Effect: At the next interaction.

Specifies the name of the Interaction Queue that is used by the 'routing based' feature for E-Mail. The following attached data are added by Interaction Worskpace:

 $IW_Routing Based Original Employee Id, IW_Routing Based Target Id, IW_Routing Based Target Type, IW_Routing Based Request Type.$

>> Back to Top

intercommunication.email.routing-based-actions

Default Value:

Valid Values: A comma-separated list of valid operation names from the following list: OneStepTransfer. **Changes Take Effect:** At the next interaction.

Specifies the list of 'routing based' actions that an agent is allowed perform.

>> Back to Top

intercommunication.email.routing-based-targets

Default Value:

Valid Values: A comma-separated list of valid object types from the following list: Agent, InteractionQueue

Changes Take Effect: At the next interaction.

Dependencies: intercommunication.email.routing-based-actions

Specifies the list of targets that are contacted through the routing based mechanism for requests that are defined by the following option: intercommunication.email.routing-based-actions

Warning: The AgentGroup and Skill targets are always addressed through routing; therefore, these are not affected by this

option.

>> Back to Top

intercommunication.im.routing-based-actions

Default Value: MakelM

Valid Values: Comma separated list of valid operation names from the following: MakeIM

Changes Take Effect: When the application is started or restarted.

Specifies the list of routing-based actions that an agent is allowed to perform.

>> Back to Top

intercommunication.im.routing-based-targets

Default Value:

Valid Values: Comma separated list of valid object types from the following: Agent, ACDQueue, RoutingPoint

Changes Take Effect: At the next interaction.

Dependencies: intercommunication.im.routing-based-actions

Specifies the list of targets that are contacted through the routing-based mechanism for requests that are defined by the following option: intercommunication.im.routing-based-actions

Warning: The AgentGroup and Skill targets are always addressed through routing; therefore, these are not affected by this option.

>> Back to Top

intercommunication.im.routing-points

Default Value:

Valid Values: A comma-separated list of call number names in the following format: \$dn_name@switch\$
Changes Take Effect: At the next interaction.

Specifies the call number that is used by the routing-based feature. The following attached data are added by Interaction Worskspace: IW_RoutingBasedOriginalEmployeeId,IW_RoutingBasedTargetId,IW_RoutingBasedTargetType, IW_RoutingBasedActionType,IW_RoutingBasedRequestType, IW_RoutingBasedLocation

>> Back to Top

intercommunication.sms.queue

Default Value:

Valid Values: Name of a valid Script object of type InteractionQueue

Changes Take Effect: At the next interaction.

Specifies the name of the Interaction Queue that is used by the 'routing based' feature for SMS. The following attached data are added by Interaction Worskpace:

 $IW_Routing Based Original Employee Id, IW_Routing Based Target Id, IW_Routing Based Target Type, IW_Routing Based Request Type.$

>> Back to Top

intercommunication.sms.routing-based-actions

Default Value: OneStepTransfer

Valid Values: A comma-separated list of valid operation names from the following list: OneStepTransfer.

Changes Take Effect: At the next interaction.

Specifies the list of routing-based actions that an agent is allowed to perform.

>> Back to Top

intercommunication.sms.routing-based-targets

Default Value:

Valid Values: A comma-separated list of valid object types from the following list: Agent, InteractionQueue

Changes Take Effect: At the next interaction.

Dependencies: intercommunication.sms.routing-based-actions

Specifies the list of targets that are contacted through the routing-based functionality for requests that are defined by the intercommunication.sms.routing-based-actions option.

Warning: The AgentGroup and Skill targets are always addressed through routing; therefore, they are not affected by this option.

>> Back to Top

intercommunication.voice.routing-based-actions

Default Value: MakeCall,OneStepConference,InitConference,OneStepTransfer,InitTransfer

Valid Values: A comma-separated list of valid operation names from the following list: MakeCall, OneStepTransfer, InitTransfer,

InitConference, OneStepConference.

Changes Take Effect: At the next interaction.

Specifies the list of routing-based actions that an agent may perform.

>> Back to Top

intercommunication.voice.routing-based-targets

Default Value:

Valid Values: A comma-separated list of valid object types from the following list: Agent, ACDQueue, RoutingPoint, Contact, TypeDestination.

Changes Take Effect: At the next interaction.

Dependencies: intercommunication.voice.routing-based-actions

Specifies the list of targets that are contacted through the routing-based mechanism for the requests that are defined in the option intercommunication.voice.routing-based-actions.

Warning: The targets AgentGroup and Skill are always addressed through routing; therefore, these are not affected by this option.

>> Back to Top

intercommunication.voice.routing-points

Default Value:

Valid Values: A comma-separated list of call number names in the following format: \$dn_name@switch\$ **Changes Take Effect:** At the next interaction.

Specifies the call number that is used by the routing-based feature. The following attached data are added by Interaction Worskspace: IW_RoutingBasedOriginalEmployeeId,IW_RoutingBasedTargetId,IW_RoutingBasedTargetType, IW_RoutingBasedActionType, IW_RoutingBasedRequestType, IW_RoutingBasedLocation

intercommunication.voicemail.enabled-target-types

Default Value: Agent, Agent Group

Valid Values: Empty or a comma separated list of string from the following list: Agent, AgentGroup

Changes Take Effect: Immediately

Introduced: 8.5.118.10

Specifies the list of targets, Agent and/or Agent Group, that can be contacted through voicemail.

>> Back to Top

intercommunication.voicemail.routing-points

Default Value: No default value

Valid Values: A comma-separated list of call number names in the following format: dn_name@switch

Changes Take Effect: Immediately

Introduced: 8.5.118.10

Specifies the call number that is used by the routing-based feature. The following attached data are added by Interaction Worskspace:

 $IW_RoutingBasedGvmMailbox, IW_RoutingBasedOriginalEmployeeld, IW_RoutingBasedTargetId, IW_RoutingBasedRequestType$

>> Back to Top

intercommunication.<media-type>.queue

Default Value:

Valid Values: Name of a valid Script object of type InteractionQueue **Changes Take Effect:** At the next interaction.

Use this option as a template for any specific workitem media-type to specify the name of the Interaction Queue that is used by the 'routing based' feature for the specified workitem media-type. The following attached data are added by Interaction Worskpace:

IW RoutingBasedOriginalEmployeeId,IW RoutingBasedTargetId,IW RoutingBasedTargetType,IW RoutingBasedRequestType.

>> Back to Top

intercommunication.<media-type>.routing-based-actions

Default Value:

Valid Values: A comma-separated list of valid operation names from the following list: OneStepTransfer. **Changes Take Effect:** At the next interaction.

Use this option as a template for any specific workitem media type to define the list of 'routing based' actions that an agent is allowed to perform for the specified workitem media-type.

>> Back to Top

intercommunication.<media-type>.routing-based-targets

Default Value:

Valid Values: A comma-separated list of valid object types from the following list: Agent, InteractionQueue

Changes Take Effect: At the next interaction.

Dependencies: intercommunication.<media-type>.routing-based-actions

Use this option as a template for any specific workitem media type to define the list of targets that are contacted through the routing based mechanism for the requests that are defined in the option intercommunication.media-type>.routing-based-actions.

Note: The targets AgentGroup and Skill are always addressed through routing; therefore, they are not affected by this option.

>> Back to Top

keyboard.hotkey.agent-not-ready

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to set the agent state to Not Ready. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.hotkey.agent-not-ready-with-reason.<action-code>

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to set the agent state to Not Ready with a reason. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V. You must also name the option by adding the Action Code 'code' attribute to the name of the option. For example, if the name of the "Not Ready" Action Code is "Meeting" and its code is '1001', then the option key name is specified as "keyboard.hotkey.agent-not-ready-with-reason.1001" and the value should be specified as Ctrl+Alt+M.

>> Back to Top

keyboard.hotkey.agent-ready

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to set the agent state to Ready. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.hotkey.decrease-microphone-volume-active-sip-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to increase the volume of the microphone during an active SIP call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.hotkey.decrease-speaker-volume-active-sip-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

A shortcut key to decrease the volume of the speaker during an active SIP call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.hotkey.hold-active-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to hold the active call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.hotkey.increase-microphone-volume-active-sip-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to increase the volume of the microphone during an active SIP call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.hotkey.increase-speaker-volume-active-sip-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

 $A shortcut \ key \ to \ increase \ the \ volume \ of \ the \ speaker \ during \ an \ active \ SIP \ call. For \ example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.$

>> Back to Top

keyboard.hotkey.mute-microphone-active-sip-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to mute the microphone during an active SIP call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.hotkey.mute-speaker-active-sip-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

A shortcut key to mute the speaker during an active SIP call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.hotkey.release-active-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to release the active call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.hotkey.toaster.accept

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to accept the interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.hotkey.toaster.decline

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to decline the interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.action.help

Default Value: F1

Valid Values: Only the name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key by using the + character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to open the help. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.campaign.get-record

Default Value: Ctrl+Shift+R

Valid Values: he name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

A shortcut key to get a new campaign record. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.contact.assigncontact

Default Value: Ctrl+A

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to assign a contact to the current interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.contact.reset

Default Value: Ctrl+R

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

A shortcut key to reset a contact record. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.contact.save

Default Value: Ctrl+S

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to save the contact record. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.hamburger.open

Default Value:

Valid Values: he name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

Introduced: 8.5.115.17

The combination of keys that can be used as a keyboard shortcut to open the Main Menu (Hamburger menu).

>> Back to Top

keyboard.shortcut.interaction.chat.add-attachments

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

A shortcut key to add attachments to the chat. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.chat.conference

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. Changes Take Effect: When the application is started or restarted.

A shortcut key to start a chat conference. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.chat.end

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. Changes Take Effect: When the application is started or restarted.

A shortcut key to end a chat conference. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.chat.hold

Default Value: No default value

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.128.07

The combination of keys that can be used as a keyboard shortcut to place a chat on hold. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.chat.transfer

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. Changes Take Effect: When the application is started or restarted.

A shortcut key to transfer a chat. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.consult

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and

Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to start a consultation. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.email.add-attachments

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to add an attachment to the active email interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.email.cancelforward

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to cancel forwarding the inbound email as an attachment to an external resource. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.email.completeforward

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to complete forwarding the inbound email as an attachment to an external resource. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.email.delete

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to delete the current email interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

keyboard.shortcut.interaction.email.forward

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A valid shortcut key to forward an email as an attachment. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.email.inline-forward

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

Introduced: 8.5.113.11

The combination of keys that can be used as a keyboard shortcut to forward an email to an external resource. Does not apply to Forwarding email as an attachment.

>> Back to Top

keyboard.shortcut.interaction.email.interim-send

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to send an interim copy of the current email interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.email.print

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A valid shortcut key to print an email. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.email.put-back-to-origin-queue

Default Value: Ctrl+Shift+B

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A valid shortcut key to store the email in the original queue. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

keyboard.shortcut.interaction.email.reply

Default Value: Ctrl+R

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

A shortcut key to reply to the current email interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.email.reply-all

Default Value: Ctrl+Shift+A

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

A shortcut key to reply to the sender and all recipients of the current email interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.email.save

Default Value: Ctrl+S

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

A shortcut key to save the current email interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.email.save-in-workbin

Default Value: Ctrl+Shift+W

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

A shortcut key to save the current email interaction in a workbin. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.email.send

Default Value: Ctrl+Return

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

A shortcut key to send the current email interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

keyboard.shortcut.interaction.email.transfer

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to transfer the current email interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.im.release

Default Value: Ctrl+D

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to release an IM interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.mark-done

Default Value: Ctrl+E

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

A shortcut key to mark the current interaction as done. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.preview.call-record

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to view a call record for a preview interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.preview.cancel-record

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to cancel a record for a preview interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

keyboard.shortcut.interaction.preview.mark-done

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to mark a preview interaction as done. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.preview.mark-done-get-next

Default Value: Ctrl+E

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to mark a preview interaction as done and get a new preview interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.preview.reject-record

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

 $A shortcut \ key \ to \ reject \ a \ preview \ interaction. \ For \ example: F1, \ Ctrl+Alt+V, \ Ctrl+Shift+Alt+V.$

>> Back to Top

keyboard.shortcut.interaction.pull-preview.mark-done

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to mark a pull-preview interaction as done. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.pull-preview.mark-done-get-next

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key mark a pull-preview interaction as done and get the next pull-preview interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

keyboard.shortcut.interaction.sms.delete

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to delete the current SMS interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.sms.transfer

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to transfer the current SMS interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.voice.answer-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to answer a voice call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.voice.hold-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to hold a voice call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.voice.pause-recording-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to pause recording of a voice call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

keyboard.shortcut.interaction.voice.reconnect-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to reconnect to a voice call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.voice.release-call

Default Value: Ctrl+D

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to release a voice call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.voice.resume-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to resume a voice call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.voice.resume-recording-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to resume the recording of a voice call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.voice.single-step-conference

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to start an instant voice conference. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

keyboard.shortcut.interaction.voice.single-step-transfer

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to instantly transfer a voice interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.voice.start-recording-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to start recording a voice call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.voice.stop-recording-call

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to stop recording a voice call. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.webcallback.call-contact

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to call a contact who has requested a web callback interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.webcallback.mark-done

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to mark a web callback interaction as Done. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

keyboard.shortcut.interaction.workitem.move-to-workbin

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to move the current workitem to a workbin. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.workitem.put-back-to-origin-queue

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.interaction.workitem.transfer

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to transfer the current workitem. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.state.logout

Default Value: Ctrl+Alt+X

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to logout. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.state.not-ready

Default Value: Ctrl+Alt+N

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A shortcut key to set the agent state to Not Ready. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

keyboard.shortcut.state.not-ready-after-call-work

Default Value: Ctrl+Alt+Z

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

A shortcut key to set the agent state to Not Ready After Call Work. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.state.ready

Default Value: Ctrl+Alt+R

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

A shortcut key to set the agent state to Ready. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.team-communicator.focus

Default Value: No default value

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.117.18

A valid shortcut key to set the focus to (navigate to) Team Communicator. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.teamlead.chat.bargein

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A valid shortcut key to barge in to a chat session. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.teamlead.chat.stop-monitoring

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A valid shortcut key to end monitoring of a chat session. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

keyboard.shortcut.teamlead.stop-monitoring

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A valid shortcut key to stop monitoring the current monitored target. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.teamlead.voice.bargein

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A valid shortcut key to barge in to a monitored voice interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.teamlead.voice.coaching

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A valid shortcut key to start coaching the voice interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.teamlead.voice.monitor

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A valid shortcut key to switch from coaching to monitoring the voice call. Works only for Cisco Call Manager switch. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.teamlead.voice.stop-monitoring

Default Value:

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character. **Changes Take Effect:** When the application is started or restarted.

A valid shortcut key to stop monitoring the current monitored voice interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

keyboard.shortcut.toaster.accept

Default Value: Ctrl+G

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

A shortcut key to accept a new interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

keyboard.shortcut.toaster.decline

Default Value: Ctrl+M

Valid Values: The name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, and Alt, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

A shortcut key to reject a new interaction. For example: F1, Ctrl+Alt+V, Ctrl+Shift+Alt+V.

>> Back to Top

kpi.displayed-kpis

Default Value:

Valid Values: A comma-separated list of KPI names.

Changes Take Effect: Immediately.

Defines the KPIs that are displayed to the agent. The KPI names refer to the names of the Application Option sections that are defining the KPIs.

>> Back to Top

kpi.refresh-time

Default Value: 10

Valid Values: An integer value greater than 0.

Changes Take Effect: When the application is started or restarted.

Defines the frequency of notification (in seconds) for statistics.

>> Back to Top

kpi.show-agent-groups

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specify if agent group KPI information is displayed to the agent for all groups to which the agent is a member.

license.lrm-enabled

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the Workspace signature is recognized by Genesys License Reporting Manager.

>> Back to Top

log.default-filter-type

Default Value: Copy

Valid Values: Select a value from the following list:

- copy
- skip
- hide
- hide-first, <n>
- unhide-last, < n>
- unhide-first.<n>
- unhide-last,<n>
- custom-filter,<KeyPrefix>,<KeyPost>,<ValuePrefix>,<ValuePost>

The filter 'custom-filter' enables you to define some KeyPrefix, KeyPost, ValuePrefix, ValuePost.

Example: log.default-filter-type: custom-filter,<,>,<#,#>

Changes Take Effect: Immediately.

Specifies the default view of KVList information (including UserData, Extensions, and Reasons) in the log. It is applied to the attributes of all KVList pairs except those that are explicitly defined in the log-filter-data key.

>> Back to Top

log.ESDK

Default Value: All

Valid Values: One value from this list: All, Debug, Trace, Interaction, Alarm

Changes Take Effect: Immediately.

Defines the level of logging for API ESDK.

>> Back to Top

log.expire

Default Value: 10

Valid Values: An integer value from 1 through 100.

Changes Take Effect: Immediately.

Specifies if Interaction Workspace log files and Workspace SIP Endpoint log files are to be stored. If they are stored, specifies the maximum number of files (segments) to be stored before the oldest file is removed. The value \$number\$ sets the maximum number of log files to store.

>> Back to Top

log.filter-data.<keyName>

Default Value: Copy

Valid Values: Select a value from the following list:

- copy
- skip
- hide
- hide-first, <n>
- unhide-last,<n>
- unhide-first, < n>
- unhide-last, < n>
- custom-filter, < KeyPrefix>, < KeyPost>, < ValuePrefix>, < ValuePost>

The filter 'custom-filter' enables you to define KeyPrefix, KeyPost, ValuePrefix, and ValuePost.

Example: log.filter-data.Subject: custom-filter,>,<,>#,#<

Changes Take Effect: Immediately.

Defines the treatment of specific data in the log.

It overrides the general settings specified by the log.default-filter-type option.

>> Back to Top

log.max-age

Default Value: 10

Valid Values: An integer value from 0 in days

Changes Take Effect: When the application is started or restarted.

Specifies the maximum number of days for which Workspace log files are kept. If the option value is greater than 0, the application deletes the old log files (older than the value of this option) at startup. If the option value is set to 0, log files are not deleted at startup.

>> Back to Top

log.PSDK

Default Value: Standard

Valid Values: One value from this list: All, Debug, Trace, Interaction, Standard, Alarm

Changes Take Effect: Immediately.

Specifies the level of logging for the PSDK API.

>> Back to Top

log.PSDK.SwitchPolicy

Default Value: Standard

Valid Values: One value from this list: All, Debug, Trace, Interaction, Standard, Alarm

Changes Take Effect: Immediately.

Introduced: 8.5.100.05

Specifies the level of logging for the PSDK SwitchPolicy API.

>> Back to Top

log.segment

Default Value: 10MB

Valid Values: \$number\$ KB or \$number\$ sets the maximum segment size, in kilobytes. The minimum segment size is 100 KB. \$number\$ MB sets the maximum segment size, in megabytes.

Changes Take Effect: When the application is started or restarted.

If set, specifies that there is a segmentation limit for a log file and defines the limit size in either kilobytes (KB) or megabytes (MB). If the current log segment exceeds the defined size, the file is closed and a new one is created.

>> Back to Top

log.Trace

Default Value: \$Application.RootApplicationData\$\log\InteractionWorkspace

Valid Values: A valid URL.

Changes Take Effect: Immediately.

Defines the full path of the log file. The file name uses the following extension:

?.%date{yyyyMMdd_HHmmss_fff}.log?.

The full path can also contain the following field codes:

\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$,\$Application.Exe\$, \$Application.ApplicationData\$,\$ApplicationData\$,\$Env.X\$ (where X is the name of environment variable).

>> Back to Top

log.verbose

Default Value: Trace

Valid Values: Select a value from the following list: All, Debug, Trace, Interaction, Standard, Alarm, None

Changes Take Effect: Immediately.

Defines the level of logging of overall application. If the value is set lower than the level specified by ESDK or PSDK, all levels are set to verbose. The levels correspond with the following keywords in the log file:

- Debug corresponds with the DEBUG keyword.
- Trace corresponds with the INFO keyword.
- Interaction corresponds with the WARN keyword.
- Standard corresponds with the ERROR keyword.
- Alarm corresponds with the FATAL keyword.

login.available-place-groups

Default Value:

Valid Values: A comma-separated value list of valid Place Group object names or .

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.114.08

Specifies the list of Place Groups objects agent is allowed to used for login. If \$All\$ is configured, all the PlaceGroups objects that are contained in the Agent's Tenant and on which the Agent has Read Access are available.

>> Back to Top

login.chat.auto-not-ready-reason

Default Value:

Valid Values: A valid Not-Ready Reason Action Code name of type "Not Ready"

Changes Take Effect: When the application is started or restarted

Specifies the Not Ready Reason that is displayed after an agent logs in on a channel that is not automatically set to Ready. The Not Ready Reason corresponds to the name of a Not Ready Action Code. If the reason is empty, no Not Ready Reason is displayed for the channel at log in time if the channel is in the Not Ready state. This option is ignored if the option login.chat.is-auto-ready is set to true.

>> Back to Top

login.chat.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can select and unselect (auto-login or not) the chat channel.

>> Back to Top

login.chat.is-auto-ready

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the chat channel is automatically set to the Ready state at login.

>> Back to Top

login.default-place

Default Value:

Valid Values: Valid place or place Group

Changes Take Effect: When the application is started or restarted.

Specify the Place or PlaceGroup name populated by default during login. This option can be filled by the variable \$Agent.DefaultPlace\$ (if the agent has a default place specified in the agent configuration, that Place is used; however, if no default Place exists, the agent must enter his or her Place in the Place field).

login.email.auto-not-ready-reason

Default Value:

Valid Values: A valid Not-Ready Reason Action Code name of type "Not Ready"

Changes Take Effect: When the application is started or restarted

Specifies the Not Ready Reason that is displayed after an agent logs in on a channel that is not automatically set to Ready. The Not Ready Reason corresponds to the name of a Not Ready Action Code. If the reason is empty, no Not Ready Reason is displayed for the channel at log in time if the channel is in the Not Ready state. This option is ignored if the option login.email.is-autoready is set to true.

>> Back to Top

login.email.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can select and unselect (auto-login or not) the e-mail channel.

>> Back to Top

login.email.is-auto-ready

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the e-mail channel is automatically set to the Ready state at login.

>> Back to Top

login.enable-login-without-channel

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether agents can login to the Workspace application without being logged in to any channels.

>> Back to Top

login.enable-place-completion

Default Value: true **Valid Values:** true or false

Changes Take Effect: When the application is started or restarted.

This option is used for performance issue at login time (when a lot of agents logs in at the same time). Set this option to false to disable the load of all the places when the Workspace is started. This improves the performance if there are a lot of places in your environment. The restriction with this option set to false is that there is no longer a list of available places in the 2nd login panel.

login.enable-same-agent-place

Default Value: true

Valid Values: true, false, prompt

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can login on the same Place from different workstations. The value prompt allows the agent to login on the same Place from different workstations, but the agent is first prompted for confirmation before an additional login is permitted.

Note: This option is applicable only when the agent is granted only Voice and/or Instant Messaging channels. It is not applicable for eServices medias.

>> Back to Top

login.im.auto-not-ready-reason

Default Value:

Valid Values: A valid Not-Ready Reason Action Code name of type "Not Ready"

Changes Take Effect: When the application is started or restarted

Dependencies: login.im.is-auto-ready

Related Options: login.voice.auto-not-ready-reason

Specifies the Not Ready Reason that is displayed after an agent logs in on a channel that is not automatically set to Ready. The Not Ready Reason corresponds to the name of a Not Ready Action Code. If the reason is empty, no Not Ready Reason is displayed for the channel at log in time if the channel is in the Not Ready state. This option is ignored if the option login.im.is-autoready is set to true. For a channel with the capacity "voice/im", if the login.voice.auto-not-ready-reason option is empty, the channel uses the value of the login.im.auto-not-ready-reason option to determine the Not Ready Reason.

>> Back to Top

login.im.available-queues

Default Value: ACDQueue

Valid Values: "" or a combination of: ACDQueue, RoutingPoint, VirtualQueue

Changes Take Effect: When the application is started or restarted.

Specifies the way the list of available queues is displayed to the agent. If the option value is left blank, no queue is displayed to the agent; the agent can enter any valid login queue name. If set to a combination of the valid values, the agent must select the queue from the list of objects that is provided by the configuration.

>> Back to Top

login.im.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted

Specifies whether the agent can select and unselect (auto-login or not auto-login) the Instant Messaging channel.

>> Back to Top

login.im.is-auto-ready

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted

Specifies whether the IM channel is automatically set to the Ready state at login.

>> Back to Top

login.im.prompt-agent-login-id

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can select a login id from the configured ones for the IM channel in the login window.

>> Back to Top

login.im.prompt-dn-password

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent must enter his password for the IM channel in the login window.

>> Back to Top

login.im.prompt-queue

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent must enter the ACD Queue for the IM channel in the login window.

>> Back to Top

login.place-location-source

Default Value: standard

Valid Values: A value from the following list: standard,machine-name,vdi **Changes Take Effect:** When the application is started or restarted.

Dependencies: login.store-recent-place

Introduced: 8.5.112.08

Specifies how Workspace stores the last selected login Place or PlaceGroup in the Windows User Profile when the value of the login.store-recent-place option is set to true. The following values (modes) are supported:

- standard The most recently used Place or PlaceGroup is stored in the Windows User Profile without any information about the workstation. This is the legacy recent place storage model.
- machine-name The most recently used Place or PlaceGroup is stored in the Windows User Profile, along with the name of the machine where the Workspace application is running. Use this value when Workspace is installed on the physical workstation where the agent logs in.
- vdi The most recently used Place or PlaceGroup is stored in the Windows User Profile, along with
 the name of the physical machine from which the agent executes a virtual session (for example, in
 Citrix XenApp/XenDesktop, VMWare Horizon, and Windows Terminal Server environments). Use this
 value when Workspace is installed in a Virtual Desktop Environment. If the machine name of the VDI

client is not found, for example because user is running Workspace on a physical workstation, the machine-name mode is used instead. Use this value in hybrid environments where agents use Workspace both on physical workstations and in virtual sessions.

>> Back to Top

login.place-selection-type

Default Value: Place

Valid Values: Comma separated list of types from the following list: Place, PlaceGroup.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.114.08

Specifies the types of object that can be used to fill place selection. About PlaceGroup, see reference login.available-place-groups.

>> Back to Top

login.place-state-timeout

Default Value: 30

Valid Values: Any positive integer.

Changes Take Effect: When the application is started or restarted.

Specifies how long Workspace should wait for information about the state of a Place when checking Place availability at login time.

>> Back to Top

login.prompt-place

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent must enter a Place or a PlaceGroup name in the login window.

>> Back to Top

login.sip-cluster.phone-number

Default Value:

Valid Values: Any valid device number or a string that contains one of the following field codes: \$Agent.Employeeld\$. **Changes Take Effect:** When the application is started or restarted.

Specifies the device number that is used to log in an agent to the SIP Cluster. This option can use the \$Agent.Employeeld\$ variable. If the value of the option is empty, agents must enter their phone number for the voice channel in the Login view.

>> Back to Top

login.sip-cluster.store-recent-phone-number

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Dependencies: login.sip-cluster.phone-number

Specifies whether the phone number that was typed during the most recent login to the SIP Cluster infrastructure is stored in the user profile so that it can be restored during the next login.

This option is available if the login.sip-cluster.phone-number option is empty.

>> Back to Top

login.sms.auto-not-ready-reason

Default Value:

Valid Values: A valid Not-Ready Reason Action Code name of type "Not Ready"

Changes Take Effect: When the application is started or restarted

Dependencies: login.sms.is-auto-ready

Specifies the Not Ready Reason that is displayed after an agent logs in on a channel that is not automatically set to Ready. The Not Ready Reason corresponds to the name of a Not Ready Action Code. If the reason is empty, no Not Ready Reason is displayed for the channel at log in time if the channel is in the Not Ready state. This option is ignored if the option login.sms.is-autoready is set to true.

>> Back to Top

login.sms.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can select and unselect (activate and deactivate) the SMS channel.

>> Back to Top

login.sms.is-auto-ready

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the SMS channel is automatically in the ready state at agent login.

>> Back to Top

login.store-recent-place

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Dependencies: login.default-place

Specifies whether the most recently used Place or PlaceGroup is stored. This option is available if the login.default-place
option is not set to \$Agent.DefaultPlace\$.

>> Back to Top

login.store-username

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.103.10

Specifies whether the most recently used Username is stored locally in the user profile. If the value is false, the previous value is cleared.

>> Back to Top

login.voice.auto-not-ready-reason

Default Value:

Valid Values: A valid Not-Ready Reason Action Code name of type "Not Ready" Changes Take Effect: When the application is started or restarted Dependencies: login.voice.is-auto-ready, login.voice.auto-not-ready-reason

Related Options: login.im.auto-not-ready-reason

Specifies the Not Ready Reason that is displayed after an agent logs in on a channel that is not automatically set to Ready. The Not Ready Reason corresponds to the name of a Not Ready Action Code. If the reason is empty, no Not Ready Reason is displayed for the channel at log in time if the channel is in the Not Ready state. This option is ignored if the option login.voice.is-autoready is set to true. For a channel with the capacity "voice/im", if the login.voice.auto-not-ready-reason option is empty, the channel uses the value of the login.im.auto-not-ready-reason option to determine the Not Ready Reason.

>> Back to Top

login.voice.available-queues

Default Value: ACDQueue

Valid Values: "", or a combination of ACDQueue,RoutingPoint,VirtualQueue **Changes Take Effect:** When the application is started or restarted.

Specifies the way the list of available queues is displayed to the agent. If the option value is left blank, no queue is displayed to the agent; the agent can enter any valid login queue name. If this option is set to a combination of the valid values, the agent must select the queue from the list of objects that is provided by the configuration.

>> Back to Top

login.voice.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted

Specifies whether the agent can select and unselect (auto-login or not auto-login) the voice channels.

>> Back to Top

login.voice.force-relogin

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted

Specifies whether the voice channels should be re-logged on automatically if logged off from outside the application. This option is applicable to SIP Server Business Continuity deployments only.

Notes:

- This option was previously incorrectly documented as login.force-relogin
- Genesys recommends that you do not use this feature if you are using the enhanced support of

graceful shutdown in Business Continuity environments, beginning with release 8.5.108.11.

>> Back to Top

login.voice.is-auto-ready

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted

Specifies whether the voice channels are in the Ready state at login.

>> Back to Top

login.voice.prompt-agent-login-id

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction

Specifies whether the agent can select a login id from the configured ones for the voice channel in the login window.

>> Back to Top

login.voice.prompt-dn-less-phone-number

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether a DN-less phone number is prompted for in the login window. This option can be defined in a **PlaceGroup** Object. This option is specific to SIP Server environments.

>> Back to Top

login.voice.prompt-dn-password

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent must enter his password for the voice channel in the login window.

>> Back to Top

login.voice.prompt-queue

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent must enter the ACD Queue for the voice channel in the login window.

login.voice.restore-dn-less-phone-number-on-logout

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted

Introduced: 8.5.140.08

Related Options: login.voice.prompt-dn-less-phone-number

In SIP Server environments, this option specifies whether the DN-less phone number stored in the annexes of the agent's DN in Configuration Server is restored to its original value when the agent logs out of this DN. This option is applicable only when the value of the login.voice.prompt-dn-less-phone-number option is set to true.

>> Back to Top

login.voice.use-dn-less-login-extension

Default Value: false **Valid Values:** true, false

Changes Take Effect: At next voice channel login.

Introduced: 8.5.141.04

Related Options: login.voice.prompt-dn-less-phone-number

Specifies how the DN-less phone number provided by an agent during login is propagated to the Genesys back-end:

- false: The phone number is stored in the agent's DN annex in Configuration Server.
- true: The phone number is passed as an extension through the agent's login request to SIP Server (SIP Server 8.1.102.93 or higher is required).

>> Back to Top

login.webcallback.auto-not-ready-reason

Default Value:

Valid Values: A valid not ready reason

Changes Take Effect: When the application is started or restarted

Dependencies: login.webcallback.is-auto-ready

Specifies the Not Ready Reason that is displayed after an agent logs in on a channel that is not automatically set to Ready. The Not Ready Reason corresponds to the name of a Not Ready Action Code. If the reason is empty, no Not Ready Reason is displayed for the channel at log in time if the channel is in the Not Ready state. This option is ignored if the option login.webcallback.is-auto-ready is set to true.

>> Back to Top

login.webcallback.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can select and unselect (auto-login or not auto-login) the web callback channel.

>> Back to Top

login.webcallback.is-auto-ready

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the Web Callback channel is automatically set to the Ready state at login.

>> Back to Top

login.workmode

Default Value: unknown

Valid Values: unknown, auto-in, manual-in

Changes Take Effect: When the application is started or restarted or if the agent changes place.

Specifies the workmode that is applied when the voice DN logs in. If this option is set to auto-in, the agent is automatically in Ready state. If this option is set to manual-in, the agent must manually activate the Ready state. To determine whether your switch supports the workmode, refer to the Deployment Guide of the relevant T-Server.

>> Back to Top

login.<media-type>.auto-not-ready-reason

Default Value: false

Valid Values: A valid not ready reason

Changes Take Effect: When the application is started or restarted. **Dependencies:** login. keyworkitemchannel>.is-auto-ready

Specifies the Not Ready Reason that is displayed after an agent logs in on a channel that is not automatically set to Ready. The Not Ready Reason corresponds to the name of a Not Ready Action Code. If the reason is empty, no Not Ready Reason is displayed for the channel at log in time if the channel is in the Not Ready state. This option is ignored if the option <a href="login. login.keyworkitemchannel.is-auto-ready is set to true.

>> Back to Top

login.<media-type>.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can select and unselect (auto-login or not auto-login) the specific Workitem channel.

>> Back to Top

login.<media-type>.is-auto-ready

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the indicated workitem channel is automatically set to the Ready state at login.

>> Back to Top

logout.enable-exit-on-logoff-error

Default Value: true

Valid Values: true, false, prompt

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can log out from the application even if one of the voice channel log offs resulted in an error. The value **prompt** allows the agent to log out of the application if a log-off channel error occurs. The agent is first prompted for confirmation before logging out of the application.

>> Back to Top

logout.voice.use-login-queue-on-logout

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.124.08

(For Alcatel 4400/OXE switch only) Specifies whether or not the queue that is used on login is also used for the queue on logout.

- If this option is set to true, Supervisors must refine their Place/Channel information to None before selecting Exit.
- If this option is set to false, Supervisors are not required to refine their Place/Channel information to log out correctly.

>> Back to Top

main-window.auto-hide-display-delay

Default Value: 0

Valid Values: Any positive integer

Changes Take Effect: At the next interaction.

Introduced: 8.5.136.07

When the Main Window - Can Auto-hide the Main Window privilege is granted, this option specifies the duration, in milliseconds, for which the Main Window remains hidden before being displayed when the mouse is at the top of the screen. The value 0 means specifies the minimum value.

>> Back to Top

main-window.bypass-auto-hide-conditions

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.109.16

In environments where an agent is granted the privilege to auto-hide the main window, the value of this option can be set to true when it is necessary to bypass the default control that disables the Workspace auto-hide function when a third party auto-hide window is reported as already present by the Windows Operating System. This is useful in a Citrix XenApp environment where Workspace is running as a Seamless Window.

>> Back to Top

main-window.window-title

Default Value: \$Window.Title\$

Valid Values:

\$Window.Title\$,\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$. Changes Take Effect: Immediately.

Defines the title of the Main Window that appears in the Windows Task Bar by specifying a string that contains the following field codes:

\$Window.Title\$,\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$, \$Agent.LastName\$,\$Agent.FirstName\$,
\$Agent.EmployeeId

If all field codes are empty, the following field codes are used:

\$Window.Title\$

>> Back to Top

openmedia.bundle.sms

Default Value: sms,smssession **Valid Values:** sms, smssession, mms

Changes Take Effect: When the application is started or restarted.

Modified: 8.5.110.13

Specifies the list of media types that are used to implement the SMS channel. The value sms specifies the SMS Page media-type, and the value smssession specifies the SMS Session media-type. The value mms enables the attachment of images as Multimedia Message Service (MMS) to an SMS interaction. MMS is a separate media channel that appears as part of the SMS channel in the agent interface.

>> Back to Top

openmedia.workitem-channels

Default Value:

Valid Values: A comma-separated list of valid Media Types. **Changes Take Effect:** When the application is started or restarted.

Specifies the list of Workitem channels that are used by the agent.

>> Back to Top

options.clean-up-former-record-location

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Dependencies: options.record-location

Introduced: 8.5.112.08

Specifies whether locally stored configuration information should be removed from a shared folder or Person's annex. Use this option when you enable the options.record-location option.

>> Back to Top

options.record-location

Default Value:

Valid Values: A valid file path to a host directory.

Changes Take Effect: When the application is started or restarted.

Dependencies: options.record-option-locally-only

Introduced: 8.5.112.08

In environments where the value of the options.record-option-locally-only is set to false, this option specifies the location where agent preferences are stored when an agent exits the application. If the value of this option is left empty, agent preferences are stored in Person's Annex in Configuration Server. The full path can also contain the following field codes: \$Agent.UserName\$, \$Agent.LastName\$, \$Agent.FirstName\$, \$Agent.EmployeeId\$, \$Env.X\$ (where X is the name of the environment variable). Genesys recommends that you append the agent's Username to the specified path as shown above.

options.record-option-locally-only

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the display settings for the agent are stored locally or in the agent annex.

>> Back to Top

outbound.assured-connection.allow-release-engaging-call-timeout

Default Value: -1

Valid Values: any integer greater or equal to -1

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.150.06

Specifies the time, in seconds, after which an engaging call of Outbound Assured Connection can be released. If the value -1 is specified, an engaging call is not allowed to release.

>> Back to Top

outbound.call-result-automatically-selected

Default Value:

Valid Values: Select one value from the list.
Changes Take Effect: At the next interaction.
Dependencies: outbound.call-result-values

Specifies the call result to be selected by default for outbound records. The specified call result must be defined by the values that are specified for the outbound.call-result-values option. If set to an empty value, the current call result of the outbound record is selected, or 'unknown' is selected if there is no current value.

>> Back to Top

outbound.call-result-is-mandatory

Default Value: false Valid Values: true, false

Changes Take Effect: Immediatly.

Specifies whether it is mandatory for agents to set a Call Result before Marking Done an Outbound interaction. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

outbound.call-result-values

Default Value: Answered, Answering Machine, Busy, No Answer, Wrong Number **Valid Values:** Select at least one item from the list. **Changes Take Effect:** At the next interaction.

The list of call results that are available for the agent to use for outbound interaction. The call results are displayed in the order in which they appear in the list. Specify one or more items from the following list:

- · Abandoned (Abandoned)
- AgentCallbackError (Agent Callback Error)

- AllTrunksBusy (All Trunks Busy)
- Answered (Answered)
- AnsweringMachine (Answering Machine)
- Busy (Busy)
- CallDropError (Call Drop Error)
- CancelRecord
- DialError (Dial Error)
- DoNotCall (Do Not Call)
- Dropped (Dropped)
- DroppedNoAnswer (Dropped No Answer)
- FaxDetected (Fax Detected)
- General Error (General Error)
- GroupCallbackError (Group Callback Error)
- NoAnswer (No Answer)
- NoDialTone (No Dial Tone)
- NoEstablished (No Established)
- NoFreePortError (No Free Port Error)
- NoProgress (No Progress)
- NoRingback (No Ringback)
- NuTone (Nu Tone)
- 0k (Ok)
- PagerDetected (Pager Detected)
- Silence (Silence)
- SitDetected (Sit Detected)
- SitInvalidNum (Sit Invalid Num)
- SitNoCircuit (Sit No Circuit)
- SitOperintercept (Sit Operintercept)
- SitReorder (Sit Reorder)
- SitUnknown (Sit Unknown)
- SitVacant (Sit Vacant)
- Stale (Stale)
- SwitchError (Switch Error)
- SystemError (System Error)
- TransferError (Transfer Error)
- Unknown (Unknown)

- WrongNumber (Wrong Number)
- WrongParty (Wrong Party)

>> Back to Top

outbound-callback.ringing-bell

Default Value: Sounds\Ring.mp3|10|-1|primary

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric values.

Changes Take Effect: At the next interaction.

Related Options: application.secondary-audio-out-device

Specifies the sound-configuration string of a scheduled callback pushed to the agent as a preview. For example: "Sounds\ Ring.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority. The higher the integer the higher the priority.
- 3. The duration:
 - a. -1 means plays and repeats until an explicit message stops it. For example, the established event stops the ringing sound.
 - b. 0 means play the whole sound one time.
 - c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value |primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

>> Back to Top

outbound.callback-types

Default Value: personal, campaign

Valid Values: A comma separated list of callback types from the following list: personal, campaign

Changes Take Effect: At the next interaction.

Introduced: 8.5.115.17

Specifies whether an agent can select a personal callback or a campaign callback when rescheduling an Outbound campaign record, or whether all callbacks are either personal or campaign. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

outbound.campaign-stale-timeout

Default Value: 0

Valid Values: An integer value

Changes Take Effect: When the application is started or restarted.

Records remain editable for a specified period of time after a campaign is unloaded, to reflect the Outbound Contact Server (OCS) OCServer section stale_clean_timeout option. A value of 0 means that the outbound record becomes read-only when the campaign is unloaded. A positive value is the duration, in minutes, during which the outbound record remains editable. During this period, the agent sees the campaign as Active. The campaign is removed from the campaigns list after this period. A value of -1 means that the outbound record is always editable (however, this action may fail in the OCS).

>> Back to Top

outbound.complete-record-before-transfer

Default Value: false Valid Values: true, false

Changes Take Effect: At the next transfer attempt.

Introduced: 8.5.117.18

Specifies whether the processing of an Outbound record will be completed when the call is transferred or conferenced. If the value is set to false, the outbound record will be editable after the call is transferred or conferenced; Workspace attempts to update the record in OCS accordingly; however, the update operation can fail, depending on topology. If the target agent is part of the campaign, he or she can edit the record. This is the legacy behavior. If the value is set to true, the Outbound record will be marked as processed and the Outbound record fields will become read-only after the call is transferred or conferenced. Workspace updates and closes the record in OCS before validating the call transfer; the target agent receives a read-only record.

>> Back to Top

outbound.fields.float-separator-in-db

Default Value:

Valid Values: A valid float separator. Typical float separators are: '.' (period), ',' (comma), and '\' (backslash). Changes Take Effect: Immediately.

Specifies the separator that is used for floating point numbers in the database for outbound fields. This option should be used when the decimal symbol in the regional settings of the agent workstation is different from the one provided by the database.

>> Back to Top

outbound.load-at-startup

Default Value: false Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.109.16

When the value of this option is set to true, the description of all the Outbound Calling Lists visible to the logged in agent is loaded and cached at login time. When the value of this option is set to false, the description of the Outbound Calling Lists assigned to a specific Campaign is loaded on demand when the agent is notified by Outbound Server that he or she is engaged in this Outbound Campaign.

>> Back to Top

outbound.push-preview.auto-answer

Default Value: false Valid Values: true, false

Changes Take Effect: At the next interaction.

Specifies whether a push preview outbound interaction is automatically accepted when Interaction Server Invite event is received. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

outbound.push-preview.auto-answer.enable-reject

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Dependencies: outbound.push-preview.auto-answer, outbound.push-preview.auto-answer.timer

Introduced: 8.5.105.12

Specifies whether the **Reject** button is available in the interaction notification when the value of outbound.push-preview.auto-answer is set to true and the value of outbound.push-preview.auto-answer.timer is greater than 0. The privilege to reject interactions must be granted. This option can be overridden by a routing strategy, as described in This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy..

>> Back to Top

outbound.push-preview.auto-answer.timer

Default Value: 0

Valid Values: Any integer greater than or equal to 0. Changes Take Effect: At the next interaction.

Dependencies: outbound.push-preview.auto-answer

Introduced: 8.5.105.12

Specifies the time, in seconds, after which an incoming interaction is automatically answered if the value of outbound.push-preview.auto-answer is set to true. If the value 0 is specified, interactions are immediately auto-answered. If any positive integer value is specified, then an interaction notification is displayed to the agent and a timer counts down the seconds until the interactions is auto-answered. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

outbound.push-preview.media-types

Default Value: outboundpreview

Valid Values: A comma separated list of valid media-types. Changes Take Effect: When the application is started or restarted.

The list of media types that are available for the agent to use for outbound push-preview interactions.

>> Back to Top

outbound.push-preview.use-combined-channel

Default Value: true **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the outboundpreview channel is combined with the voice channel in the User Interface. If set to 'true', only the voice channel is presented, and any change in the status of one channel is applied to the other channel

>> Back to Top

outbound.record-information.frame-color

Default Value: #FF17849D

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB

hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: At the next interaction.

Specifies the background color the Record Information view header of Outbound interactions. Examples: #FFFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

outbound.record-information.header-foreground-color

Default Value: #FFFFFFF

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB beyodecimal color code (3 values in the '00'-'FF' range)

hexadecimal color code (3 values in the '00'-'FF' range). Changes Take Effect: At the next interaction.

Specifies the color of the text of the Record Information view header of Outbound interactions. Example #FFFFFFF for white color. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

outbound.reschedule-inherit-parent-availability-interval

Default Value: false Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies how Workspace populates the default values of the availability ("From" and "Till") interval for a new outbound record created when rescheduling to a new number.

- false: the default values are retrieved from the "From" and "Till" Field object of the Configuration
- true: the "From" and "Till" are inherited from the parent record.

>> Back to Top

outbound.sound.campaign-updated

Default Value:

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric values.

Changes Take Effect: At the next interaction.

Related Options: application.secondary-audio-out-device, application.secondary-audio-out-device

Specifies the sound-configuration string when the campaign status is updated. For example: "Sounds\Ring.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority. The higher the integer the higher the priority.
- 3. The duration:
 - a. -1 means plays and repeats until an explicit message stops it. For example, the established event stops the ringing sound.
 - b. 0 means play the whole sound one time.
 - c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.

- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

>> Back to Top

outbound.timed-preview-auto-dial

Default Value: -1

Valid Values: -1, 0, or any positive integer. **Changes Take Effect:** At the next interaction.

Introduced: 8.5.109.16

Specifies whether agents in Preview, Push preview, and Reschedule preview campaigns can manually dial a record (-1), have the call auto-dialed as soon as the record is accepted (0), or have the call auto-dialed after a specified number of seconds. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

outbound.treatment-mode

Default Value: none

Valid Values: Select one value from the following list: personal, campaign, none.

Changes Take Effect: Immediately.

Specifies the type of treatment to be applied for the outbound record after it is marked as processed.

- none—The application never applies any treatment to mark processed requests.
- campaign—The treatment RecordTreatCampaign is applied to the record when a mark processed action is executed.
- personal—The treatment RecordTreatPersonal is applied to the record when a mark processed action is executed.

>> Back to Top

presence.evaluate-presence

Default Value: true **Valid Values:** true or false

Changes Take Effect: When the application is started or restarted.

When this option is set to true, the presence (availability) of agents, agent groups, T-Server queues, routing points, and interaction queues is shown in Team Communicator in the search results.

>> Back to Top

printing.use-print-preview

Default Value: true

Valid Values: true, false

Changes Take Effect: Immediately.

Specifies whether a print preview is shown when the user request to print a document. If set to true the Print Preview window is displayed when an agent clicks **Print**. If set to false the standard system print dialog box is displayed.

>> Back to Top

reporting.case.report-case-in-focus-duration

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.112.08

When set to true, Workspace reports to the Genesys back-end the time, in seconds, when an interaction had the focus. When set to false, nothing is reported.

>> Back to Top

screen-recording.client.address

Default Value:

Valid Values: A valid IP address or host.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.143.08

Specifies the IP address or host of the Screen Recording Service. If left blank, the connection to the Screen Recording Service is established on the localhost, according the IP version specified at the system level.

>> Back to Top

screen-recording.client.max-attempts

Default Value: 5

Valid Values: An integer greater than 0.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.106.19

Specifies the maximum number of attempts to establish communication with Screen Recording Client at Workspace initialization time before considering the Screen Recording Client inactive.

>> Back to Top

screen-recording.client.ping-interval

Default Value: 10000

Valid Values: An integer greater than 0.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.106.19

Specifies the interval in milliseconds between two keep-alive requests to Screen Recording Client.

>> Back to Top

screen-recording.client.port

Default Value: 443

Valid Values: A valid TCP/IP port number.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.106.19

Specifies the port on which Screen Recording Client listens for credentials. The value of this option should be set to 443.

>> Back to Top

screen-recording.client.secure-connection

Default Value: true **Valid Values:** true, false.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.106.19

Specifies whether secure connection should be used for the communication between Workspace and Screen Recording Client.

>> Back to Top

screen-recording.htcc.peer_uri

Default Value:

Valid Values: Any valid HTTP/HTTPS URI.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.118.10

Specifies the URI representing the HTTP/HTTPS access to the Genesys Interaction Recording Web Services (or Genesys Web Services for older versions of the Genesys Interaction Recording solutions) of the peer site in a Disaster Recovery deployment. For example: http://server.domain:443.

>> Back to Top

screen-recording.htcc.uri

Default Value:

Valid Values: A valid HTTP/HTTPS URI.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.106.19 Modified: 8.5.116.10

Specifies the URI representing the HTTP/HTTPS access to Genesys Interaction Recording Web Services (or Genesys Web Services for older versions of the Genesys Interaction Recording solutions). For example: http://server.domain:443.

>> Back to Top

security.client-authentication-certificate-search-value

Default Value: A string value or one of the supported field codes, Workspace uses to select a certificate. **Valid Values:** A string value or one of the supported field codes, Workspace uses to select a certificate. **Changes Take Effect:** When the application is started or restarted.

Introduced: 8.5.148.04

For mutual TLS only. Specifies a string or one of the supported field codes that Workspace should use to select a certificate from the Windows Certificate Store to be used on the client-side to authenticate to server.

Search order with this value is:

- 1. The certificate **Thumbprint**.
- The certificate Subject with this value, such as: Email, Common Name, Organizational Unit, and so on.
- 3. The certificate **Subject Alternative Name** with this value.

Supported field codes:

- \$Agent.UserName\$: The User Name.
- \$Agent.UPN\$: The Explicit User Principal Name (eUPN) specified in the Windows Active Directory by the Windows Administrator when provisioning the agent account. This mode is deprecated and should be substituted by implicitUPN.
- \$Agent.ImplicitUPN\$: The Implicit User Principal Name (iUPN), which is a combination of the samAccountName and the user's Domain.
- \$Agent.SAMAccountName\$: The SAM Account Name attribute in the Windows Active Directory specified by the Windows Administrator when provisioning the agent account.
- \$Agent.MachineName\$: The Machine Name attribute.
- \$Agent.MachineNameWithDomain\$: The period (.) separated combination of Machine Name and Domain attributes.

Note: For authentication to Configuration Server, this option should be present in the local InteractionWorkspace.exe.config configuration file.

>> Back to Top

security.disable-rbac

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Disables role based access (RBAC). If this option is set to true, all the Workspace tasks are available to the agents. If this option is set to false, the list of agent tasks must be defined in Genesys Administrator.

>> Back to Top

security.enable-debug-information

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediately.

For the About window, this option specifies whether agents are able to display the controls that provide quick access to the Executable directory, the Log directory, the GC, and so on, if they CTRL+Click the Genesys logo in the About box.

>> Back to Top

security.inactivity-force-not-ready-state

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.139.06

Specifies whether channels that are in a Not Ready status (with or without a Not Ready Reason) are forced to new Not Ready Reason status specified by the security.inactivity-not-ready-reason option when workstation is locked. If the value of this option is set to false, only the status of channels with Ready and After Call Work statuses are updated. Depends on security.inactivity-set-agent-not-ready.

security.inactivity-not-ready-reason

Default Value:

Valid Values: A valid not ready reason

Changes Take Effect: When the application is started or restarted.

Dependencies: inactivity.set-agent-not-ready

Specifies the Not Ready Reason if the inactivity.set-agent-not-ready option is set to true.

>> Back to Top

security.inactivity-set-agent-not-ready

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent is automatically set to Not Ready when agent inactivity is detected.

>> Back to Top

security.inactivity-timeout

Default Value: 0

Valid Values: Any integer from 0 through 100.

Changes Take Effect: When the application is started or restarted.

Specifies the amount of time in minutes of agent inactivity (no mouse or keyboard usage) that triggers application locking. If the agent has been inactive longer than the number of minutes that are specified by the inactivity timeout, the agent must reauthenticate to be able to use the Workspace application. A value of 0 disables this functionality.

>> Back to Top

security.session-lock-force-not-ready-state

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.139.06

Related Options: security.session-lock-not-ready-reason, security.session-lock-set-agent-not-ready

Specifies whether channels that are already in a Not Ready status (with or without a Not Ready Reason) are switched to the Not Ready reason specified by the security.session-lock-not-ready-reason option when the agent is set to Not Ready when their workstation is locked. If the value of this option is set to false, only the status of channels in the Ready and After Call Work statuses are updated. Depends on security.session-lock-set-agent-not-ready.

>> Back to Top

security.session-lock-not-ready-reason

Default Value: No default value **Valid Values:** A valid Not Ready reason

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.139.06

Specifies the Not Ready Reason used when the agent status is set to the Not Ready on session lock. Depends on security.session-lock-set-agent-not-ready.

security.session-lock-set-agent-not-ready

Default Value: false Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.139.06

Specifies whether the agent status is switched to Not Ready automatically when the Windows session is locked while the agent

state is Ready.

>> Back to Top

sip-cluster.data-center-locations

Default Value:

Valid Values: A comma separated list of data center location names. **Changes Take Effect:** When the application is started or restarted.

Specifies the list of data center locations that are available for SIP Clustering.

>> Back to Top

sip-cluster.reconnect-timeout

Default Value: 10

Valid Values: from 0 to MAXINT Changes Take Effect: Immediatly.

In SIP Cluster environment, specifies the duration, in seconds, between each attempt to reconnect to SIP Server (TController) and/ or Stat Server in the case of a connection loss.

>> Back to Top

sipendpoint.authenticate-with-dn-password

Default Value: false Valid Values: true, false

Changes Take Effect: At next Log Off operation or at next login.

Modified: 8.5.117.26

Related Options: login.voice.prompt-dn-password

Specifies how Workspace Desktop Edition configures Workspace SIP Endpoint so that it can populate the password in the SIP Requests that require authentication:

- false: If the DN where agent is logging in has the TServer/authenticate-requests option set to a valid non-empty value, Workspace Desktop Edition configures Workspace SIP Endpoint with the value that it reads in the TServer/password. DN option.
- · true: Workspace Desktop Edition configures Workspace SIP Endpoint with the DN password that is specified by the agent in the advanced Login window (activated by the login.voice.prompt-dnpassword).

>> Back to Top

sipendpoint.codecs.g729/8000.fmtp

Default Value: annexb=yes

Valid Values: annexb=yes, annexb=no

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.101.14

Specifies whether the G729 codec is configured with AnnexB = Yes or AnnexB = No.

>> Back to Top

sipendpoint.codecs.h264.fmtp

Default Value: profile-level-id=420028

Valid Values: The string 'profile-level-id=' followed by a sequence of 3 hexadecimal values in the '00'-'FF' range that

respectively define the profile_idc, profile-iop and level-idc.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.policy.session.auto_accept_video

Introduced: 8.5.101.14

Specifies the profile of the H.264 codec. This option is applicable only if the value of the sipendpoint.policy.session.auto_accept_video option is set to 1.

>> Back to Top

sipendpoint.core-deadlock-detection-delay

Default Value: 12500

Valid Values: Any positive integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the time, in milliseconds, that Workspace SIP Endpoint waits when it detects that its main subsystem has become unresponsive before considering itself deadlocked. When Workspace SIP Endpoint considers itself deadlocked, it automatically restarts. Genesys recommends that you specify a value greater than 12500 ms.

>> Back to Top

sipendpoint.enable-ipv6

Default Value: auto

Valid Values: A value from the following list: auto, false, true.

Changes Take Effect: When the application is started or restarted.

Specifies that the GCTI_CONN_IPV6_ON environment variable can be overridden for connections to SIP Server and RTP. If the value auto and the GCTI_CONN_IPV6_ON variable does not exist, then the value of ip-version is set to 4,6.

>> Back to Top

sipendpoint.exit-on-voice-logoff

Default Value: false **Valid Values:** true, false

Changes Take Effect: At next Log Off operation or at next login.

Specifies whether Interaction Workspace SIP Endpoint is unregistered and stopped if the voice channel is logged off manually by an agent. If the value of this option is set to 'true', the corresponding voice DN is also unregistered from SIP Server and therefore Interaction Workspace does not get notifications of any activity that occurs on it. If an agent manually Logs On to the voice channel, the corresponding DN is registered again and Interaction Workspace SIP Endpoint is restarted.

sipendpoint.headset-enforce-configured-usage

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted. **Dependencies:** sipendpoint.genesys.device.headset_name

Specifies whether the SIP Endpoint must wait for the detection of the headset that is configured in the sipendpoint.genesys.device.headset_name option before finalizing initialization. The agent remains logged out until the headset is detected.

>> Back to Top

sipendpoint.headset-replugged-set-ready

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent SIP DN is set automatically to Ready when the headset that is used by the agent is plugged back in.

>> Back to Top

sipendpoint.headset-unplugged.not-ready-reason

Default Value:

Valid Values: A valid Not Ready reason.

Changes Take Effect: When the application is started or restarted. Dependencies: sipendpoint.headset-unplugged-set-not-ready

Specifies the Not Ready reason that is to be set for the SIP DN when the headset that is used by the agent is unplugged and sipendpoint.headset-unplugged-set-not-ready option is set to true.

>> Back to Top

sipendpoint.headset-unplugged-set-not-ready

Default Value: true Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent SIP DN is set automatically to Not Ready when the headset that is configured for the agent is unplugged.

>> Back to Top

sipendpoint.init-attempt-nb

Default Value: 10

Valid Values: A positive integer value.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.init-attempt-timer

The maximum number of communication attempts between Workspace and Workspace SIP Endpoint during initialization. This option works in conjunction with the sipendpoint.init-attempt-timer option.

sipendpoint.init-attempt-timer

Default Value: 1

Valid Values: A positive integer value.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.init-attempt-nb

The interval of time, in seconds, between attempts to communicate with the Workspace SIP Endpoint during initialization. This option works in conjunction with the sipendpoint.init-attempt-nb option.

>> Back to Top

sipendpoint.ip-version

Default Value: auto

Valid Values: auto, 4,6, or 6,4

Changes Take Effect: When the application is started or restarted.

Specifies the Internet Protocol Version of connections to SIP Server and RTP. The value auto specifies that the Internet Protocol Version is inherited by the value set for the ip-version option or the GCTI_CONN_IP_VERSION environment variable. If the GCTI_CONN_IP_VERSION environment variable does not exist, the value of the ip-version option is set to 4,6.

>> Back to Top

sipendpoint.log.expire

Default Value: 10

Valid Values: An integer value from 1 through 100.

Changes Take Effect: When the application is started or restarted.

Specifies if log files are stored. If they are stored, specifies the maximum number of files (segments) to be stored before the oldest file is removed. \$number\$ sets the maximum number of log files to store.

This entire requires Westerness SIR Endocite 9.5.102 or above.

This option requires Workspace SIP Endpoint 8.5.102 or above.

>> Back to Top

sipendpoint.log.segment

Default Value: 10MB

Valid Values: \$number\$ KB, \$number\$ MB

Changes Take Effect: When the application is started or restarted.

If set, specifies that there is a segmentation limit for a log file and defines the limit size in either kilobytes (KB) or megabytes (MB). If the current log segment exceeds the defined size, the file is closed and a new one is created. This option requires Workspace SIP Endpoint 8.5.102 or above.

>> Back to Top

sipendpoint.log.verbose

Default Value: Trace

Valid Values: Select a value from the following list: All, Debug, Trace, Interaction, Standard, Alarm, None.

Changes Take Effect: When the application is started or restarted.

Defines the level of logging for the Workspace SIP Endpoint. If set to None, no log file is created for Workspace SIP Endpoint.

sipendpoint.policy.device.audio in device

Default Value:

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters. And also Regular expressions characters (. $^{\circ}$ { [(|) * + ? \).

Changes Take Effect: When the application is started or restarted.

Specifies the regular expression used to recognize the device name for the agent's microphone. This option requires Workspace SIP Endpoint 8.5.1 or above.

>> Back to Top

sipendpoint.policy.device.audio_out_device

Default Value:

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters. And also Regular expressions characters (. $^ { (()) * + ?)}$.

Changes Take Effect: When the application is started or restarted.

Specifies the regular expression used to recognize device name for the agent's speakers. This option requires Workspace SIP Endpoint 8.5.1 or above.

>> Back to Top

sipendpoint.policy.device.capture device

Default Value:

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters. And also Regular expressions characters (. $^{\circ}$ { [(|) * + ? \).

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.policy.session.auto accept video

Introduced: 8.5.101.14

Specifies the regular expression used to recognize the video capture device. This option is applicable only if the value of the sipendpoint.policy.session.auto_accept_video option is set to 1. This option requires Workspace SIP Endpoint 8.5.1 or higher.

>> Back to Top

sipendpoint.policy.device.headset_name

Default Value:

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters. And also Regular expressions characters (. $^ { (()) * + ?) }$.

Changes Take Effect: When the application is started or restarted.

The name of the agent's USB headset device. Use the "|" character to separate the names of different headsets if more than one type is supported. For example: 'Type1'|'Type2'.

>> Back to Top

sipendpoint.policy.device.use_headset

Default Value: 1

Valid Values: 0 (for false), 1 (for true)

Changes Take Effect: When the application is started or restarted.

Specifies that a USB headset is used. The value 1 means that a USB headset is used.

>> Back to Top

sipendpoint.policy.endpoint.defer device release

Default Value: 200

Valid Values: Any positive integer

Changes Take Effect: When the application is started or restarted.

Introduced: WSEP 8.5.115.27

Specifies a time in milliseconds before releasing audio devices after the audio stream has been stopped. Deferring device release avoids potential service interruptions if the audio will be restarted quickly and if audio device operations are too slow on the user workstation or has other problems with restart. The value 0 disables deferred device release.

>> Back to Top

sipendpoint.policy.endpoint.include mac address

Default Value: 0

Valid Values: 0 (false) or 1 (true)

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.113.11

If set to 1, the MAC address is included in the Contact header of the REGISTER message of the host's network interface in a format compatible with RFC 5626.

>> Back to Top

sipendpoint.policy.endpoint.public address

Default Value: Empty string which is fully equivalent to the \$auto value. **Valid Values:** Refer to the description. **Changes Take Effect:** When the application is started or restarted. **Introduced:** 8.5.126.07

- Valid Values: This setting may have one of the following explicit values:
 - An IP address. For example, 192.168.16.123 for IPv4 or FE80::0202:B3FF:FE1E:8329 for IPv6.
 - A bare host name or fully qualified domain name (FQDN). For example, epsipwin2 or epsipwin2.us.example.com.
- **Description:** Specifies the Local IP address or Fully Qualified Domain Name (FQDN) of the machine. This setting can be an explicit setting or a special value that the Workspace SIP Endpoint uses to automatically obtain the public address. This setting can have one of the following special values:
 - \$auto: The SIP Endpoint selects the first valid IP address on the first network adapter that is active (status=up) and has the default gateway configured.
 - \$ipv4 or \$ipv6: This value has the same behavior as the \$auto setting but the SIP Endpoint restricts the address to a particular IP family.
 - \$host: The SIP Endpoint retrieves the standard host name for the local computer using the **gethostname** system function.
 - \$fqdn: The SIP Endpoint retrieves the fully qualified DNS name of the local computer. The SIP Endpoint uses the GetComputerNameEx function with parameter ComputerNameDnsFullyQualified.
 - \$net:subnet: The SIP Endpoint selects the first valid IP address that belongs to the specified

subnet (where subnet is a full CIDR name according to RFC 4632. For example, \$net:192.168.0.0/16). To support dynamic VPN connections, SIP Endpoint does not start registration attempts until the interface (configured by adapter name or subnet) is available.

 An adapter name or part of an adapter name prefixed with \$. For example, \$Local Area Connection 2 or \$Local. The specified name must be different from the special values \$auto, \$ipv4, \$host, and \$fqdn.

>> Back to Top

sipendpoint.policy.endpoint.rtp_inactivity_timeout

Default Value: 30

Valid Values: Any integer from 5 to 150.

Changes Take Effect: When the application is started or restarted.

Specifies the timeout interval for RTP inactivity. A value in the range of 5 to 150 specifies the inactivity timeout interval in seconds. The recommended value is 30 seconds. If DTX is configured on MCP, the option must be set to a higher value to prevent calls from being dropped.

>> Back to Top

sipendpoint.policy.endpoint.rtp port max

Default Value: 9999

Valid Values: An integer of the range 1-65535

Changes Take Effect: When the application is started or restarted. Related Options: sipendpoint.policy.endpoint.rtp_port_min

Specifies the integer value that represents the maximum value for an RTP port range. If the minimum and maximum values are not specified or are set to an invalid value, the default minimum (9000) and maximum (9099) are used. Setting the maximum to a value that is less than the minimum is considered an error and results in a failure to initialize the endpoint.

>> Back to Top

sipendpoint.policy.endpoint.rtp_port_min

Default Value: 9000

Valid Values: An integer of the range 9000-65535

Changes Take Effect: When the application is started or restarted. Related Options: sipendpoint.policy.endpoint.rtp_port_max

Specifies the integer value that represents the minimum value for an RTP port range. If the minimum and maximum values are not specified or are set to an invalid value, the default minimum (9000) and maximum (9999) are used. Setting the minimum to a value that is larger than the maximum value is considered an error and results in a failure to initialize the endpoint.

>> Back to Top

sipendpoint.policy.endpoint.sip_port_max

Default Value: 5080

Valid Values: An integer of the range 1-65535

Changes Take Effect: When the application is started or restarted.

Related Options: sipendpoint.policy.endpoint.sip_port_min

Specifies the integer value that represents the maximum value for a SIP port range. If the minimum and maximum values are not specified or are set to an invalid value, the default minimum (5060) and maximum (5080) are used. Setting the maximum to a value that is less than the minimum is considered an error and results in a failure to initialize the endpoint.

sipendpoint.policy.endpoint.sip port min

Default Value: 5060

Valid Values: An integer of the range 1-65535

Changes Take Effect: When the application is started or restarted.

Related Options: sipendpoint.policy.endpoint.sip_port_max

Specifies the integer value that represents the minimum value for a SIP port range. If the minimum and maximum values are not specified or are set to an invalid value, the default minimum (5060) and maximum (5080) are used. Setting the minimum to a value that is larger than the maximum is considered an error and results in a failure to initialize the endpoint.

>> Back to Top

sipendpoint.policy.endpoint.tcp_port_max

Default Value: 0

Valid Values: An integer in the range 1 to 65535 or 0.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.policy.endpoint.tcp_port_min

Introduced: 8.5.113.11

The maximum value for a TCP client-side port range. If set to 0, or if the configured range is not valid, SIP connections over TCP and TLS use ephemeral ports, assigned by the operating system. If the value is non-zero and greater than the value of the sipendpoint.policy.endpoint.tcp_port_min option, this value specifies the maximum value for a TCP client-side SIP port range that will be used for all outgoing SIP connections over TCP and TLS transport.

>> Back to Top

sipendpoint.policy.endpoint.tcp_port_min

Default Value: 0

Valid Values: An integer in the range 1 to 65535 or 0.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.policy.endpoint.tcp_port_max

Introduced: 8.5.113.11

The minimum value for the TCP client-side port range. If set to θ, or if the configured range is not valid, SIP connections over TCP and TLS use ephemeral ports that are assigned by the operating system. This option is related to the sipendpoint.policy.endpoint.tcp_port_max option.

>> Back to Top

sipendpoint.policy.endpoint.video_max_bitrate

Default Value: 1000

Valid Values: Any positive integer value greater than 0.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.101.14

The maximum video bit-rate in kb/sec.

>> Back to Top

sipendpoint.policy.endpoint.webrtc_audio_layer

Default Value: 0

Valid Values: 0, 1, 2, 500, 501, 502, 1000, 1001, 1002, 2000, 2001, 2002, 3000, 3001, 3002

Changes Take Effect: When the application is started or restarted.

Modified: 8.5.112.08

Specifies which audio layer is used for WebRTC.

- 0 The audio layer is defined by the GCTI_AUDIO_LAYER environment variable Core audio is used if this environment variable is not specified.
- 1 Wave audio layer is used.
- 2 Core audio layer is used.
- 500 The audio layer ensures that Microsoft Windows MultiMedia Class Scheduler Service (MMCSS) is kept alive by the system independent of the actual audio activity on input and output devices. It can be combined with the values 0, 1, or 2 (500, 501, or 502) to specify the type of audio layer.
- 1000: Instructs the audio layer to open the microphone channel when the endpoint starts up, using the audio layer type defined by option 0, and to keep it open until the endpoint is terminated. It can be combined with the values 0, 1, or 2 (1000, 1001, or 1002) to specify the type of audio layer.
- 2000: Opens the speaker channel for the life of the endpoint, using the audio layer type defined by option 0. Eliminates any delay in opening the audio device when an incoming or outgoing call is connected, for example in environments where audio device startup is slow due to a required restart of the Windows MMCSS service. It can be combined with the values 0, 1, or 2 (2000, 2001, or 2002) to specify the type of audio layer.
- 3000: Opens the microphone and speaker channels for the life of the endpoint, using the audio layer type defined by option 0. It can be combined with the values 0, 1, or 2 (3000, 3001, or 3002) to specify the type of audio layer.

>> Back to Top

sipendpoint.policy.session.agc mode

Default Value: 1

Valid Values: 0 (for false), 1 (for true)

Changes Take Effect: When the application is started or restarted.

Specifies whether automatic gain control (AGC) is enabled for the outgoing headset audio stream. If set to 0, AGC is disabled; if set to 1, it is enabled.

Note: It is not possible to apply different AGC settings for different channels in multi-channel scenarios.

>> Back to Top

sipendpoint.policy.session.auto_accept_video

Default Value: 0

Valid Values: 0 (for false), 1 (for true)

Changes Take Effect: When the application is started or restarted.

Specifies whether video calls are accepted automatically (1) or manually (0).

>> Back to Top

sipendpoint.policy.session.auto_answer

Default Value: 0

Valid Values: 0 (for false), 1 (for true)

Changes Take Effect: When the application is started or restarted.

Specifies whether incoming SIP interactions are automatically answered. If set to 1, all incoming calls are answered automatically.

>> Back to Top

sipendpoint.policy.session.dtmf_method

Default Value: rfc2833

Valid Values: One value from this list: rfc2833, Info, InbandRtp. Changes Take Effect: When the application is started or restarted.

Specifies the method by which DTMF are sent.

>> Back to Top

sipendpoint.policy.session.dtx mode

Default Value: 0

Valid Values: 0 (for false), 1 (for true)

Changes Take Effect: When the application is started or restarted.

Specifies whether Discontinuous Transmission (DTX) is enabled. If DTX is enabled, transmission to the remote party is suspended when the application detects that the local user is not speaking. If this option is set to 1, DTX is enabled; and silence is not transmitted.

>> Back to Top

sipendpoint.policy.session.echo control

Default Value: 0 **Valid Values:** 0, 1

Changes Take Effect: Immediately.

Specifies whether headset echo control is disabled (0) or enabled (1) for the session.

>> Back to Top

sipendpoint.policy.session.noise_suppression

Default Value: 0 **Valid Values:** 0, 1

Changes Take Effect: Immediately.

Specifies whether headset noise suppression is disabled (0) or enabled (1) for the session.

>> Back to Top

sipendpoint.policy.session.reject_session_when_headset_na

Default Value: 0

Valid Values: 0 (for false), 1 (for true)

Changes Take Effect: When the application is started or restarted.

Specifies whether calls are rejected if a headset is unavailable. If set to 1, the SDK rejects the incoming session if a USB headset is not available.

>> Back to Top

sipendpoint.policy.session.ringback enabled

Default Value: 0

Valid Values: 0, 1, 2, 3, 4, or 6

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.114.08 Modified: WSEP 8.5.115.21

Related Options: sipendpoint.policy.session.ringback_file

Specifies how the ringback feature is enabled:

- 0: do not play a ringback when the INVITE dialog is not yet established.
- 1: play the incoming media stream, if provided by the media gateway in a reliable provisional response with SDP.
- 2: play ringback from a local file only.
- · 3: always play ringback using media provided by gateway or a local file if not provided.
- 4: same as 1, but the incoming media stream is played even if the provisional response from Media gateway is not reliable.
- 6: the ringback is always played using either a local file or media provided by the gateway (regardless of whether the provisional response is reliable or not).

>> Back to Top

sipendpoint.policy.session.ringback file

Default Value:

Valid Values: Empty or a valid path to a 16-bit 8-, 16-, or 32-Khz .wav sound file. The path may be a file name in the Workspace SIP Endpoint directory or the full path to the sound file.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.policy.session.ringback_enabled

Introduced: 8.5.114.08

Specifies the audio file that is played when the sipendpoint.policy.session.ringback_enabled option is configured to play a local file as the ringback tone.

>> Back to Top

sipendpoint.policy.session.rx_agc_mode

Default Value: 0 Valid Values: 0, 1

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.126.07

Specifies whether Receiving-side Automatic Gain Control (Rx AGC) is enabled.

- 0: Rx AGC is disabled.
- 1: Rx AGC is enabled; the volume of a received RTP stream is automatically adjusted, to address the problem with some calls having too low a volume for agents to hear the contact clearly.

sipendpoint.policy.session.sip_code_when_headset_na

Default Value: 480

Valid Values: Any positive integer value.

Changes Take Effect: When the application is started or restarted.

Error code for an unavailable USB headset. The error code is sent if a call is rejected because of the unavailability of a headset. If a valid SIP error code is supplied and a USB headset is not available, the SDK rejects the incoming session with the specified SIP error code.

>> Back to Top

sipendpoint.policy.session.vad_level

Default Value: 0

Valid Values: An integer from 0 to 3.

Changes Take Effect: When the application is started or restarted.

Specifies the degree of bandwidth reduction voice activity detection (VAD). The value 0 specifies that conventional VAD is used. The value 3 specifies that "aggressive high" is used.

>> Back to Top

sipendpoint.proxies.proxy0.domain

Default Value:

Valid Values: A valid domain name.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.112.08

Related Options: sipendpoint.proxies.proxy1.domain

Specifies a SIP domain (an application layer configuration that defines the management domain of a SIP proxy), including 'hostport' and an optional 'uri-parameters', as defined by RFC 3261 (but not the scheme nor 'userinfo' parts, nor 'transport' URI parameter, which are added automatically). See also the sipendpoint.proxies.proxy1.domain option.

>> Back to Top

sipendpoint.proxies.proxy0.nat.ice_enabled

Default Value: 0

Valid Values: 0 (for false), 1 (for true)

Changes Take Effect: When the application is started or restarted.

Specifies whether Interactive Connectivity Establishment (ICE) is enabled or disabled for connections on line 1.

>> Back to Top

sipendpoint.proxies.proxy0.nat.stun_server

Default Value:

Valid Values: Any valid host name (either with or without a Fully Qualified Domain Name) or IP Address.

Changes Take Effect: When the application is started or restarted.

Specifies the Session Traversal Utilities for NAT (STUN) server address of Line 1. An empty or null value indicates this feature is not used.

sipendpoint.proxies.proxy0.nat.stun server port

Default Value: 3478

Valid Values: Any valid port number on the host.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.proxies.proxy0.nat.stun_server

Specifies the Session Traversal Utilities for NAT (STUN) server port for Line 1. Relies on a value being specified for the sipendpoint.proxies.proxy0.nat.stun_server option.

>> Back to Top

sipendpoint.proxies.proxy0.nat.turn password

Default Value:

Valid Values: A valid password.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.proxies.proxy0.nat.turn_server

Specifies the password for Traversal Using Relay NAT (TURN) authentication for Session Traversal Utilities for NAT (STUN) for Line 1. Relies on a value being specified for the sipendpoint.proxies.proxy0.nat.turn_server option.

>> Back to Top

sipendpoint.proxies.proxy0.nat.turn_relay_type

Default Value: 0

Valid Values: 0 (TURN over UDP) or 1 (TURN over TCP)

Changes Take Effect: When the application is started or restarted. **Dependencies:** sipendpoint.proxies.proxy0.nat.turn_server

Specifies the type of Traversal Using Relay NAT (TURN) authentication for Session Traversal Utilities for NAT (STUN) that is used for Line 1. Specify 0 for TURN over UDP, or 1 for TURN over TCP. Relies on a value being specified for the sipendpoint.proxies.proxy0.nat.turn_server option.

>> Back to Top

sipendpoint.proxies.proxy0.nat.turn_server

Default Value:

Valid Values: A valid host name.

Changes Take Effect: When the application is started or restarted.

Specifies the Traversal Using Relay NAT (TURN) server address for Line 1. An empty or null value indicates this feature is not used.

>> Back to Top

sipendpoint.proxies.proxy0.nat.turn_server_port

Default Value: 3478

Valid Values: Any valid port number on the host.

Changes Take Effect: When the application is started or restarted. **Dependencies:** sipendpoint.proxies.proxy0.nat.turn server

Specifies the Traversal Using Relay NAT (TURN) server port for Line 1. Relies on a value being specified for the sipendpoint.proxies.proxy0.nat.turn_server option.

sipendpoint.proxies.proxy0.nat.turn user name

Valid Values: A valid user name.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.proxies.proxy0.nat.turn_server

The user ID for Traversal Using Relay NAT (TURN) authorization for Line 1. Relies on a value being specified for the sipendpoint.proxies.proxy0.nat.turn_server option.

>> Back to Top

sipendpoint.proxies.proxy0.reg interval

Default Value: 30

Valid Values: An integer greater than or equal to 0.

Changes Take Effect: When the application is started or restarted.

Specifies the period, in seconds, after which the endpoint starts a new registration cycle when a SIP proxy is down for Line 1. The default value of 0 means that a new registration cycle is not allowed. If the setting is greater than 0, a new registration cycle is allowed and will start after the period specified by regInterval.

>> Back to Top

sipendpoint.proxies.proxy0.reg match received rport

Default Value: 0

Valid Values: 0 (for false), 1 (for true)

Changes Take Effect: When the application is started or restarted.

Discontinued: 8.5.119.05

Specifies whether Workspace SIP endpoint should re-REGISTER itself if it receives a mismatched IP address in the 'received' parameter of the response to the first REGISTER. This resolves a condition when the SIP Endpoint SDK obtains the "wrong" local IP

address in environments with multiple network interfaces.

>> Back to Top

sipendpoint.proxies.proxy0.reg timeout

Default Value: 1800

Valid Values: Integers greater than or equal to 0.

Changes Take Effect: When the application is started or restarted.

Specifies the interval of time, in seconds, after which registration should expire. A new REGISTER request is sent before expiration for Line 1. If the value is set to θ or "" (empty/null), then registration is disabled, putting the endpoint in standalone mode.

>> Back to Top

sipendpoint.proxies.proxy1.domain

Default Value:

Valid Values: A valid domain name.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.112.08

Related Options: sipendpoint.proxies.proxy0.domain

Specifies a SIP domain (an application layer configuration that defines the management domain of a SIP proxy), including 'hostport' and an optional 'uri-parameters', as defined by RFC 3261 (but not the scheme nor 'userinfo' parts, nor 'transport' URI parameter, which are added automatically). See also the sipendpoint.proxies.proxy0.domain option.

>> Back to Top

sipendpoint.proxies.proxy1.domain

Default Value:

Valid Values: A valid domain name.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.112.08

Related Options: sipendpoint.proxies.proxy0.domain

Specifies a SIP domain (an application layer configuration that defines the management domain of a SIP proxy), including 'hostport' and an optional 'uri-parameters', as defined by RFC 3261 (but not the scheme nor 'userinfo' parts, nor 'transport' URI parameter, which are added automatically). See also the sipendpoint.proxies.proxy0.domain option.

>> Back to Top

sipendpoint.proxies.proxy1.domain

Default Value:

Valid Values: A valid domain name.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.112.08

Related Options: sipendpoint.proxies.proxy0.domain

Specifies a SIP domain (an application layer configuration that defines the management domain of a SIP proxy), including 'hostport' and an optional 'uri-parameters', as defined by RFC 3261 (but not the scheme nor 'userinfo' parts, nor 'transport' URI parameter, which are added automatically). See also the sipendpoint.proxies.proxy0.domain option.

>> Back to Top

sipendpoint.proxies.proxy1.domain

Default Value:

Valid Values: A valid domain name.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.112.08

Related Options: sipendpoint.proxies.proxy0.domain

Specifies a SIP domain (an application layer configuration that defines the management domain of a SIP proxy), including 'hostport' and an optional 'uri-parameters', as defined by RFC 3261 (but not the scheme nor 'userinfo' parts, nor 'transport' URI parameter, which are added automatically). See also the sipendpoint.proxies.proxy0.domain option.

>> Back to Top

sipendpoint.proxies.proxy1.nat.ice_enabled

Default Value: 0

Valid Values: 0 (for false), 1 (for true)

Changes Take Effect: When the application is started or restarted.

Specifies whether Interactive Connectivity Establishment (ICE) is enabled or disabled for connections on line 2.

>> Back to Top

sipendpoint.proxies.proxy1.nat.stun_server

Default Value:

Valid Values: Any valid host name (either with or without a Fully Qualified Domain Name) or IP Address. **Changes Take Effect:** When the application is started or restarted.

Specifies the Session Traversal Utilities for NAT (STUN) server address of Line 2. An empty or null value indicates this feature is not used.

>> Back to Top

sipendpoint.proxies.proxy1.nat.stun_server_port

Default Value: 3478

Valid Values: Any valid port number on the host.

Changes Take Effect: When the application is started or restarted. Dependencies: sipendpoint.proxies.proxy1.nat.stun server

Specifies the Session Traversal Utilities for NAT (STUN) server port for Line 2. Relies on a value being specified for the sipendpoint.proxies.proxyl.nat.stun_server option.

>> Back to Top

sipendpoint.proxies.proxy1.nat.turn password

Default Value:

Valid Values: A valid password.

Changes Take Effect: When the application is started or restarted. **Dependencies:** sipendpoint.proxies.proxy1.nat.turn_server

Specifies the password for Traversal Using Relay NAT (TURN) authentication for Session Traversal Utilities for NAT (STUN) for Line 2. Relies on a value being specified for the sipendpoint.proxies.proxyl.nat.turn_server option.

>> Back to Top

sipendpoint.proxies.proxy1.nat.turn_relay_type

Default Value: 0

Valid Values: 0 (TURN over UDP) or 1 (TURN over TCP)

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.proxies.proxy0.nat.turn_server

Specifies the type of Traversal Using Relay NAT (TURN) authentication for Session Traversal Utilities for NAT (STUN) that is used for Line 1. Specify 0 for TURN over UDP, or 1 for TURN over TCP. Relies on a value being specified for the sipendpoint.proxies.proxy0.nat.turn_server option.

>> Back to Top

sipendpoint.proxies.proxy1.nat.turn_server

Default Value:

Valid Values: A valid host name.

Changes Take Effect: When the application is started or restarted.

Specifies the Traversal Using Relay NAT (TURN) server address for Line 1. An empty or null value indicates this feature is not used.

sipendpoint.proxies.proxy1.nat.turn server port

Default Value: 3478

Valid Values: A valid port number.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.proxies.proxy1.nat.turn_server

Specifies the Traversal Using Relay NAT (TURN) server port for Line 2. Relies on a value being specified for the

sipendpoint.proxies.proxyl.nat.turn_server option.

>> Back to Top

sipendpoint.proxies.proxy1.nat.turn user name

Default Value:

Valid Values: A valid user name.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.proxies.proxy1.nat.turn_server

The user ID for Traversal Using Relay NAT (TURN) authorization for Line 2. Relies on a value being specified for the sipendpoint.proxies.proxyl.nat.turn_server option.

>> Back to Top

sipendpoint.proxies.proxy1.reg_interval

Default Value: 30

Valid Values: An integer greater than or equal to 0.

Changes Take Effect: When the application is started or restarted.

Specifies the period, in seconds, after which the endpoint starts a new registration cycle when a SIP proxy is down for Line 2. The default value of 0 means that a new registration cycle is not allowed. If the setting is greater than 0, a new registration cycle is allowed and will start after the period specified by regInterval.

>> Back to Top

sipendpoint.proxies.proxy1.reg_match_received_rport

Default Value: 0

Valid Values: 0 (for false), 1 (for true)

Changes Take Effect: When the application is started or restarted.

Discontinued: 8.5.119.05

Specifies whether Workspace SIP endpoint should re-REGISTER itself if it receives a mismatched IP address in the 'received' parameter of the response to the first REGISTER. This resolves a condition when the SIP Endpoint SDK obtains the "wrong" local IP address in environments with multiple network interfaces.

>> Back to Top

sipendpoint.proxies.proxy1.reg_timeout

Default Value: 1800

Valid Values: Integers greater than or equal to 0.

Changes Take Effect: When the application is started or restarted.

Specifies the interval of time, in seconds, after which registration should expire on Line 2. A new REGISTER request is sent before expiration. If the setting is 0 or empty/null, then registration is disabled, putting the endpoint in standalone mode.

sipendpoint.retain-volume-settings-between-sessions

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the headset and microphone volume settings are restored from the settings at the previous session login when Workspace SIP Endpoint starts.

>> Back to Top

sipendpoint.sbc-register-address

Default Value:

Valid Values: Any valid host name (either with or without a Fully Qualified Domain Name) or IP Address.

Changes Take Effect: When the application is started or restarted.

Modified: Workspace SIP Endpoint 8.5.113.02 Related Options: sipendpoint.sbc-register-port

Specifies the host name or DNS SRV Domain or IP Address of the Session Border Controller or SIP Proxy where the SIP REGISTER request will be sent by Workspace SIP Endpoint. If this option is empty, the SIP REGISTER request will be sent to the address specified in the TServer option sip-address of the SIP Server that monitors the DN of this agent. In Business Continuity environments, this corresponds to the preferred site registration. In environments that use a DNS SRV Domain, the value of the sipendpoint.sbc-register-port must be 0.

Note: To set the Domain/Realm of your contact center instead of an IP when Workspace SIP Endpoint tries to register through a session border controller (SBC) device, set the value of the this option to the FQDN of your domain instead of just the IP Address.

>> Back to Top

sipendpoint.sbc-register-address.peer

Default Value:

Valid Values: Any valid port number on the host or 0.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.sbc-register-address.peer

Modified: Workspace SIP Endpoint 8.5.113.02

In a Business Continuity environment, specifies the host name or DNS SRV Domain or IP Address of the Session Border Controller or SIP Proxy where the SIP REGISTER request is sent by Workspace SIP Endpoint for the peer site. If this option is empty, the SIP REGISTER request is sent to the address that is specified in the TServer option sip-address of the SIP Server that monitors the DN of this agent. In Business Continuity environments, this corresponds to the peer site registration. If a DNS SRV Domain is specified in the sipendpoint.sbc-register-address.peer, the value of this option must be 0.

Note: To set the Domain/Realm of your contact center instead of an IP when Workspace SIP Endpoint tries to register through a session border controller (SBC) device, set the value of the this option to the FQDN of your domain instead of just the IP Address.

>> Back to Top

sipendpoint.sbc-register-port

Default Value:

Valid Values: Any valid port number on the host.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.sbc-register-address **Modified:** Workspace SIP Endpoint 8.5.113.02

Specifies the port of the Session Border Controller or SIP Proxy where the SIP REGISTER request will be sent by Workspace SIP Endpoint. If this option is empty, the SIP REGISTER request will be sent to the port that is specified in the TServer option sipport of the SIP Server that monitors the DN of this agent. In Business Continuity environments, this corresponds to the preferred site registration. If a DNS SRV Domain is specified in the sipendpoint.sbc-register-address option, the value of this option must be 0.

>> Back to Top

sipendpoint.sbc-register-port.peer

Default Value:

Valid Values: Any valid port number on the host or 0.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.sbc-register-address.peer

Modified: Workspace SIP Endpoint 8.5.113.02

In a Business Continuity environment, specifies the port of the Session Border Controller or SIP Proxy where the SIP REGISTER request is sent by Workspace SIP Endpoint. If this option is empty, the SIP REGISTER request is sent to the port that is specified in the TServer option sip-port of the SIP Server that monitors the DN of this agent. In Business Continuity environments, this corresponds to the peer site registration. If a DNS SRV Domain is specified in the sipendpoint.sbc-register-address.peer, the value of this option must be 0.

>> Back to Ton

sipendpoint.standalone.certificate-search-value

Default Value:

Valid Values: A valid string that represents the thumbprint or a part of a certificate issuer or subject.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.standalone.protocol, sipendpoint.standalone.security-level

Introduced: 8.5.109.16

Specifies a string value that Workspace uses to select a certificate. This option is used only if the value of the sipendpoint.standalone.protocol option is https and the value of the sipendpoint.standalone.security-level option is set to 2 or 3. The search order with this value is:

- 1. The certificate thumbprint
- 2. A part of the certificate subject
- 3. A part of the certificate issuer

>> Back to Top

sipendpoint.standalone.port

Default Value: 8000

Valid Values: A positive integer value.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.109.16

Specifies the port number of the SIP Endpoint HTTP service that Workspace uses to contact the SIP Endpoint.

>> Back to Top

sipendpoint.standalone.protocol

Default Value:

Valid Values: http, https

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.109.16

Specifies whether Workspace should use a secure HTTPS or unsecure HTTP connection to communicate with a standalone Workspace SIP Endpoint. If no value is set, Workspace looks for a local SIP Endpoint.

sipendpoint.standalone.security-level

Default Value: 0

Valid Values: One value from the list: 0, 1, 2, 3

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.standalone.protocol

Introduced: 8.5.109.16

Specifies the Workspace security level for HTTPS connections. This option is applicable only if the value of the sipendpoint.standalone.protocol is https.

- 0—Encryption without SIP Endpoint certificate validation
- 1—Workspace makes a standard validation of SIP Endpoint certificate (certificate authority, expiration, revocation)
- 2—Workspace makes a standard validation of SIP Endpoint certificate (certificate authority, expiration, revocation) and exposes a certificate for standard mutual TLS
- 3—Workspace makes a personal validation of SIP Endpoint certificate (certificate authority, expiration, revocation, subject) and exposes a personal certificate for personal mutual TLS

>> Back to Top

sipendpoint.standalone.subject-criteria

Default Value:

Valid Values: A coma separated list of certificate subject fields.

Changes Take Effect: At next application start.

Dependencies: sipendpoint.standalone.protocol, sipendpoint.standalone.security-level

Introduced: 8.5.109.16

Specifies a list of certificate subject fields to validate in the SIP Endpoint certificate (for example: "E,CN,OU,OU,OU,OU,DC,DC,DC,DC,DC"). This option is used only if the value of the sipendpoint.standalone.security-level option is set to 3.

>> Back to Top

sipendpoint.standalone.subject-matching-properties

Default Value:

Valid Values: A comma separated list of Active Directory Current User properties.

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.standalone.subject-criteria, sipendpoint.standalone.protocol, sipendpoint.standalone.security-level

Introduced: 8.5.109.16

Specifies a list of properties of Active Directory Current User. Each defined Active Directory Current User property must match in the same order, the corresponding certificate subject fields that are specified by the value of the sipendpoint.standalone.subject-criteria. For example: "mail,cn,distinguishedName.OU,distinguishedName.OU, distinguishedName.OU,distinguishedName.DC,distinguishedName.DC,distinguishedName.DC,distinguishedName.DC,distinguishedName.DC.This option is used only if the value of the sipendpoint.standalone.protocol option is https and the value of the

sipendpoint.standalone.security-level option is set to 3.

>> Back to Top

sipendpoint.standalone.vdi-detection-model

Default Value: auto

Valid Values: One value from the list: auto,xenapp,xendesktop,vmware-horizon,rdp,localhost

Changes Take Effect: When the application is started or restarted.

Dependencies: sipendpoint.standalone.protocol

Introduced: 8.5.109.16

Modified: 8.5.131.07

Specifies the type of Virtual Desktop Infrastructure (VDI) environment Workspace is running, and determines the address detection model used by Workspace to connect to the Standalone SIP Endpoint that is running on the local physical workstation. This option is used only if sipendpoint.standalone.protocol option is not empty. The following VDI environments are supported:

- auto—Workspace automatically detects the VDI type (for Workspace SIP End Point only)
- xenapp—The VDI type is Citrix XenApp (for Workspace SIP End Point only)
- xendesktop—The VDI type is Citrix XenDesktop (for Workspace SIP End Point only)
- vmware-horizon—The VDI type is VMware Horizon (for Workspace SIP End Point only)
- rdp—The VDI type is Microsoft Remote Desktop Protocol (RDP) (for Workspace SIP End Point only)
- localhost—The SIP Endpoint is running on the VDI server along with Workspace (applicable only when the SIP Endpoint is Genesys Softphone, which must be deployed specifically for VDI environments)

>> Back to Top

sipendpoint.standalone.vdi-detection-use-dns

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.140.08

In a Virtual Desktop Infrastructure (VDI) environment, this option specifies whether Workspace relies on a DNS resolution to identify the IP Address used to connect to Workspace SIP Endpoint. When set to false, Workspace uses the IP Address provided by VDI infrastructure.

>> Back to Top

sipendpoint.system.diagnostics.enable_logging

Default Value: 1 Valid Values: 1.0

Changes Take Effect: When the application is started or restarted.

Specifies whether logging is enabled for Workspace SIP Endpoint. A value of 1 enables this feature. This option applies to Workspace SIP Endpoint 8.0.2.

>> Back to Top

sipendpoint.system.diagnostics.log filter

Default Value:

Valid Values: dtmf or blank.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.114.08

Specifies the list of keys of SIP Messages for which the value should be hidden in the log files.

>> Back to Top

sipendpoint.system.diagnostics.log_level

Default Value: 0

Valid Values: 0, 1, 2, 3, or 4

Changes Take Effect: When the application is started or restarted.

Specifies the log level for Workspace SIP Endpoint.

- 0 = "Fatal"
- 1 = "Error"
- 2 = "Warning"
- 3 = "Info"
- 4 = "Debug"

>> Back to Top

sipendpoint.system.diagnostics.log_options_provider

Default Value: gsip=2, webrtc=(warning)

Valid Values: gsip=x (where x is a valid value for gsip) + , + webrtc=(y) (where valid values for y are warning, state, api, debug, info, error, and/or critical). For example: gsip=2, webrtc=(error, critical)

Changes Take Effect: When the application is started or restarted.

Specifies the log level for webrtc. For example: gsip=2, webrtc=(error,critical)

>> Back to Top

sipendpoint.system.security.cert file

Default Value:

Valid Values: A valid certificate thumbprint.

Changes Take Effect: When the application is started or restarted.

Thumbprint value of the Public endpoint certificate file, which is used as a client-side certificate for outgoing TLS connection and server-side certificate for incoming TLS connections. For example: 78 44 34 36 7a c2 22 48 bd 5c 76 6b 00 84 5d 66 83 f5 85 d5

>> Back to Top

sipendpoint.system.security.tls_enabled

Default Value: 0

Valid Values: 0 (for false), 1 (for true)

Changes Take Effect: When the application is started or restarted.

Specifies with TLS transport is registered. If the value is set to 1, the connection with TLS transport is registered.

>> Back to Top

sipendpoint.system.security.use_srtp

Default Value: optional

Valid Values: One value from the following list: optional, allowed, disabled, off, elective, both, enabled, force, mandatory **Changes Take Effect:** When the application is started or restarted.

Modified: 8.5.112.08, 8.5.126.07

Specifies whether to use SRTP (Secure Real-Time Transport Protocol)

- optional or allowed: Do not send secure offers, but accept them.
- disabled or off: Do not send secure offers and reject incoming secure offers.
- elective or both: Send both secure and non-secure offers and accept either.
- enabled: Send secure offers, accept both secure and non-secure offers.
- force or mandatory: Send secure offers, reject incoming non-secure offers.

Adding either ', UNENCRYPTED_SRTCP' (long form) or ', UEC' (short form) to any value (for example, 'enabled, UEC'), adds the UNENCRYPTED_SRTCP parameter to that offer. When this parameter is negotiated, RTCP packets are not encrypted but are still authenticated. **Note:** Workspace SIP Endpoint supports only the Session Description Protocol Security Descriptions (SDES) method to negotiate SRTP keys.

>> Back to Top

sipendpoint.transport-protocol

Default Value: UDP

Valid Values: A value from the following list: UDP,TCP,TLS.
Changes Take Effect: When the application is started or restarted.

Specifies the transport protocol that is used by Workspace SIP Endpoint for SIP Communication. This option can be used with Interaction Workspace SIP Endpoint 8.0.204 and above.

>> Back to Top

sipendpoint.video.always-on-top

Default Value: true **Valid Values:** true false

Changes Take Effect: When the application is started or restarted.

Specifies whether the Video Window, when it is displayed, is displayed on top of all the other windows of end user workstation without the possibility to put it in the background.

>> Back to Top

sipendpoint.video.auto-activate

Default Value: true **Valid Values:** true false

Changes Take Effect: When the application is started or restarted.

Specifies whether or not the video window is populated automatically when an incoming interaction, which has a video component, is connected. If the value false is specified, the video can be activated later by using the 'Start Video' button.

>> Back to Top

sipendpoint.video.camera-frame-rate

Default Value: 30

Valid Values: An integer that specifies the rate, in frame per second, of the video camera capture.

Changes Take Effect: When the application is started or restarted.

Specifies the video capture rate, in frame per second, of the local video camera.

>> Back to Top

sipendpoint.video.camera-frame-size

Default Value: 352x288

Valid Values: A string that specifies the width and height, separated by an 'x', of the camera frame capture (for example:

353x288).

Changes Take Effect: When the application is started or restarted.

Specifies the frame size capture of the local video camera. To determine the list of available resolutions, consult the specifications of your device or check the Workspace SIP Endpoint logs, which prints the list of available frame sizes.

>> Back to Top

sipendpoint.video.camera-render-format

Default Value: 6

Valid Values: A integer between 0 and 13 that specifies the render format of camera capture.

Changes Take Effect: When the application is started or restarted.

Specifies the video format of the local video camera. To determine the list of available formats, consult the specifications of your device or check Workspace SIP Endpoint logs, which prints the list of available video formats. The following values correspond to the supported video formats:

- 0 = i420
- 1 = YV12
- 2 = YUY2
- 3 = UYVY
- 4 = IYUV
- 5 = ARGB
- 6 = RGB24
- 7 = RGB565
- 8 = ARGB4444
- 9 = ARGB1555
- 10 = MJPEG
- 11 = NV12
- 12 = NV21
- 13 = BGRA

>> Back to Top

sipendpoint.video.thumbnail-ratio

Default Value: 0.25

Valid Values: A float value.

Changes Take Effect: When the application is started or restarted.

Specifies the size ratio of the thumbnail to the video in the SIP video window when both local and remote video are displayed.

>> Back to Top

sms.agent.prompt-color

Default Value: #FF2E6599

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB

hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the prompt for the messages that are entered by an agent in the SMS interaction view.

>> Back to Top

sms.agent.text-color

Default Value: #FF3D464D

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB

hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the text of the messages that are entered by an agent in the SMS interaction view.

>> Back to Top

sms.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether a SMS interaction is automatically accepted and joined if necessary when a Interaction Server Invite event is received. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

sms.auto-answer.enable-reject

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Dependencies: sms.auto-answer, sms.auto-answer.timer

Introduced: 8.5.105.12

Specifies whether the **Reject** button is available in the interaction notification when the value of **sms.auto-answer** is set to true and the value of **sms.auto-answer.timer** is greater than 0. The **privilege** to reject interactions must be granted. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

sms.auto-answer.timer

Default Value: 0

Valid Values: Any integer greater than or equal to 0.

Changes Take Effect: At the next interaction.

Dependencies: sms.auto-answer

Introduced: 8.5.105.12

Specifies the time, in seconds, after which an incoming interaction is automatically answered if the value of sms.auto-answer is set to true. If the value of is specified, interactions are immediately auto-answered. If any positive integer value is specified, then an interaction notification is displayed to the agent and a timer counts down the seconds until the interactions is auto-answered. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

sms.client.prompt-color

Default Value: #FFAF4F0B

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB

hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the text received by a contact in the SMS interaction view.

>> Back to Top

sms.client.text-color

Default Value: #FF3D464D

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB

hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the prompt for the messages entered by a contact in the SMS interaction view.

>> Back to Top

sms.default-queue

Default Value:

Valid Values: Name of a valid Script object of type InteractionQueue

Changes Take Effect: At the next interaction.

Specifies the Interaction Queue in which new or reply outbound SMS are submitted when an agent clicks Send and before the interaction is placed in outbound queue.

>> Back to Top

sms.from-numbers-business-attribute

Default Value:

Valid Values: A valid name of a Business Attribute.

Changes Take Effect: At the next interaction.

A character string that specifies the name of the Business Attribute that contains the Attribute Values that are used as 'from numbers' of outbound SMS interactions.

>> Back to Top

sms.max-message-number

Default Value: 8

Valid Values: Any integer greater than or equal to 0. **Changes Take Effect:** At the next interaction.

Specifies the maximum number of SMS allowed per message. 0 means there is no maximum value.

>> Back to Top

sms.other-agent.prompt-color

Default Value: #FF295B00

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the prompt for the messages that are entered by the target agent in the SMS interaction view.

>> Back to Top

sms.other-agent.text-color

Default Value: #FF3D464D

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB

hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: Immediately.

Modified: 8.5.122.08

Specifies the color of the text entered by another agent in the SMS interaction view.

>> Back to Top

sms.outbound-queue

Default Value:

Valid Values: Name of a valid Script object of type InteractionQueue

Changes Take Effect: Immediately.

Specifies the Interaction Queue in which outbound SMS are placed when agents click 'Send' (Page mode only). This options is used only when Interaction Workflow does not set 'Queue for New Interactions' when it is routing Inbound SMS to Agents.

>> Back to Top

sms.prompt-for-done

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies if the application prompts a confirmation message when the user clicks Done. This option is only available for interaction open media. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

sms.ringing-bell

Default Value: Sounds\Ring.mp3|10|-1|primary

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric values.

Changes Take Effect: At the next interaction.

Dependencies: application.secondary-audio-out-device, application.secondary-audio-out-device

Specifies the path of the sound file that is played when SMS interaction is ringing. For example: "Sounds\Ring.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority. The higher the integer the higher the priority.
- 3. The duration:
 - a. -1 means play and repeat until an explicit message stops it. For example, the established event stops the ringing sound.
 - b. 0 means play the whole sound one time.
 - c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value |primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

>> Back to Top

sms.simple-transcript

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediately

Introduced: 8.5.122.08

Specifies whether the SMS transcript is displayed as simple lines of text lines instead of text blocks.

>> Back to Top

sms.subject-max-chars

Default Value: 25

Valid Values: A positive integer.

Changes Take Effect: At the next interaction.

Specifies the maximum number of characters from the SMS message that are used to create the message subject in the contact history if the history does not contain subject. A value of 0 means no subject is created.

>> Back to Top

sms.system.text-color

Default Value: #FF8C8C8C

Valid Values: Valid Hexadecimal color code.

Changes Take Effect: Immediately

Specifies the color of the text for system messages in the SMS interaction view.

>> Back to Top

sms.time-stamp

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Specifies whether the time stamp is displayed in the SMS transcript area.

>> Back to Top

sms.transcript-enable-history-filters

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.132.05

Specifies that the value specified for the contact.history.filters-<attribute> option is used to filter the history-based part of the SMS transcript.

>> Back to Top

sms.transcript-time-frame

Default Value: 24

Valid Values: A positive integer value. Changes Take Effect: At the next interaction.

Specifies the range of time, in hours, in which to search for previous interactions by the same contact to populate the SMS transcript from the contact history. A value of 0 means nothing is added to the contact history.

>> Back to Top

sounds.preloadfiles

Default Value: Sounds\Ring.mp3

Valid Values: A comma-separated list of valid Windows directory paths and file names. '|' character after the file name must be followed by the output device definition.

Changes Take Effect: When the application is started or restarted...

Dependencies: application.secondary-audio-out-device **Related Options:** voice.ringing-bell, chat.new-message-bell

Specifies the name and location in the application folder of audio files that are to be pre-loaded when an agent logs in. For Example: "Sounds\Ring.mp3|primary,Sounds\bell|secondary.mp3,Sounds\chord.mp3|both,Sounds\warning.mp3". The audio files are defined by the options that control sounds, such as voice.ringing-bell and chat. new-message-bell. Files that are not specified by this option are loaded whenever they are needed. The file value has two components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority. The higher the integer the higher the priority.

3. The duration:

- a. -1 means play and repeat until an explicit message stops it. For example, the established event stops the ringing sound.
- b. 0 means play the whole sound one time.
- c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

>> Back to Top

spellchecker.chat.prompt-on-send

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.105.12

Specify by whether you want agents to be prompted when they click Send if there are misspelled words in a chat.

>> Back to Top

spellchecker.corporate-dictionary

Default Value:

Valid Values: Comma-separated list of words

Changes Take Effect: When the application is started or restarted.

Specifies a comma-separated list of dictionary words that conform to the limitations of allowable characters in the configuration layer. Typically you would use this list to specify common words in your company, such as your company name or product name.

>> Back to Top

spellchecker.corporate-dictionary-file

Default Value:

Valid Values: Absolute or relative path to a text file.

Changes Take Effect: When the application is started or restarted.

Specifies the name and the path to your corporate dictionary file. The path can be relative to the Workspace working directory (for example: Dictionaries\CorporateDictionary.txt) or an absolute path (for example: C:\PathToDictionaries\CorporateDictionary.txt). The file must consist of a list of words (one word per line) with ANSI, Unicode, UTF-8 encoding (any encoding accepted by Microsoft .NET).

spellchecker.email.prompt-on-send

Default Value: false **Valid Values:** true, false.

Changes Take Effect: At the next interaction.

Introduced: 8.5.105.12

Specify whether you want agents to be prompted when they click Send if there are misspelled words in an email.

>> Back to Top

spellchecker.im.prompt-on-send

Default Value: false **Valid Values:** true, false.

Changes Take Effect: At the next interaction.

Introduced: 8.5.105.12

Specify whether you want agents to be prompted when they click **Send** if there are misspelled words in an IM message.

>> Back to Top

spellchecker.sms.prompt-on-send

Default Value: false **Valid Values:** true, false.

Changes Take Effect: At the next interaction.

Introduced: 8.5.105.12

Specify whether you want agents to be prompted when they click **Send** if there are misspelled words in an SMS message.

>> Back to Top

spellchecker.<media-type>.prompt-on-send

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.105.12

Specify by media type whether you want agents to be prompted when they click **Send** if there are misspelled words in an email, chat, or SMS message. The following media names are supported: chat, email, sms.

>> Back to Top

standard-response.auto-append-star-to-search

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next search.

Introduced: 8.5.117.18

Specifies whether an asterisk ("*") character is automatically appended to a Standard Response keyword search to force a starts with search. When searching in languages, such as Chinese or Japanese, set this option to false and set up a CJK Analyzer in Universal Contact Server.

standard-response.categories

Default Value: \$All\$

Valid Values: \$All\$ or a comma-separated list of one or more Category paths, using the '/' separator as tree level separator.

Changes Take Effect: At the next interaction.

Specifies the list of categories that are used to filter the Standard Responses. Agents see only those standard responses that are part of the subtree of those categories. Each category must be defined using the full access path that must be specified as the root for the agent or agent group to the category; for example: RootCategory1/CategoryLevel1/CategoryLevel2/CategorySpecifiedAsRoot.

If the option is set to \$All\$ or left empty, then Standard Responses for all the Category objects defined in the Configuration Layer are displayed. If an invalid category name is specified in the option, this category is ignored. If all the specified categories are invalid, the option behaves as if it is empty, resulting in the display of all categories.

This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

standard-response.default-search-type

Default Value: AnyKeyword

Valid Values: One of the following values: AnyKeyword, AllKeywords, or ExactText

Changes Take Effect: At the next interaction.

Specifies the default search type that is used to search for text in the Standard Response Library. If empty, the default search type is "AnyKeywords".

>> Back to Top

standard-response.enable-usage-feedback

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the usage information of the Standard Response Library is populated in the interaction record in Universal Contact Server (UCS) so that it can be read by the Training Server.

>> Back to Top

standard-response.field.<CustomFieldCode>

Default Value:

Valid Values: Any valid text string.

Changes Take Effect: At the next interaction.

Introduced: 8.5.112.08

In the name of the option, CustomFieldCode represents a field code that is called in a Standard Response object created in Knowledge Manager and stored in Universal Contact Server. There is an optional Agent parameter that you can include with the CustomFieldCode parameter to make the field code specific to an agent.

Use this option to specify a custom field code such as an agent nickname, role, department, or other qualification. The value of the option is specific to the agent, agent group, tenant, or application. Refer to Enabling the Standard Responses feature for more information.

The value of this option represents the data that is used to populate the corresponding field codes when a Standard Response is inserted into an interaction. You can format CustomFieldCode to represent a custom agent attribute using the following pattern:

Agent.<CustomAgentAttr>, or any custom attribute by dropping the agent modifier: <CustomFieldCode>.

Examples:

- standard-response.field.Agent.Nickname = Lee
- standard-response.field.Department = Sales

>> Back to Top

standard-response.languages

Default Value: \$All\$

Valid Values: \$All\$ or a comma-separated list of one or more language-name Business Attributes

Changes Take Effect: At the next interaction.

Specifies the list of languages that are used to filter the Standard Responses. Agents see only those standard responses that are part of the subtree of the root categories of the specified languages. The language corresponds to a Business Attribute named Language in Knowledge Manager or eServices Manager. If the value \$All\$ is specified, then Standard Responses for all the Language objects that are defined in Knowledge Manager or eServices Manager are displayed. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

standard-response.shortcuts.<keyword>

Default Value: No default value

Valid Values: The path to a standard response as defined in Knowledge Manager or eServices Manager.

Changes Take Effect: At the next interaction.

Introduced: 8.5.118.10

Related Options: editor.shortcuts.prefix

Specifies the path to a standard response as defined in the configuration layer. The name of the option defines a keyword that agents can enter into an editor view, along with a prefix that is defined by the editor.shortcuts.prefix option and Ctrl+Space, to automatically add the standard response to the interaction.

>> Back to Top

standard-response.suggested-responses-min-relevancy

Default Value: 50

Valid Values: An integer between 0 and 100. Changes Take Effect: At the next interaction.

Specifies the minimum level of relevancy above which Suggested Responses will be shown from the Standard Response Library.

>> Back to Top

statistics.displayed-statistics

Default Value:

Valid Values: A comma-separated list of Statistic names.

Changes Take Effect: Immediately.

Specifies the statistics that are displayed in the Contact Center Statistics tab. The statistics specified by this option match the names of the statistics defined in the options of the Application sections.

statistics.queues

Default Value:

Valid Values: A comma-separated list of queue identifiers in the following format: (<queueNumber>@<switchName>)

Changes Take Effect: Immediately.

Specifies the list of queues for which queue statistics are calculated. List of queues can be set through a variable: \$AGENT.LOGINQUEUE\$ (the queue on which the agent logged in), \$AGENTGROUP.ORIGINATIONDNS\$ (the queues set as the origination DNs in the agent groups to which this agent belongs).

>> Back to Top

statistics.refresh-time

Default Value: 10

Valid Values: An integer value greater than 0.

Changes Take Effect: When the application is started or restarted.

Defines the frequency of notification (in seconds) for statistics.

>> Back to Top

statistics.routing-points

Default Value:

Valid Values: A comma-separated list of Routing Point identifiers in the following format:

(<routingPointNumber>@<switchName>)
Changes Take Effect: Immediately.

Specifies the list of routing points for which routing point statistics are calculated.

>> Back to Top

system-tray.tooltip

Default Value: \$Application.Title\$

Valid Values:

\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.Employeeld\$

Changes Take Effect: When the application is started or restarted.

Defines the tooltip of the Workspace system tray icon by specifying a string that contains the following field codes: \$Application.Title\$, \$Application.Name\$, \$Agent.UserName\$, \$Agent.LastName\$, \$Agent.FirstName\$, \$Agent.Employeeld\$. If all field codes are empty, the following field codes are used:\$Application.Title\$.

>> Back to Top

teamcommunicator.add-recent-filters.voice

Default Value:

Valid Values: A comma-separated list of interaction types taken from the following values: internal, external, consultation. **Changes Take Effect:** At next interaction event.

Specifies whether to store incoming interactions into the "Recent" buffer. By default, the Recent buffer stores only the actions of the agent, such as recent outbound voice calls. If one or more of the valid values is specified, then recent inbound interactions of that type are also stored in the Recent buffer. This enables agents to see a record of missed calls of the specified type(s).

>> Back to Top

teamcommunicator.always-clear-textbox-on-new-interaction

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

When this option is set to true, Workspace clears the teamcommunicator search textbox when the interaction is initiated by pressing "Enter" or by clicking on one of the medias of teamcommunicator results. When it is set to false, this option clears the teamcommunicator search textbox only when the interaction is initiated by pressing "Enter"

>> Back to Top

teamcommunicator.contact-favorite-fields

Default Value: Category,FirstName,LastName,PhoneNumber,EmailAddress

Valid Values: A comma-separated list of values from the followeing list: CategoryContact, FirstName, LastName, PhoneNumber,

EmailAddress.

Changes Take Effect: When the application is started or restarted.

The list of fields that are displayed to an agent when adding or editing a favorite that is created from a Contact.

>> Back to Top

teamcommunicator.corporate-favorites

Default Value:

Valid Values: A comma-separated list of favorite names (section names) defined in the Workspace application.

Changes Take Effect: When the application is started or restarted.

Modified: 8.5.141.04 (behavior description clarified)

Related Options: teamcommunicator.corporate-favorites-file

The list of corporate favorites (quick dial favorites) that are configured in Configuration Server for an Agent, Agent Group, Skill, Routing Point, Queue, Interaction Queue, or Custom Contact in the same tenant as the agent. See the Procedure: Creating Corporate Favorites for information about creating Corporate Favorite objects in the configuration layer. For operations such as transfer and conference from the Interaction Window Team Communicator, this option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy, but not for the Main Window Team Communicator.

>> Back to Top

teamcommunicator.corporate-favorites-file

Default Value:

Valid Values: Absolute or relative path to an XML file.

Changes Take Effect: When the application is started or restarted.

Modified: 8.5.141.04

Related Options: teamcommunicator.corporate-favorites

Specifies the name and the path to your corporate favorites definition file. The path can be relative to the Workspace working directory (for example: Favorites\CorporateFavorites.txt) or an absolute path (for example: C:\PathToFavorites\CorporateFavorites.txt). The file must be in XML format. For information about how to use this option with the teamcommunicator.corporate-favorites option and transaction overrides see Creating Corporate Favorites.

teamcommunicator.custom-favorite-fields

Default Value: Category, FirstName, LastName, PhoneNumber, EmailAddress

Valid Values: A comma-separated list of values from the following list: Category, FirstName, LastName, PhoneNumber,

EmailAddress.

Changes Take Effect: When the application is started or restarted.

The list of fields that are displayed to an agent when adding or editing a favorite that is created from a typed phone number or email address.

>> Back to Top

teamcommunicator.interaction-queue-presence-metrics

Default Value: interaction-queue-presence

Valid Values: A string that contains a comma separated list of interaction queue presence options section names.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.102.06

Specifies a list of interaction queue presence sections. Each of these sections contain a valid statistic name related to the interaction queue, the text to be displayed in Team Communicator, a warning level value, an error level value, and a list of object ids that apply to this presence statistic.

>> Back to Top

teamcommunicator.internal-favorite-fields

Default Value: Category, DisplayName

Valid Values: A comma-separated value list of values from the following list: Category, DisplayName.

Changes Take Effect: When the application is started or restarted.

The list of fields that are displayed to an agent when adding or editing a favorite that is created from a named resource.

>> Back to Top

teamcommunicator.list-filter-showing

Default Value: Agent, AgentGroup, Skill, Routing Point, Queue, Interaction Queue, Contact, Custom Contact

Valid Values: A comma-separated list of values from the following list: Agent, AgentGroup, Skill, RoutingPoint, Queue,

Contact, InteractionQueue, CustomContact

Changes Take Effect: When the application is started or restarted.

Specifies the list of filters that an agent can use to search for contacts and internal targets by using the team communicator. The object types are presented in the specified order.

>> Back to Top

teamcommunicator.list-status-reachable

Default Value: NotReady

Valid Values: A comma-separated list of agent status from the following list: NotReady, LoggedOff, Busy

Changes Take Effect: When the application is started or restarted.

Specifies the list of statuses, excepting Ready, for which a target agent can be contacted for consultation, transfer, and conference, requests. If the status of the target agent is neither Ready nor in the list of allowed statuses, the target agent will not be listed as available for consultation, transfer, and conference requests.

Note: The value LoggedOff typically applies to off-line media types such as Email.

>> Back to Top

teamcommunicator.load-at-startup

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Provides performance protection if you have a large number of agents that all login at the same time. Specifies whether all the configuration elements (Agents, Agent Groups, Queues, Routing Points, Skills) that are required by the Team Communicator are loaded at login. If this option is set to false, the elements are not loaded at login; instead, they are loaded when the Team Communicator is used for the first time in the session.

>> Back to Top

teamcommunicator.max-favorites-size

Default Value: 50

Valid Values: Any positive integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the maximum number of entries in the list of favorites that is displayed while an agent is entering a contact or target name in the favorites view.

Note: High values (100+) will impact the performance of the workstation and application.

>> Back to Top

teamcommunicator.max-suggestion-size

Default Value: 10

Valid Values: An integer value from 1 through 50.

Changes Take Effect: When the application is started or restarted.

Specifies the maximum number of internal entries (agent, agent groups and so on) and maximum number of external entries (customer contacts) to be displayed in the Team Communicator suggestion list while an agent is entering a contact or target name.

For example, if 10 is specified, up to 10 internal targets and up to 10 contacts may be displayed.

>> Back to Top

teamcommunicator.queue-presence-metrics

Default Value: queue-presence

Valid Values: A string that contains a comma separated list of queue presence options section names.

Changes Take Effect: When the application is started or restarted.

Specifies a list of queue presence sections. Each of these sections contain a valid statistic name related to the queue, the text displayed in Team Communicator, a warning level value, an error level value, and a list of object ids that apply to this presence statistic.

teamcommunicator.recent-max-records

Default Value: 10

Valid Values: An integer value from 1 through 50.

Changes Take Effect: When the application is started or restarted.

Specifies the maximum number of internal entries (for example, agent and groups) and the maximum number of external entries (customer contacts) to be displayed in the Team Communicator suggestion list while an agent is entering a contact or target name. For example, if 10 is specified, up to 10 internal targets and up to 10 contacts may be displayed.

>> Back to Top

teamcommunicator.request-start-timer

Default Value: 300

Valid Values: An integer value from 1 through 5000.

Changes Take Effect: When the application is started or restarted.

Request start timer wait interval, in milliseconds, between the last key pressed and the beginning of the search through the contact database.

>> Back to Top

teamcommunicator.routing-point-presence-metrics

Default Value: routing-point-presence

Valid Values: A string that contains a comma separated list of routing point presence options section names.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.102.06

Specifies a list of routing point presence sections. Each of these sections contain a valid statistic name related to the routing point, the text to be displayed in Team Communicator, a warning level value, an error level value, and a list of object ids that apply to this presence statistic.

>> Back to Top

teamlead.agent-status.enabled-agent-group-security-mode

Default Value: true **Valid Values:** true, false

Changes Take Effect: At next agent search.

Specifies that a Team Lead may change the status of an agent only if the agent is a member of an Agent Group that the Team Lead supervises. When set to false, any Team Lead can change the agent's status. Relies on the 'Team Lead - Can Change Agent Status' privilege being granted.

>> Back to Top

teamlead.agent-status.enabled-remote-actions

Default Value: Ready, NotReady, LogOff

Valid Values: A comma-separated list of states: Ready, NotReady, LogOff

Changes Take Effect: At the next agent search.

Introduced: 8.5.126.07

Specifies the list of agent statuses to which a Team Lead can set an agent selected from Team Communicator. The order of the statuses defines the order they are displayed in Team Communicator. This option is applicable only when the 'Team Lead - Agent Status Enabled Remote Actions' privilege is granted to the Team Lead.

>> Back to Top

teamlead.monitoring-scope

Default Value: call

Valid Values: Select a value from the following list: agent,call

Changes Take Effect: Immediately.

Specifies the scope of monitoring that is to be used for voice interactions in environments that use SIP Server. If the value call is specified, the supervisor remains on the call until it is finished. This mode enables barge-in. If the value agent is specified, the system disconnects the supervisor automatically from the call when the monitored agent leaves the call. In this mode, the barge-in operation is not possible.

>> Back to Top

toast.case-data.content

Default Value: History, CaseData **Valid Values:** History, CaseData

Changes Take Effect: At the next interaction.

Dependencies: toast.case-data.format-business-attribute

Modified: 8.5.143.08

Related Options: interaction.case-data.content, display-format.caller-name

Specifies the content of the Case Information area in the interaction preview.

- The CaseData key enables the display of the attached data that is defined by the toast.casedata.format-business-attribute option; the relative order of case data keys can be specified in the configured Business Attribute object as described in that option.
- The History key enables the display of interaction history information such as 'origin', 'queue', 'call type'. The content displayed in the 'history' block is controlled by the application and the list of keys depends on the context. Administrators do not have control over this content.
- The order of the values in the option defines the order of the Case Data (as a block) and History (as another block) information in the Case Information area of the interaction preview.
- This option can be overridden by a routing strategy, as described in Overriding Options by Using a
 Routing Strategy. Starting from the 8.1.1 release, display of case information in the toast view is no
 longer controlled by case information in the interaction view. Please refer to the interaction.casedata.content option for this purpose.

>> Back to Top

toast.case-data.format-business-attribute

Default Value:

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters.

Changes Take Effect: At the next interaction Related Options: toast.case-data.order

Specifies the name of the Business Attribute that contains the Business Attribute Values that are used to filter and render attached data in the interaction preview. You can define the display order of Business Attribute Values by creating an interaction-workspace section in the annex of the Business Attribute, then add the toast.case-data.order option. This option is a comma-separated list of Business Attributes Values Names that specifies the order of the Business Attribute Values. The Attributes Values that are not listed in the toast.case-data.order option are put at the bottom of the list. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

toast.window-title

Default Value: (\$Contact.FirstName\$ \$Contact.LastName\$|\$Interaction.MainParty\$) - \$Window.Title\$

\$Window.Title\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.Employeeld\$,\$Interaction.Caseld\$,\$Interaction.MainParty\$,\$Co (X: name of contact attribute, Y: attached data key name).

Changes Take Effect: Immediately.

Defines the title of the Interactive Notification window by specifying a string that contains the following field codes: \$Window.Title\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$,\$Interaction.CaseId\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$

Where X is the name of the contact attribute and Y is the name of the attached-data key. If all field codes are empty, the following field codes are used:

\$Window.Title\$ - \$Interaction.MainParty\$. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

views.CaseContactRegion.activate-order

Default Value: InteractionContactInformationView,InteractionContactHistoryView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom views):

InteractionContactInformationView,InteractionContactHistoryView,...

Changes Take Effect: When the views are instantiated.

Specifies the tab order of the Contact Information view and the Contact History view in the Case information. If this option is not configured, then the default ordering is used. If you do not specify all the options, then the default order is used except where an item order is specified. The following document enumerates all the views and regions: Customize Views and Regions

>> Back to Top

views.CaseContactRegion.order

Default Value: InteractionContactInformationView,InteractionContactHistoryView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom views):

InteractionContactInformationView,InteractionContactHistoryView,...

Changes Take Effect: When the views are instantiated.

Specifies the display order of the Contact Information view and the Contact History view in the Case Information view. If this option is not configured, then the default ordering is used. If you do not specify all the options, then the default order is used except where an item order is specified. The following document enumerates all the views and regions: Customize Views and Regions

>> Back to Top

views.CaseViewSideButtonRegion.order

Default Value: InteractionContainerSideButtonView,SRLSideButtonView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom views):

InteractionContainerSideButtonView,SRLSideButtonView,...

Changes Take Effect: When the views are instantiated.

Specifies the display order of the side button region. If this option is not configured, then the default ordering is used. If you do not specify all the options, then the default order is used except where an item order is specified. The following document enumerates all the views and regions: Customize Views and Regions

views.ContactInfoHistoryMultiRegion.activate-order

Default Value: ContactInformationView,ContactHistoryView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom views):

ContactInformationView,ContactHistoryView,...

Changes Take Effect: When the views are instantiated.

Specifies the tab order of the Contact Information view and the Contact History view in the Case Information view. The following document enumerates all the views and regions: Customize Views and Regions

>> Back to Top

views.ContactInfoHistoryMultiRegion.order

Default Value: ContactInformationView,ContactHistoryView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom views):

ContactInformationView,ContactHistoryView,...

Changes Take Effect: When the views are instantiated.

Specifies the display order of the Contact Information view and the Contact History view in the Contact Information view. If this option is not configured, then the default ordering is used. If you do not specify all the options, then the default order is used except where an item order is specified. The following document enumerates all the views and regions: Customize Views and Regions

>> Back to Top

views.ContactTabBottomHistoryMultiRegion.activate-order

Default Value: ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView **Valid Values:** A comma-separated list of valid view names from the following list (plus the custom views): ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView,... **Changes Take Effect:** When the views are instantiated.

Specifies the tab order of the Contact Tab in the Contact History. If this option is not configured, then the default ordering is used. If you do not specify all the options, then the default order is used except where an item order is specified. The following document enumerates all the views and regions: Customize Views and Regions

>> Back to Top

views. Contact Tab Bottom History MultiRegion. order

Default Value: ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom views):

ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView,...

Changes Take Effect: When the views are instantiated.

Specifies the display order of the Contact Tab in the Contact History. If this option is not configured, then the default ordering is used. If you do not specify all the options, then the default order is used except where an item order is specified. The following document enumerates all the views and regions: Customize Views and Regions

>> Back to Top

views.InteractionDetailsRegion.activate-order

Default Value: NotepadVoiceNotepadView, DispositionsView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom views):

NotepadVoiceNotepadView, DispositionsView,...

Changes Take Effect: When the views are instantiated.

Specifies the tab order of the disposition and notepad views in an interaction window. If this option is not configured, then the default ordering is used. If you do not specify all the options, then the default order is used except where an item order is specified. The following document enumerates all the views and regions: Customize Views and Regions

>> Back to Top

views.InteractionDetailsRegion.order

Default Value: DispositionsView,NotepadVoiceNotepadView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom views):

DispositionsView, NotepadVoiceNotepadView,...

Changes Take Effect: When the views are instantiated.

Specifies the display order of the disposition and notepad views in an interaction window. If this option is not configured, then the default ordering is used. If you do not specify all the options, then the default order is used except where an item order is specified. The following document enumerates all the views and regions: Customize Views and Regions

>> Back to Top

views.ToolbarWorkplaceRegion.activate-order

Default Value: MyPlaceStatusView,myCampaignsListView,MyContactHistory,MyStatisticsView,MyCallCenterStatisticsView **Valid Values:** A comma-separated list of valid view names from the following list (plus the custom views): MyPlaceStatusView,myCampaignsListView,MyContactHistory,MyStatisticsView,MyCallCenterStatisticsView,... **Changes Take Effect:** When the views are instantiated.

Specifies the tab order of the buttons on the toolbar. If this option is not configured, then the default ordering is used. If you do not specify all the options, then the default order is used except where an item order is specified. The following document enumerates all the views and regions: Customize Views and Regions

>> Back to Top

views.ToolbarWorkplaceRegion.order

Default Value: MyPlaceStatusView,myCampaignsListView,MyContactHistory,MyStatisticsView,MyCallCenterStatisticsView **Valid Values:** A comma-separated list of valid view names from the following list (plus the custom views): MyPlaceStatusView,myCampaignsListView,MyContactHistory,MyStatisticsView,MyCallCenterStatisticsView,... **Changes Take Effect:** When the views are instantiated.

Specifies the display order of the buttons on the toolbar. If this option is not configured, then the default ordering is used. If you do not specify all the options, then the default order is used except where an item order is specified. The following document enumerates all the views and regions: Customize Views and Regions

>> Back to Top

views.ToolbarWorksheetButtonRegion.order

Default Value:

MyWorkplaceButtonView,MainToolbarWorkbinsContainerButtonView,MainToolbarContainerButtonView,MainToolbarContainerAlertMessageButtonView,MainToolbarContainerAlertMessageButtonView,MainToolbarContainerAlertMessageButtonView,MainToolbarContainerButtonView,MainToolbarContainerAlertMessageButtonView,MainToolbarContainerAlertMessag

Changes Take Effect: When the views are instantiated.

Specifies the display order of items in the Workspace region. If this option is not configured, then the default ordering is used. If you do not specify all the options, then the default order is used except where an item order is specified. The following document enumerates all the views and regions: Customize Views and Regions

>> Back to Top

views.WorkbinsTabBottomHistoryMultiRegion.activate-order

Default Value: ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom views):

Contact Detail View, Contact History Note pad View, Contact History Case Data View,

Changes Take Effect: When the views are instantiated.

Specifies the tab order of the workbins in the Contact History view. If this option is not configured, then the default ordering is used. If you do not specify all the options, then the default order is used except where an item order is specified. The following document enumerates all the views and regions: Customize Views and Regions

>> Back to Top

views.WorkbinsTabBottomHistoryMultiRegion.order

Default Value: ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom views):

ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView,....

Changes Take Effect: When the views are instantiated.

Specifies the display order of the workbins in the Contact History view. If this option is not configured, then the default ordering is used. If you do not specify all the options, then the default order is used except where an item order is specified. The following document enumerates all the views and regions: Customize Views and Regions

>> Back to Top

voice.after-call-work-extension

Default Value: untimed

Valid Values: untimed, repeat, or deny Changes Take Effect: Immediately

Introduced: 8.5.124.08

In SIP Server environments, specifies the action to be performed if an agent repeatedly requests the After Call Work (ACW) status. This does not apply to the IM channel which is always untimed.

- untimed: Sets an untimed ACW period (this is the default behavior for Workspace).
- · repeat: Allows an agent to extend the ACW period.
- deny: Does not allow an agent to extend the current ACW period.

>> Back to Top

voice.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Modified: 8.5.117.18

Specifies whether a voice interaction is automatically answered when a TServer Ringing event is received. This feature is disabled if the voice media that handles the interaction is in Logged Off state. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

voice.auto-answer.enable-reject

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Dependencies: outbound.push-preview.auto-answer, voice.auto-answer.timer

Introduced: 8.5.105.12

Specifies whether the **Reject** button is available in the interaction notification when the value of outbound.push-preview.auto-answer is set to true and the value of voice.auto-answer.timer is greater than 0. The privilege to reject interactions must be granted. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

voice.auto-answer.timer

Default Value: 0

Valid Values: Any integer greater than or equal to 0. Changes Take Effect: At the next interaction.

Dependencies: voice.auto-answer

Introduced: 8.5.105.12

Specifies the time, in seconds, after which an incoming interaction is automatically answered if the value of voice.auto-answer is set to true. If the value θ is specified, interactions are immediately auto-answered. If any positive integer value is specified, then an interaction notification is displayed to the agent and a timer counts down the seconds until the interactions is auto-answered. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

voice.cancel-after-call-work-on-done

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediately.

Introduced: 8.5.103.10

If the value false is specified, agents must manually change their state from After Call Work to some other status. If the value true is specified, the After Call Work state is changed to the former status when an agent clicks **Done**.

>> Back to Top

voice.complete-conference-requires-connected-consultation-call

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.132.05

Specifies whether the 'Complete Conference' function requires a consultation call to the Agent to be established. When this option is set to 'false', the Agent can complete the conference regardless of consultation call state. When this option is set to 'true' it is not possible to complete a conference until the consultation call is established.

>> Back to Top

voice.device-type

Default Value: auto

Valid Values: auto, separate

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.138.04

Specifies the type of device that this DN represents in the configuration. Configure this option in the interaction-workspace section of the Annex of the DN object. You can enable agents to enter different Places associated with different types of SIP DNs when they log in so that they can login from a Workspace SIP Endpoint/Genesys Softphone workstation one day and from their mobile or home phone through SIP Server, or a 3rd party SIP Endpoint on a different day.

- auto: Specifies that Workspace SIP Endpoint or Genesys Softphone is used. The behavior is adjusted based on the privileges granted to the agent. If "SIP Endpoint - Can Use" is granted, Workspace tries to interact with the SIP Endpoint (Workspace SIP Endpoint or Genesys Softphone) as soon as the DN is recognized as a SIP Server DN. This is the compatibility mode that matches the behavior up to Workspace 8.5.137.xx.
- separate: Specifies that the privilege to enable Workspace SIP Endpoint or Genesys Softphone communication should be ignored. The device is supposed to have a life cycle independent from Workspace. Use this value for hard phones and SIP Endpoints from another vendor, and so on.

>> Back to Top

voice.dtmf-inactivity-typing-timeout

Default Value: 500

Valid Values: Any positive integer.

Changes Take Effect: At the next interaction.

Defines the inactivity duration, in milliseconds, after which any buffered digits will be sent. A value of 0 means that each digit will be sent individually.

>> Back to Top

voice.enable-agent-reservation

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.111.21

Specifies whether Workspace should prevent an agent from manually setting the voice channel to Not Ready, Do Not Disturb, After Call Work, or Logged Off status, or from exiting the application if the agent has been marked as **Reserved** by the Router or any other server that can reserve an Agent for call distribution.

>> Back to Top

voice.enable-init-conference

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the 'Initiate Transfer' and 'Initiate Conference' functions are displayed as separate actions to the Agent in the 'Consultation' area. When this option is set to 'false', the single menu item 'Start Voice Consultation' is displayed. This menu item triggers the 'Initiate Transfer' function.

>> Back to Top

voice.end-consultation-method

Default Value: reconnect **Valid Values:** reconnect, release

Changes Take Effect: At the next interaction.

Introduced: 8.5.103.10

Specifies the type of telephony action that is executed when an agent clicks End during a voice consultation call.

- reconnect: A **Reconnect Call** action is applied, which results in the automatic retrieval of the leg which was on hold during the consultation.
- release: A Release Call action is applied, which releases the consultation leg while keeping the
 principal leg on hold. This enables agents to make a subsequent consultation call without retrieving
 the main party first. Note: Genesys SIP Server supports this mode but not all switch environments
 can support it. For other switches, consult the corresponding documentation.

>> Back to Top

voice.hold-indicator-timer

Default Value: 30,60

Valid Values: Two integer values separated by a comma.

Changes Take Effect: At the next interaction. Dependencies: voice.show-hold-duration

Introduced: 8.5.111.21

Specifies two alarm thresholds, in seconds, that warn agents that a voice call is on hold for a long time. Three levels are displayed by the progress indicator: before the warning time, between the warning time and the maximum time, and after the maximum time. If the value 0, 0 means that the progress indicator is not enabled. This option can be enabled only if the value of the voice. show-hold-duration is set to true.

>> Back to Top

voice.hot-standby.backup-retry-delay

Default Value: 40

Valid Values: A positive integer value.

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.135.05

In a hot-standby TServer configuration, this option specifies the time, in seconds, between the two attempts to reconnect to the back-up TServer. Genesys recommends that you keep the value of this option above 30 seconds for optimal performance.

>> Back to Top

voice.hybrid-switch-preference

Default Value: No default value

Valid Values: A comma separated list of valid Switch Object names. **Changes Take Effect:** When the application is started or restarted.

Introduced: 8.5.117.18

In Hybrid environments where agents are configured to work with Places that contain Voice DNs from two different switches. The order of the names specifies the preferred switch when the call policy does not favor either switch.

>> Back to Top

voice.mark-done-on-release

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specify if an interaction should be closed automatically if a TServer Release event is received. This option can be overridden by a

routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

voice.nb-max-independent-calls

Default Value: 0

Valid Values: 0 or any positive integer.

Changes Take Effect: When the application is started or restarted

Specifies that an agent cannot place a new, independent call if the number of active calls is equal to or greater than the specified value. If the value 0 is specified, the agent is not prevented by Workspace from placing new calls; instead, the back-end system controls this behavior. This option does not affect consultation calls that are placed on top of voice calls.

>> Back to Top

voice.one-step-trsf-mode

Default Value: default

Valid Values: At least one item from the list: default, single-step-transfer, mute-transfer

Changes Take Effect: When the application is started or restarted.

Specifies the type of one-step transfer. If you specify default, the one-step transfer operation is single-step-transfer, if it is supported by your switch, or mute-transfer, if one-step transfer is not supported by your switch.

>> Back to Top

voice.prompt-for-end

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether Workspace displays a confirmation message when the agent clicks **End** during a voice call. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

voice.ringing-bell

Default Value: Sounds\Ring.mp3|10|-1|primary

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric values.

Changes Take Effect: At the next interaction.

Related Options: application.secondary-audio-out-device

Specifies the voice channel ringing sound-configuration string. For example: "Sounds\Ring.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority. The higher the integer the higher the priority.
- 3. The duration:
 - a. -1 means plays and repeats until an explicit message stops it. For example, the established event stops the ringing sound.

- b. 0 means play the whole sound one time.
- c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specifies whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

>> Back to Top

voice.show-hold-duration

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.111.21

Specifies if the current hold call duration should be displayed as the primary timer in the Interaction Bar when a voice call is placed on hold. The total call duration remains accessible through the Interaction Bar tooltip.

>> Back to Top

voice.show-post-call-duration

Default Value: false Valid Values: true, false

Changes Take Effect: At the next interaction.

Introduced: 8.5.111.21

Specifies if the current post call duration is displayed instead of the total call duration in the Interaction Bar when a voice call is disconnected. The previous total call duration can be viewed by using the Interaction Bar tooltip.

>> Back to Top

voice.sip-preview-bell

Default Value:

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric values.

Changes Take Effect: At the next interaction.

Introduced: 8.5.109.16

Related Options: application.secondary-audio-out-device

Specifies the Voice (SIP Server only) or IM channel Preview sound-configuration string. For example: "Sounds\ Ring.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority. The higher the integer the higher the priority.
 - 3. The duration:
 - a. -1 means plays and repeats until an explicit message stops it. For example, the established event stops the ringing sound.

- b. 0 means play the whole sound one time.
- c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specifies whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
- primary—Play the sound on the default audio output device
- secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
- both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

>> Back to Top

voicemail.access-number

Default Value:

Valid Values: Any valid DN

Changes Take Effect: When the application is started or restarted.

Specifies the number to call to access your voicemail system.

>> Back to Top

voicemail.notification-types

Default Value: personal, public

Valid Values: A comma separated list of valid voicemail box types: personal and public

Changes Take Effect: At the next change of the counter that tracks the number of voicemail messages.

Specifies the types of voicemail boxes that will be included in the count of unread voicemail messages in the Main Window. The value personal refers to the voicemail box that is identified as the personal voicemail box of the agent. The value public refers to group voicemail boxes to which the agent has access.

>> Back to Top

warm-standby.reconnection-random-delay-range

Default Value: 2

Valid Values: Any positive integer.

Changes Take Effect: When the application is started or restarted

Introduced: 8.5.106.19

Specifies the range of the delay, from 0 to the number of seconds specified by the value, before Workspace attempts to reconnect to the last opened endpoint after disconnection.

>> Back to Top

warm-standby.retry-delay

Default Value: 10

Valid Values: Any positive integer.

Changes Take Effect: When the application is started or restarted

Introduced: 8.5.106.19

Related Options: warm-standby.retry-delay

Specifies the delay, in seconds, that is applied after connections to all endpoints have been checked and failed, and before the next iteration is started. This parameter can be overridden as follows:

- In the Primary/Backup connection case, the Reconnect Timeout parameter of the Primary server is used.
- In the connection without backup case, this parameter could be defined by the warm-standby.retry-delay option in the interaction-workspace section of the application to which Workspace is connected.
- In the Cluster Connection case, this parameter could be defined by the warm-standby.retry-delay
 option in the interaction-workspace section of the cluster application to which Workspace is
 connected.

>> Back to Top

webcallback.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether a Web Callback interaction is automatically accepted when Interaction Server Invite event is received. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

webcallback.auto-answer.enable-reject

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Dependencies: webcallback.auto-answer, webcallback.auto-answer.timer

Introduced: 8.5.105.12

Specifies whether the **Reject** button is available in the interaction notification when the value of webcallback.auto-answer is set to true and the value of webcallback.auto-answer.timer is greater than 0. The privilege to reject interactions must be granted. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

webcallback.auto-answer.timer

Default Value: 0

Valid Values: Any integer greater than or equal to 0. Changes Take Effect: At the next interaction.

Dependencies: webcallback.auto-answer

Introduced: 8.5.105.12

Specifies the time, in seconds, after which an incoming interaction is automatically answered if the value of webcallback.auto-answer is set to true. If the value 0 is specified, interactions are immediately auto-answered. If any positive integer value is specified, then an interaction notification is displayed to the agent and a timer counts down the seconds until the interactions is auto-answered. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

webcallback.auto-dial

Default Value: false

Valid Values: true, false

Changes Take Effect: At the next interaction.

Specifies whether Callback Phone Number is automatically dialed when an Interaction Web Callback is accepted. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

webcallback.callback-information.content

Default Value: Subject, Phone Number, Type, Scheduled Date, Contact Time, Local Time, Former Attempts

Valid Values: A comma separated list of items within the following list: Subject, PhoneNumber, Type, ScheduledDate,

ContactTime, LocalTime, FormerAttempts, Result. Changes Take Effect: At the next interaction.

Specifies the callback data that is displayed in the Callback Information Area. The callback data entries are displayed in the order in which they appear in the list.

>> Back to Top

webcallback.callback-information.frame-color

Default Value: #FF17849D

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB

hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: At the next interaction.

Specifies the background color of the Callback Information view header of Web Callback interactions. Examples: #FFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

webcallback.callback-information.header-foreground-color

Default Value: #FFFFFFFF

Valid Values: The hexadecimal Alpha (from '00' for fully transparent color to 'FF' for regular plain color) followed by the RGB

hexadecimal color code (3 values in the '00'-'FF' range).

Changes Take Effect: At the next interaction.

Specifies the color of the foreground of the Callback Information view frame of Web Callback interactions. Example #FFFFFFF for white color. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

webcallback.complete-queue

Default Value:

Valid Values: Name of a valid Script object of type InteractionQueue

Changes Take Effect: Immediately.

Specifies the Interaction Queue in which Web Callback interactions are placed when an agent marks one as processed.

webcallback.park-queue

Default Value:

Valid Values: Name of a valid Script object of type InteractionQueue

Changes Take Effect: Immediately.

Specifies the Interaction Queue in which the parent Web Callback interaction is placed when an agent transfers a voice call that is created from a Web Callback interaction.

>> Back to Top

webcallback.reschedule-queue

Default Value:

Valid Values: Name of a valid Script object of type InteractionQueue

Changes Take Effect: Immediately.

Specifies the Interaction Queue in which Web Callback interactions are placed when an agent reschedules one and marks it as processed.

>> Back to Top

webcallback.ringing-bell

Default Value: Sounds\Ring.mp3|10|-1|primary

Valid Values: All special characters that are valid Windows file path, '|' separator and numeric values.

Changes Take Effect: At the next interaction.

Related Options: application.secondary-audio-out-device

Specifies the path of the sound file that is played when Web Callback interaction is delivered to the agent. For example: "Sounds\ Ring.mp3|10|-1|primary" The value has four components that are separated by the character '|':

- 1. The file name and folder relative to the application folder. In some virtual desktop environments, MP3 and other sound file formats cannot be rendered by Direct Show filters. In this scenario, use Direct Show compatible formats such as .wav.
- 2. The priority. The higher the integer the higher the priority.
- 3. The duration:
 - a. -1 means plays and repeats until an explicit message stops it. For example, the established event stops the ringing sound.
 - b. 0 means play the whole sound one time.
 - c. An integer > 0 means a time, in milliseconds, to play and repeat the sound.
- 4. Specify whether tones are played on the default audio device, a secondary audio device, or both. If no value is specified for this flag, the value | primary is used by default.
 - primary—Play the sound on the default audio output device
 - secondary—Play the sound on the secondary audio device, as defined by the application.secondary-audio-out-device configuration option
 - both—Play the sound on the default and secondary (application.secondary-audio-out-device configuration option) audio devices

webproxy.address

Default Value:

Valid Values: An empty address to specify the default proxy configuration of Microsoft Internet Explorer, a valid proxy address (for example: http://my-proxy-server:3128), "None", or an invalid address to use no proxy at all.

Changes Take Effect: At the next interaction.

Specifies the web proxy host address that is used to download content from external web sites. This applies for example to the images that are contained in the e-mail body or to the pushed chat pages.

>> Back to Top

webproxy.password

Default Value:

Valid Values: The password of the proxy credentials. Leave empty to not use any credentials.

Changes Take Effect: At the next interaction.

Specifies the password to be used to access the web proxy that is used to download content from external web sites. This applies for example to the images that are contained in the e-mail body or to the pushed chat pages.

>> Back to Top

webproxy.username

Default Value:

Valid Values: The username of the proxy credentials. Leave empty to not use any credentials.

Changes Take Effect: At the next interaction.

Specifies the username to be used to access the web proxy that is used to download content from external web sites. This applies for example to the images that are contained in the email body or to the pushed chat pages.

>> Back to Top

workbin.email.draft

Default Value:

Valid Values: The name of a valid Script object of type Interaction Workbin that is owned by Agents.

Changes Take Effect: When the application is started or restarted.

The name of the Workbin to be used to store draft email.

>> Back to Top

workbin.email.draft.displayed-columns

Default Value: To, Subject, Submitted

Valid Values: A comma-separated list of Interaction Server interaction properties, for example: From, Subject, Received

Changes Take Effect: When the application is started or restarted.

The list of interaction fields that are displayed as columns of the workbin that stores Draft email interactions.

workbin.email.in-progress

Default Value:

Valid Values: The name of a valid Script object of type Interaction Workbin that is owned by Agents.

Changes Take Effect: When the application is started or restarted.

The name of the workbin that is to be used to store inbound email for later processing, after an agent explicitly saved the email or submitted an outbound reply.

>> Back to Top

workbin.email.in-progress.displayed-columns

Default Value: From, Subject, Received

Valid Values: A comma-separated list of Interaction Server interaction properties, for example: From, Subject, Received

Changes Take Effect: When the application is started or restarted.

The list of interaction fields that are displayed as columns of the workbin that stores In-Progress email interactions.

>> Back to Top

workbin.<media type>.in-progress

Default Value:

Valid Values: The name of a valid Script object of type Interaction Workbin, that is owned by Agents.

Changes Take Effect: When the application is started or restarted.

The name of the workbin to be used to store In-Progress workitems of the specified media type. **Default Value:**

Valid Values: The name of a valid Script object of type Interaction Workbin, that is owned by Agents.

Changes Take Effect: When the application is started or restarted.

The name of the workbin to be used to store In-Progress workitems of the specified media type.

>> Back to Top

workbin.<media_type>.in-progress.displayed-columns

Default Value: From, To, Subject, Received

Valid Values: A comma-separated list of Interaction Server interaction properties, for example: From, Subject, Received **Changes Take Effect:** When the application is started or restarted.

The list of interaction fields that are displayed as columns of the workbin that stores In Progress workitems of specified media type. **Default Value:** From, To, Subject, Received

Valid Values: A comma-separated list of Interaction Server interaction properties, for example: From, Subject, Received Changes Take Effect: When the application is started or restarted.

The list of interaction fields that are displayed as columns of the specified workbin.

>> Back to Top

workbin.<media-type>.<nick-name>.notify-property-changed

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.122.08

Related Options: notify-workbin-userdata-changed

Specifies whether Workspace should register for key-value pair updates of interactions stored in this workbin. It is recommended not to enable this kind of update registration on a workbin that contains a large number of interactions and is accessed by a large number of agents.

>> Back to Top

workbin.<media-type>.<workbin-nickname>

Default Value:

Valid Values: The name of a valid Script object of type Interaction Workbin. **Changes Take Effect:** When the application is started or restarted.

The name of the workbin that is to be used to store interactions of a particular workitem media type. Agents can open interactions from this workbin but not save interactions in it.

Note: Genesys recommends that you do not assign the same script name to two distinct media-type/workbin-nickname pairs. Using uniquely named scripts ensures a consistent application of advanced options defined for this media-type/workbin-nickname pair.

>> Back to Top

workbin.<media-type>.<workbin-nickname>.auto-update

Default Value: true **Valid Values:** true or false

Changes Take Effect: When the application is started or restarted.

Introduced: 8.5.110.13

Specifies whether the content of the designated workbin is automatically updated on any content change. If the value of this option is set to true, search results are updated in near real-time. If the value of this option is set to false, agents must click a button to refresh search results.

>> Back to Top

workbin.<media-type>.<workbin-nickname>.displayed-columns

Default Value: From, To, Subject, Received

Valid Values: A comma-separated list of Interaction Server interaction properties, for example: From, Subject, Received **Changes Take Effect:** When the application is started or restarted.

The list of interaction fields that are displayed as columns of the specified workbin.

>> Back to Top

workbin.<media-type>.<workbin-nickname>.max-results

Default Value: 50

Valid Values: Any integer greater than 0. **Changes Take Effect:** At next workbin refresh.

Dependencies: workbin.<media-type>.<workbin-nickname>.auto-update

Introduced: Added: 8.5.110.13

Specifies the maximum number of interactions returned by Interaction Server or Interaction Server Proxy when making a search query or a requesting the workbin content when the value of <a href="workbin.<media-type>.<workbin-nickname>.auto-update">workbin.nickname>.auto-update is set to false. This option requires Interaction Server 8.5.104.00 or higher.

workbin.<media-type>.<workbin-nickname>.quick-search-attributes

Default Value:

Valid Values: A comma-separated list of Interaction Server interaction properties, for example: AssignedTo,FromAddress **Changes Take Effect:** When the application is started or restarted.

Introduced: 8.5.110.13

Specifies the list of interaction properties that are used to build the Quick Search query against Interaction Server when the agent makes a quick search in this workbin.

>> Back to Top

workbin.<media-type>.in-progress

Default Value:

Valid Values: The name of a valid Script object of type Interaction Workbin, that is owned by Agents. **Changes Take Effect:** When the application is started or restarted.

The name of the workbin to be used to store In-Progress workitems of the specified media type.

>> Back to Top

workbin.<media-type>.in-progress.displayed-columns

Default Value: From, To, Subject, Received

Valid Values: A comma-separated list of Interaction Server interaction properties, for example: From, Subject, Received **Changes Take Effect:** When the application is started or restarted.

The list of interaction fields that are displayed as columns of the workbin that stores In Progress workitems of specified media type.

>> Back to Top

Team Communicator Presence Options

The following option groups enable agents to view queue, interaction queue, and routing point statistics information in Team Communicator. Refer to the Enabling Team Communicator Calling Features and Enabling the E-Mail Channel for information about how to use these options.

- interaction-queue-presence
- queue-presence
- routing-point-presence

interaction-queue-presence Section

The interaction queue presence options enable agents to view interaction queue statistics information in Team Communicator. Refer to the Enabling Team Communicator Calling Features and Enabling the E-Mail Channel for information about how to use these options.

- associated-object-ids
- associated-statistic-type
- error-level

- · object-ids
- statistic-name
- statistic-text

· warning-level

For information about how to use these options to configure Genesys Web Services functionality and behavior, refer to the *Workspace Desktop Edition Deployment Guide*.

associated-object-ids

Default Value: No default value

Valid Values: A comma separated list of object identifiers that represent the objects that store the

statistic requested from Stat Server

Changes Take Effect: When the application is started or restarted

A comma separated list of object identifiers that represent the objects that store the statistic requested from Stat Server that is displayed as the "presence metric" of the object displayed in Team Communicator.

The type of those objects must match the type specified by the value of the associated-statistic-type option.

If multiple values are specified by the value of the object-ids option, this option must contain the same number to associate the first object of object-ids with the first object of associated-object-ids, the second object of the object-ids with the second object of associated-object-ids and so on.

This option is applicable only if associated-statistic-type is also set

associated-statistic-type

Default Value: No default value

Valid Values: A valid statistic type from Stat Server.

Changes Take Effect: When the application is started or restarted

Specifies the statistic type (from Stat Server reference) that is requested to display the presence metric when this metric is not calculated directly on the object displayed in Team Communicator, but on the objects referenced in option associated-object-ids.

This option is applicable only if associated-object-ids is also set.

error-level

Default Value: 10

Valid Values: An integer or a double value.

Changes Take Effect: When the application is started or restarted.

The value at which a statistic is considered to be at the upper threshold level.

object-ids

Default Value: No default value

Valid Values: A comma separated list of Script identifiers that represent Interaction Queue objects

Changes Take Effect: When the application is started or restarted

A comma separated list of Script identifiers that represent Interaction Queue objects presented in Team Communicator for which this presence metric is applicable.

Object identifier format is: <Script_Name> This key is optional. If it is absent from the section, the presence metric applies to all Interaction Queue objects that don't have explicit presence metric assignment.

statistic-name

Default Value:

Valid Values: A valid name of a Stat Server's statistic.

Changes Take Effect: When the application is started or restarted.

The name of the statistic that is used to evaluate interaction queue presence.

statistic-text

Default Value: interaction(s) waiting.

Valid Values: A string containing a valid time or number format according to Windows rules number format (https://msdn.microsoft.com/en-us/library/8kb3ddd4(v=vs.110).aspx). For example: "interaction(s) 04001 {0:HH:mm:ss} average waiting time" or "interaction(s) 04001 {0}%

abandoned".

Changes Take Effect: When the application is started or restarted.

Modified: 8.5.109.25

Specifies the formatting to be used to display the Stat Server metric used for the presence of the displayed object. If no valid format is found in the option, the display format of the Stat Server metric is set automatically to TimeFormat if a time metric is recognized, or Percentage if a percentage is recognized. If a number metric is recognized or if the type of metric is not recognized, then a raw number format is used.

warning-level

Default Value: 5

Valid Values: An integer or a double value.

Changes Take Effect: When the application is started or restarted.

The value at which a statistic is considered to be at the warning level.

queue-presence Section

The queue presence options enable agents to view queue statistics information in Team Communicator. Refer to the Enabling Team Communicator Calling Features and Enabling the E-Mail Channel for information about how to use these options.

- associated-object-ids
- associated-statistic-type
- error-level

- · object-ids
- statistic-name
- statistic-text

· warning-level

For information about how to use these options to configure Genesys Web Services functionality and behavior, refer to the *Workspace Desktop Edition Deployment Guide*.

associated-object-ids

Default Value: No default value

Valid Values: A comma separated list of object identifiers that represent the objects that store the

statistic requested from Stat Server

Changes Take Effect: When the application is started or restarted

A comma separated list of object identifiers that represent the objects that store the statistic requested from Stat Server that is displayed as the "presence metric" of the object displayed in Team Communicator.

The type of those objects must match the type specified by the value of the associated-statistic-type option.

If multiple values are specified by the value of the object-ids option, this option must contain the same number to associate the first object of object-ids with the first object of associated-object-ids, the second object of the object-ids with the second object of associated-object-ids and so on.

This option is applicable only if associated-statistic-type is also set.

associated-statistic-type

Default Value: No default value

Valid Values: Specifies the statistic type (from Stat Server reference) that is requested to display

the presence metric

Changes Take Effect: When the application is started or restarted

Specifies the statistic type (from Stat Server reference) that is requested to display the presence metric when this metric is not calculated directly on the object displayed in Team Communicator, but on the objects referenced in option associated-object-ids.

This option is applicable only if associated-object-ids is also set.

error-level

Default Value: 10

Valid Values: An integer or a double value.

Changes Take Effect: When the application is started or restarted.

The value at which a statistic is considered to be at the upper threshold level.

object-ids

Default Value: No default value

Valid Values: A comma separated list of DN identifiers that represent Queue objects

Changes Take Effect: When the application is started or restarted

A comma separated list of DN identifiers that represent Queue objects presented in Team Communicator for which this presence metric is applicable.

Object identifier format is: <DN Number>@<Switch Name> This key is optional. If it is absent from the section, the presence metric applies to all Queue objects that don't have explicit presence metric assignment.

statistic-name

Default Value: CurrNumberWaitingCalls

Valid Values: A valid name of a statistic server statistic queue. **Changes Take Effect:** When the application is started or restarted.

The name of the statistic used to evaluate presence for gueues.

statistic-text

Default Value: interaction(s) waiting.

Valid Values: A string containing a valid time or number format according to Windows rules number format (https://msdn.microsoft.com/en-us/library/8kb3ddd4(v=vs.110).aspx). For example: "interaction(s) 04001 {0:HH:mm:ss} average waiting time" or "interaction(s) 04001 {0}%

abandoned".

Changes Take Effect: When the application is started or restarted.

Modified: 8.5.109.25

Specifies the formatting to be used to display the Stat Server metric used for the presence of the displayed object. If no valid format is found in the option, the display format of the Stat Server metric is set automatically to TimeFormat if a time metric is recognized, or Percentage if a percentage is recognized. If a number metric is recognized or if the type of metric is not recognized, then a raw number format is used.

warning-level

Default Value: 5

Valid Values: An integer or a double value.

Changes Take Effect: When the application is started or restarted.

The value at which a statistic is considered to be at the warning level.

routing-point-presence Section

The routing point presence options enable agents to view routing point statistics information in Team Communicator. Refer to the Enabling Team Communicator Calling Features and Enabling the E-Mail Channel for information about how to use these options.

- associated-object-ids
- associated-statistic-type
- error-level

- · object-ids
- statistic-name
- statistic-text

· warning-level

For information about how to use these options to configure Genesys Web Services functionality and behavior, refer to the *Workspace Desktop Edition Deployment Guide*.

associated-object-ids

Default Value: No default value

Valid Values: A comma separated list of object identifiers

Changes Take Effect: When the application is started or restarted

A comma separated list of object identifiers that represent the objects that store the statistic requested from Stat Server that is displayed as the "presence metric" of the object displayed in Team Communicator.

The type of those objects must match the type specified by the value of the associated-statistic-type option.

If multiple values are specified by the value of the object-ids option, this option must contain the same number to associate the first object of object-ids with the first object of associated-statistic-type, the second object of the object-ids with the second object of associated-statistic-type and so on.

This option is applicable only if associated-statistic-type is also set.

associated-statistic-type

Default Value: No default value

Valid Values: A valid stat server statistic type

Changes Take Effect: When the application is started or restarted

Specifies the statistic type (from Stat Server reference) that is requested to display the presence metric when this metric is not calculated directly on the object displayed in Team Communicator, but on the objects referenced in option associated-object-ids.

This option is applicable only if associated-object-ids is also set.

error-level

Default Value: 10

Valid Values: An integer or a double value.

Changes Take Effect: When the application is started or restarted.

The value at which a statistic is considered to be at the upper threshold level.

object-ids

Default Value: No default value

Valid Values: A comma separated list of DN identifiers that represent Routing Point objects

Changes Take Effect: When the application is started or restarted

A comma separated list of DN identifiers that represent Routing Point objects presented in Team Communicator for which this presence metric is applicable.

Object identifier format is: <DN Number>@<Switch Name> This key is optional. If it is absent from the section, the presence metric applies to all Routing Point objects that don't have explicit presence metric assignment.

statistic-name

Default Value: CurrNumberWaitingCalls

Valid Values: A valid name of a statistic server statistic queue. **Changes Take Effect:** When the application is started or restarted.

The name of the statistic used to evaluate the presence for Routing Points.

statistic-text

Default Value: interaction(s) waiting.

Valid Values: A string containing a valid time or number format according to Windows rules number format (https://msdn.microsoft.com/en-us/library/8kb3ddd4(v=vs.110).aspx). For example: "interaction(s) 04001 {0:HH:mm:ss} average waiting time" or "interaction(s) 04001 {0}%

abandoned".

Changes Take Effect: When the application is started or restarted.

Modified: 8.5.109.25

Specifies the formatting to be used to display the Stat Server metric used for the presence of the displayed object. If no valid format is found in the option, the display format of the Stat Server metric is set automatically to TimeFormat if a time metric is recognized, or Percentage if a percentage is recognized. If a number metric is recognized or if the type of metric is not recognized, then a raw number format is used.

warning-level

Default Value: 5

Valid Values: An integer or a double value.

Changes Take Effect: When the application is started or restarted.

The value at which a statistic is considered to be at the warning level.

TServer Section

These options should be configured on DN objects.

Configuring the Instant Messaging Solution

There are a number of ways to implement the Instant Messaging solutions in Genesys. This includes enabling DNs in your contact center to handle instant messages after they arrive at SIP Server. Deploying the Instant Messaging solution requires configuring various Genesys components. For detailed information, see the Genesys 7.6 Instant Messaging Solution Guide, which consolidates possible Instant Messaging solutions and configuration information for each of them.

Multi-site or Business Continuity Deployments

On the Instant Messaging DN, in the TServer section, set the sipsignaling-chat option to none, so no SIP session with an agent endpoint is created for the IM call.

For the IM solution to work, make sure the following configuration options are enabled (set to true) in the TServer section of the DN for Workspace Desktop Edition:

- multimedia
- voice

About Workspace

For more information about using Workspace configuration options, refer to Introduction to Configuration Options.

The *Workspace Deployment Guide* contains topics specific to configuring options as a group to manage each functional area.

multimedia

- sip-signaling-chat
- voice

For information about how to use these options to configure Genesys Web Services functionality and behavior, refer to the *Workspace Desktop Edition Deployment Guide*.

Tip

The following descriptions were generated by dynamic query and include cached results that may be up to one day old. Click here to refresh the query.

multimedia

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether this SIP Server-related DN is capable of handling IM interactions (in addition to whatever other capabilities are set for it).

- When set to false, URS will not deliver IMs to this DN.
- Set this option to true for a DN that is related to SIP Server when you want it to be able to handle IMs.

>> Back to Top

sip-signaling-chat

Default Value: session **Valid Values:** session, none

Changes Take Effect: Immediately.

Specifies the chat mode for the Instant Messaging (IM) DN on which this option is configured.

- If you set this option to session, when the first SIP dialog containing an IM SDP is created, the MESSAGE requests are exchanged only in this dialog. You must use this value for Microsoft Office Communicator endpoints.
- If you set this option to none, SIP Server does not send a SIP MESSAGE to a SIP Endpoint during IM. Chat communication (IM) will be provided to the agent desktop by only the T-Library protocol.

>> Back to Top

voice

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether this SIP Server-related DN is capable of handling voice interactions (in addition to whatever other capabilities are set for it). Set this option to false for DNs that are intended for IM-only interaction handling.

>> Back to Top

Interaction Workspace

The majority of Workspace configuration options are configured in the interaction-workspace section. This is a section that you create in the annex of the object to which you want to apply the option. Most of these options can be configured hierarchically at the Application, Tenant, Agent Group, or User level; some can be configured on other objects such as DNs, skills, and switches. For more information about using Workspace configuration options, refer to Introduction to Configuration Options.

The KPI section, Statistics section, and Not Ready Reason Codes objects are not included in this option reference.

The values specified for many options can also be overridden by Routing Strategies that reference Transaction objects.

Workspace options are grouped by functionality. The first word in the name of the option indicates the functional area to which the option belongs. For example, the option chat.emojis-business-attribute is part of the **chat** functionality group. It enables you to specify the name of the **business** attribute that contains the **emojis** that agents enabled for the Chat channel can use in the Chat window. The options are named to help you know quickly what the option does.

The *Workspace Deployment Guide* contains topics specific to configuring options as a group to manage each functional area. For example, you can read about setting up the Chat channel in the Chat topic.

Options for this component are contained in the following configuration sections:

- interaction-queue-presence
- interaction-workspace

- queue-presence
- routing-point-presence

Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

Power users: Download a CSV file containing default and valid values and descriptions.

The following options are configured on the Application, Tenant, Agent Group, User, or other object.

Section	Option	Default	Changes Take Effect
interaction-queue- presence	error-level	10	When the application is started or restarted.
interaction-queue- presence	statistic-name		When the application is started or restarted.
interaction-queue- presence	statistic-text	interaction(s) waiting.	When the application is started or restarted.
interaction-queue- presence	warning-level	5	When the application is started or restarted.
interaction-workspace		0	When the application is started or restarted.
interaction-workspace	<media-type>.auto- answer</media-type>	false	At the next interaction.
interaction-workspace	<media-type>.prompt- for-done</media-type>	false	At the next interaction.
interaction-workspace	<media-type>.pull- from-history-isenabled</media-type>	false	Immediately.
interaction-workspace	<media-type>.ringing- bell</media-type>	Sounds\Ring.mp3	At the next interaction.
interaction-workspace	<media-type>.toast- information-key</media-type>	Subject	At the next interaction.
interaction-workspace	accessibility.agent- state-change-bell		At the next interaction.
interaction-workspace	accessibility.interaction- state-change-bell		At the next interaction.
interaction-workspace	accessibility.visual- impairment-profile	false	When the application is started or restarted.
interaction-workspace	accessibility.warning- message-bell		At the next interaction.
interaction-workspace	active-recording.screen-recorder-executable		At next application start.
interaction-workspace	active-recording.screen- recorder-host		At next application start.
interaction-workspace	active- recording.voice.recorder- uri		At application restart.
interaction-workspace	active- recording.voice.recording- type	NETANN	At application restart.
interaction-workspace	agent-status.enabled- actions-by-channel	Ready,NotReady,NotRead	y Recease di Aftery Call Work, Dnd
interaction-workspace	agent-status.enabled- actions-global	Ready,NotReady,NotRead	y Recease di Aftery Call Work, Dnd
interaction-workspace	agent-status.not-ready- reasons		Immediately.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect	
interaction-workspace	alert.timeout	10	When the application is started or restarted.	
interaction-workspace	application.available- layouts	main-window,gadget	When the application is started or restarted.	
interaction-workspace	broadcast.color.high- priority	1. FF663399	Immediately.	
interaction-workspace	broadcast.color.important priority	FFFF0000	Immediately.	
interaction-workspace	broadcast.color.low- priority	FF999999	Immediately.	
interaction-workspace	broadcast.color.minimal- priority	FFCCCCCC	Immediately.	
interaction-workspace	broadcast.color.normal- priority	FFDFE8F6	Immediately.	
interaction-workspace	broadcast.displayed- columns	MessageTypeIcon,Message	When the application is a type sender support the started or restarted.	ty,Date,Topic
interaction-workspace	broadcast.dn		When the application is started or restarted.	
interaction-workspace	broadcast.mark-read- timeout	5	When the application is started or restarted.	
interaction-workspace	broadcast.message- content	Subject, Sender, Priority, Date, Topic, Body	At the next message.	
interaction-workspace	broadcast.preview- timeout	10	At the next message.	
interaction-workspace	broadcast.sound.high- priority		At the next interaction.	
interaction-workspace	broadcast.sound.importan priority	t-	At the next interaction.	
interaction-workspace	broadcast.sound.low- priority		At the next interaction.	
interaction-workspace	broadcast.sound.minimal- priority		At the next interaction.	
interaction-workspace	broadcast.sound.normal- priority		At the next interaction.	
interaction-workspace	broadcast.subscribed.topi	c⊈All,\$Agent\$,\$AgentGroup\$	When the application is started or restarted.	
interaction-workspace	broadcast.toast- summary	Sender, Priority,Subject,FewWords	At the next message.	
interaction-workspace	broadcast.value- business-attribute		When the application is started or restarted.	
interaction-workspace	case-data.float- separator		Immediately.	
Section	Option	Default	Changes Take Effect	

Section	Option	Default	Changes Take Effect
interaction-workspace	channel- information.window-title	\$Window.Title\$	Immediately.
interaction-workspace	chat.agent.prompt-color•	FF385078	Immediately.
interaction-workspace	chat.agent.text-color •	FF385078	Immediately.
interaction-workspace	chat.auto-answer	false	At the next interaction.
interaction-workspace	chat.client.prompt-color •	FF166FFF	Immediately.
interaction-workspace	chat.client.text-color •	FF166FFF	Immediately.
interaction-workspace	chat.enable-auto- disconnect	true	At the next interaction.
interaction-workspace	chat.new-message-bell		Immediately
interaction-workspace	chat.nickname	\$Agent.UserName\$	At the next interaction.
interaction-workspace	chat.other- agent.prompt-color	FFD88000	Immediately.
interaction-workspace	chat.other-agent.text- color	FFD88000	Immediately.
interaction-workspace	chat.pending-response- to-customer	30,50	At the next interaction.
interaction-workspace	chat.prompt-for-end	false	At the next interaction.
interaction-workspace	chat.reconnect-attempts	5	At the next interaction.
interaction-workspace	chat.reconnect-timeout	5	At the next interaction.
interaction-workspace	chat.ringing-bell	Sounds\Ring.mp3	At the next interaction.
interaction-workspace	chat.system.text-color •	FF8C8C8C	Immediately.
interaction-workspace	chat.time-stamp	true	Immediately.
interaction-workspace	chat.toast-information- key	Subject	At the next interaction.
interaction-workspace	chat.typing-isenabled	true	At the next interaction.
interaction-workspace	chat.typing-timeout	10	At the next interaction.
interaction-workspace	contact.available- directory-page-sizes	5,10,25,50	When the application is started or restarted.
interaction-workspace	contact.cache-timeout- delay	600	When the application is started or restarted.
interaction-workspace	contact.date-search- types	On,OnOrAfter,Before	When the application is started or restarted.
interaction-workspace	contact.default- directory-page-size	10	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	contact.directory- advanced-default	LastName,PhoneNumber	When the application is started or restarted.
interaction-workspace	contact.directory- default-mode	ListView	Immediately.
interaction-workspace	contact.directory- displayed-columns	LastName,FirstName,Phon	When the application is ellumber Email Address started or restarted.
interaction-workspace	contact.directory- permissions. <contactattri< td=""><td>ibuteName></td><td>At the next contact search.</td></contactattri<>	ibuteName>	At the next contact search.
interaction-workspace	contact.directory- search-attributes	LastName,FirstName,Phon	When the application is eNumber Email Address started or restarted.
interaction-workspace	contact.directory- search-types	contains,begins-with,is	When the application is started or restarted.
interaction-workspace	contact.displayed- attributes	Title,FirstName,LastName,	When the application is Phone Number Email Addres started or restarted.
interaction-workspace	contact.history- advanced-default	Status,StartDate	When the application is started or restarted.
interaction-workspace	contact.history-default- time-filter-main	1M	When the application is started or restarted, or at the next interaction.
interaction-workspace	contact.history- displayed-columns	Status, Subject, Start Date, E	When the application is indicated or restarted.
interaction-workspace	contact.history- displayed-columns- treeview	Subject,Status,StartDate	When the application is started or restarted.
interaction-workspace	contact.history.filters- <attribute></attribute>		At the next contact search.
interaction-workspace	contact.history.media- filters	voice,email,chat,sms	When the application is started or restarted.
interaction-workspace	contact.history-search- attributes	Status, Start Date, End Date,	When the application is Subject or restarted.
interaction-workspace	contact.last-called- agent.enable	true	Immediately.
interaction-workspace	contact.last-called- agent. <media- type>.enable</media- 	true	Immediately.
interaction-workspace	contact.lookup.enable	true	Immediately.
interaction-workspace	contact.lookup.enable- create-contact	true	Immediately.
interaction-workspace	contact.lookup. <media- type>.enable</media- 	true	Immediately.
interaction-workspace	contact.lookup. <media- type>.enable-create- contact</media- 	true	Immediately.
interaction-workspace	contact.mandatory-	FirstName,LastName	When the application is
	contactimanatory	,	TTTTCTTTTTTTTTTTTTTTTTTTTTTTTTTTTTTTTT

Section	Option	Default	Changes Take Effect
	attributes		started or restarted.
interaction-workspace	contact.metrics.enable-interactions-in-progress	true	When the application is started or restarted.
interaction-workspace	contact.metrics.time- frame-customer- notification	1	When the application is started or restarted.
interaction-workspace	contact.multiple-value- attributes	EmailAddress,PhoneNumb	When the application is started or restarted.
interaction-workspace	contact.myhistory- default-time-filter-main	1W	When the application is started or restarted.
interaction-workspace	contact.myhistory- displayed-columns	Status, Subject, Start Date, I	When the application is started or restarted.
interaction-workspace	contact.myhistory- displayed-columns- treeview	Subject,Status,StartDate	When the application is started or restarted.
interaction-workspace	contact.threading-ucs- interaction.enable	true	Immediately.
interaction-workspace	contact.timeout-delay	60	When the application is started or restarted.
interaction-workspace	contact.ucs- interaction. <media- type>.enable-create</media- 	true	Immediately.
interaction-workspace	contact.ucs- interaction. <media- type>.enable-lookup</media- 	true	Immediately.
interaction-workspace	contact.ucs- interaction. <media- type>.use-server-date</media- 	false	When the application is started or restarted.
interaction-workspace	dial-plan-rule- <name></name>		When the application is started or restarted.
interaction-workspace	disaster-recovery.auto- restore	true	When the application is started or restarted
interaction-workspace	disaster- recovery.disable-login- errors	false	When the application is started or restarted.
interaction-workspace	disaster- recovery.enabled	false	When the application is started or restarted
interaction-workspace	disaster-recovery.peer- site	DRPeer	When the application is started or restarted
interaction-workspace	disaster- recovery.preferred-site	Preferred	When the application is started or restarted
interaction-workspace	disaster- recovery.restore-agent- state	true	When the application is started or restarted.
interaction-workspace	disaster-	60	When the application is
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
	recovery.timeout		started or restarted
interaction-workspace	disaster-recovery.wait- for-sipphone-timeout	0	When the application is started or restarted
interaction-workspace	display-format.acd- queue.name	\$ACDQueue.Alias\$	Immediately.
interaction-workspace	display-format.agent- name	\$Agent.FullName\$	Immediately.
interaction-workspace	display-format.caller- name	\$Contact.FirstName\$ \$Contact.LastName\$	Immediately.
interaction-workspace	display-format.case- name-format	\$Contact.FirstName\$ \$Contact.LastName\$	Immediately
interaction-workspace	display-format.chat- agent-name	\$ChatAgent.FullName\$	Immediately.
interaction-workspace	display-format.current- agent-name	\$Agent.FullName\$	Immediately.
interaction-workspace	display- format.customer-name- format	\$Contact.FirstName\$ \$Contact.LastName\$	Immediately
interaction-workspace	display- format.interaction- callback-name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$	Immediately.
interaction-workspace	display- format.interaction-chat- name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$	Immediately.
interaction-workspace	display- format.interaction- email-name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$	Immediately.
interaction-workspace	display- format.interaction-im- name	\$Interaction.Type\$ \$Interaction.MainParty\$	Immediately.
interaction-workspace	display- format.interaction- outbound-pull-preview- name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$	Immediately.
interaction-workspace	display- format.interaction- outbound-push-preview- name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$	Immediately.
interaction-workspace	display- format.interaction- queue.name	\$InteractionQueue.Display	When the application is started or restarted.
interaction-workspace	display- format.interaction-sms- name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$	Immediately.
interaction-workspace	display- format.interaction-	\$Interaction.Type\$ (\$Contact.FirstName\$	Immediately.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
	voice-name	\$Contact.LastName\$	
interaction-workspace	display- format.interaction- workitem-name	\$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$	Immediately.
interaction-workspace	display-format.routing- point.name	\$RoutingPoint.Alias\$	Immediately.
interaction-workspace	editor.font-size-units	point	At the next interaction.
interaction-workspace	email.attachment- download-timeout	20	Immediately.
interaction-workspace	email.auto-answer	false	At the next interaction.
interaction-workspace	email.default-queue		At the next interaction.
interaction-workspace	email.forward-queue		Immediately.
interaction-workspace	email.from-addresses	\$EMAILSERVER\$	At the next interaction.
interaction-workspace	email.html-format	true	At the next interaction.
interaction-workspace	email.include-original- text-in-reply	true	At the next interaction.
interaction-workspace	email.max-attachments- size	0	At the next interaction.
interaction-workspace	email.move-inbound-to- in-progress-workbin-on- reply	false	At the next interaction.
interaction-workspace	email.outbound-queue		Immediately.
interaction-workspace	email.prompt-for-done	false	At the next interaction.
interaction-workspace	email.pull-from-history- isenabled	true	Immediately.
interaction-workspace	email.qa-review- dispositions-business- attribute		At the next interaction.
interaction-workspace	email.quote-char	>	Immediately.
interaction-workspace	email.reply-format	auto	At the next interaction.
interaction-workspace	email.reply-prefix	Re: <space></space>	Immediately.
interaction-workspace	email.restricted- attachment-file-types	No default value	At the next interaction.
interaction-workspace	email.ringing-bell	Sounds\Ring.mp3	At the next interaction.
interaction-workspace	email.set-ownerid-on- send	true	At the next interaction.
interaction-workspace	email.signature		At the next interaction.
interaction-workspace	email.toast-information- key	Subject	At the next interaction.
interaction-workspace	expression.email- address	\w+([-+.]\w+)*@\w+([- .]\w+)*\.\w+([]\w+)*	At the next interaction.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	expression.phone- number	(?:(?:[\+]?([\d]{1,3}(?:[]*	At the next interaction.
interaction-workspace	expression.phone- number.supported- characters	0123456789#*	At the next interaction.
interaction-workspace	expression.url	$\w]+\.)+(?#TopLevel$	s?)\:\/\/ ~/ /)?(?#Username At the next interaction. gov mil biz info mobi name
interaction-workspace	gadget- statistics.displayed-call- center-statistics		When the application is started or restarted.
interaction-workspace	gadget- statistics.displayed-kpis		When the application is started or restarted.
interaction-workspace	gadget-statistics.nb- tagged-stats-per-page	5	When the application is started or restarted.
interaction-workspace	gadget-statistics.show	true	When the application is started or restarted.
interaction-workspace	gadget.window-title	\$Window.Title\$	Immediately.
interaction-workspace	general.configuration- update-notification	All	When the application is started or restarted.
interaction-workspace	general.gad.attached- data	false	At the next interaction.
interaction-workspace	general.non-unicode- connection-encoding		When the application is started or restarted
interaction-workspace	im.agent.prompt-color •	FF385078	Immediately.
interaction-workspace	im.agent.text-color •	FF385078	Immediately.
interaction-workspace	im.auto-answer	false	When the application is started or restarted.
interaction-workspace	im.new-message-bell		Immediately
interaction-workspace	im.other-agent.prompt- color	FFD88000	Immediately.
interaction-workspace	im.other-agent.text- color	FFD88000	Immediately.
interaction-workspace	im.prompt-for-end	false	At the next interaction.
interaction-workspace	im.ringing-bell	Sounds\Ring.mp3	At the next interaction.
interaction-workspace	im.system.text-color •	FF8C8C8C	Immediately.
interaction-workspace	im.time-stamp	true	Immediately.
interaction-workspace	im.toast-timeout	10	At the next interaction.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	interaction-bar.detail- tooltip.max-height	164	Immediately.
interaction-workspace	interaction.case- data.content	History,CaseData	At the next interaction.
interaction-workspace	interaction.case- data.enable-url-preview	false	At the next interaction.
interaction-workspace	interaction.case- data.format-business- attribute		At the next interaction
interaction-workspace	interaction.case- data.frame-color	FFFFBA00	At the next interaction.
interaction-workspace	interaction.case- data.header-foreground-• color	FF15428B	At the next interaction.
interaction-workspace	interaction.case-data.is- read-only-on-idle	true	At the next interaction.
interaction-workspace	interaction.consult-user- data	public	Immediately.
interaction-workspace	interaction.disposition.is- mandatory	false	Immediatly.
interaction-workspace	interaction.disposition.is- read-only-on-idle	false	Immediatly.
interaction-workspace	interaction.disposition.key name	DispositionCode	Immediatly
interaction-workspace	interaction.disposition.use attached-data		At the next interaction.
interaction-workspace	interaction.disposition.use connection-id		Immediatly.
interaction-workspace	interaction.disposition.valubusiness-attribute	DispositionCode	Immediatly
interaction-workspace	interaction.evaluate- real-party-for-agent	true	When the application is started or restarted.
interaction-workspace	interaction- management.available- interaction-page-sizes	5,10,25,50	When the application is started or restarted.
interaction-workspace	interaction- management.filters		When the application is started or restarted.
interaction-workspace	interaction- management.interactions- filter.displayed-columns	MessageType,From,To,Sub	When the application is ject heceived started or restarted.
interaction-workspace	interaction.override- option-key	IW_OverrideOptions	At the next interaction.
interaction-workspace	interaction.reject-route		At the next interaction.
interaction-workspace	interaction.window.popup-	false	At the next interaction if
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect	
	topmost-z-order		the value is changed to 'true' or when the application is started or restarted if the value is changed to 'false'.	
interaction-workspace	interaction.window.show- case-interaction-panel- button	true	At the next interaction.	
interaction-workspace	interaction.window.show-in-taskbar	true	At the next interaction.	
interaction-workspace	interaction.window-title	(\$Contact.FirstName\$ \$Contact.LastName\$	When the application is started or restarted.	
interaction-workspace	interactions.window.allows transparency-on-winos6	^{S-} false	At the next interaction.	
interaction-workspace	intercommunication.chat.d	conference.invite-	At the next interaction.	
interaction-workspace	intercommunication.chat.c	queue	At the next interaction.	
interaction-workspace	intercommunication.chat.rbased-actions	routing-	At the next interaction.	
interaction-workspace	intercommunication.chat.rbased-targets	routing-	At the next interaction.	
interaction-workspace	intercommunication.email	.queue	At the next interaction.	
interaction-workspace	intercommunication.email based-actions	.routing-	At the next interaction.	
interaction-workspace	intercommunication.email based-targets		At the next interaction.	
interaction-workspace	intercommunication.im.ro based-actions	u <mark>ting-</mark> MakeIM	When the application is started or restarted.	
interaction-workspace	intercommunication.im.ro based-targets	uting-	At the next interaction.	
interaction-workspace	intercommunication.im.ro points	uting-	At the next interaction.	
interaction-workspace	intercommunication.sms.c		At the next interaction.	
interaction-workspace	intercommunication.sms.r based-actions	outing- OneStepTransfer	At the next interaction.	
interaction-workspace	intercommunication.sms.r based-targets	outing-	At the next interaction.	
interaction-workspace	intercommunication.voice based-actions	.routing- Makecall,OneStepConfere	nAe,thetCoexfeiretececCioeStep	oTransf
interaction-workspace	intercommunication.voice based-targets	routing-	At the next interaction.	
interaction-workspace	intercommunication.voice points	routing-	At the next interaction.	
interaction-workspace	intercommunication. <med< td=""><td>dia-</td><td>At the next interaction.</td><td></td></med<>	dia-	At the next interaction.	
Section	Option	Default	Changes Take Effect	

Section	Option	Default	Changes Take Effect
	type>.queue		
interaction-workspace	intercommunication. <med type>.routing-based- actions</med 	dia-	At the next interaction.
interaction-workspace	intercommunication. <med type>.routing-based- targets</med 	dia-	At the next interaction.
interaction-workspace	keyboard.hotkey.agent- not-ready		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.agent- not-ready-with- reason. <action-code></action-code>		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.agent- ready		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.decrease microphone-volume- active-sip-call	-	When the application is started or restarted.
interaction-workspace	keyboard.hotkey.decrease speaker-volume-active- sip-call	-	When the application is started or restarted.
interaction-workspace	keyboard.hotkey.hold- active-call		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.increase- microphone-volume- active-sip-call		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.increase- speaker-volume-active- sip-call		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.mute- microphone-active-sip- call		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.mute- speaker-active-sip-call		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.release- active-call		When the application is started or restarted.
interaction-workspace	keyboard.hotkey.toaster.a	ccept	When the application is started or restarted.
interaction-workspace	keyboard.hotkey.toaster.d	ecline	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.action.l	nefl þ	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.contact	. ÆsslenAcontact	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.contact		When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	keyboard.shortcut.contact	t. Satvle +S	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.chat.conference	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.chat.end	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.chat.transfer	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.consult	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac attachments	tion.email.add-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.email.delete	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.email.forward	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac send	tion.email.interim-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.email.print	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	ti © ttr enR ail.reply	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion email reply- Ctrl+Shift+Ay-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac		When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac in-workbin	tion email save- Ctrl+Shift+W	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	ti@tr en Ræituænd	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.email.transfer	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac		When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac done	tion mark- CtriffEr	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac record	tion.preview.call-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac record	tion.preview.cancel-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac done	tion.preview.mark-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac done-get-next	tion.preview.mark-	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	keyboard.shortcut.interac record	tion.preview.reject-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.sms.delete	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.sms.transfer	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.voice.answer-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.voice.hold-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac recording-call	tion.voice.pause-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.voice.reconnect-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion voice release-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.voice.resume-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac recording-call	tion.voice.resume-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac step-conference	tion.voice.single-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac step-transfer	tion.voice.single-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac recording-call	tion.voice.start-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac recording-call	tion.voice.stop-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac contact	tion.webcallback.call-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac done	tion.webcallback.mark-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac to-workbin	tion.workitem.move-	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.interac	tion.workitem.transfer	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.state.lc		When the application is started or restarted.
interaction-workspace	keyboard.shortcut.state.n ready		When the application is started or restarted.
interaction-workspace	keyboard.shortcut.state.n ready-after-call-work	^{ot} Ōtrl+Alt+Z	When the application is started or restarted.
interaction-workspace	keyboard.shortcut.state.re	eaCityI+AIt+R	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

interaction-workspace keyboard.shortcut.teamlead.chat.bargein started or restarted. interaction-workspace keyboard.shortcut.teamlead.chat.stop- When the application is started or restarted. interaction-workspace keyboard.shortcut.teamlead.stop- When the application is started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.bargein Started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.coaching When the application is started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.coaching When the application is started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.monitor When the application is started or restarted. interaction-workspace keyboard.shortcut.toaster.actiop- When the application is started or restarted. interaction-workspace keyboard.shortcut.toaster.actiop- When the application is started or restarted. interaction-workspace keyboard.shortcut.toaster.actiop- When the application is started or restarted. interaction-workspace kpi.displayed-kpis When the application is started or restarted. interaction-workspace kpi.displayed-kpis When the application is started or restarted. interaction-workspace kpi.show-agent-groups true When the application is started or restarted. interaction-workspace license.lrm-enabled false When the application is started or restarted. interaction-workspace log.default-filter-type Copy Immediately. Immediatel	Section	Option	Default	Changes Take Effect
interaction-workspace keyboard.shortcut.teamlead.stop- interaction-workspace keyboard.shortcut.teamlead.voice.bargein started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.coaching started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.coaching When the application is started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.coaching When the application is started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.stop- monitoring When the application is started or restarted. interaction-workspace keyboard.shortcut.toaster.actineBe interaction-workspace keyboard.shortcut.toaster.actineBe interaction-workspace keyboard.shortcut.toaster.actineBe interaction-workspace keyboard.shortcut.toaster.actineBe interaction-workspace kpi.displayed-kpis When the application is started or restarted. interaction-workspace kpi.displayed-kpis When the application is started or restarted. interaction-workspace kpi.show-agent-groups true When the application is started or restarted. interaction-workspace log.default-filter-type Copy Immediately. interaction-workspace log.espire 10 Immediately. interaction-workspace log.expire 10 Immediately. interaction-	interaction-workspace	keyboard.shortcut.teamle	ad.chat.bargein	
interaction-workspace keyboard.shortcut.teamlead.voice.bargein started or restarted. When the application is started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.coaching When the application is started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.monitor When the application is started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.stop- When the application is started or restarted. Interaction-workspace keyboard.shortcut.toaster.detniade when the application is started or restarted. Interaction-workspace kpi.displayed-kpis When the application is started or restarted. Interaction-workspace kpi.refresh-time 10 When the application is started or restarted. Interaction-workspace kpi.show-agent-groups true When the application is started or restarted. Interaction-workspace log.default-filter-type Copy Immediately. Immediately. Interaction-workspace log.expire 10 Immediately. Immediately. Interaction-workspace log.expire 10 Immediately. Immediately. Interaction-workspace log.expire 10 Immediately. Interaction-workspace log.pspire 10 Immediately. Interaction-workspace log.pspire 10 Immediately. Immediately. Immediately. Interaction-workspace log.pspire 10 Immediately. Immediately. Immediately. Immediately. Interaction-workspace log.pspire 10 Immediately. Immediately. Immediately. Interaction-workspace log.pspire 10 Immediately. Immediately. Interaction-workspace log.pspire 10 Immediately. In	interaction-workspace		ad.chat.stop-	
interaction-workspace keyboard.shortcut.teamlead.voice.coaching started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.coaching started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.stop when the application is started or restarted. interaction-workspace keyboard.shortcut.toaster.aCtdpG When the application is started or restarted. interaction-workspace keyboard.shortcut.toaster.aCtdpG When the application is started or restarted. interaction-workspace keyboard.shortcut.toaster.aCtdpG When the application is started or restarted. interaction-workspace kpi.displayed-kpis When the application is started or restarted. interaction-workspace kpi.show-agent-groups true When the application is started or restarted. interaction-workspace license.lrm-enabled false Started or restarted. interaction-workspace log.default-filter-type Copy Immediately. interaction-workspace log.esDK All Immediately. interaction-workspace log.expire 10 Immediately. interaction-workspace log.expire 10 Immediately. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.segment 10MB When the application is started or restarted. Immediately. interaction-workspace log.segment 10MB When the application is started or restarted. Interaction-workspace log.verbose Trace Immediately. When the application is started or restarted. Interaction-workspace log.verbose Trace Immediately. When the application is started or restarted. Interaction-workspace log.verbose Trace Immediately. When the application is started or restarted. Interaction-workspace log.verbose Trace Immediately. When the application is started or restarted. Interaction-workspace log.verbose Trace Immediately. When the application is started or restarted.	interaction-workspace		ad.stop-	
interaction-workspace keyboard.shortcut.teamlead.voice.monitor started or restarted. interaction-workspace keyboard.shortcut.teamlead.voice.stop When the application is started or restarted. interaction-workspace keyboard.shortcut.toaster.acthpG When the application is started or restarted. interaction-workspace keyboard.shortcut.toaster.acthpG When the application is started or restarted. interaction-workspace kpi.displayed-kpis When the application is started or restarted. interaction-workspace kpi.refresh-time 10 When the application is started or restarted. interaction-workspace kpi.show-agent-groups true When the application is started or restarted. interaction-workspace license.lrm-enabled false When the application is started or restarted. Interaction-workspace log.default-filter-type Copy Immediately. Immediately. interaction-workspace log.expire 10 Immediately. Immediately. interaction-workspace log.expire 10 Immediately. Immediately. interaction-workspace log.max-age 10 When the application is started or restarted. Interaction-workspace log.pSDK Standard Immediately. interaction-workspace log.segment 10MB When the application is started or restarted. Interaction-workspace log.segment 10MB When the application is started or restarted. Interaction-workspace log.segment 10MB When the application is started or restarted. Interaction-workspace log.verbose Trace Immediately. Immediately. Immediately. Interaction-workspace log.verbose Trace Immediately. When the application is started or restarted. Interaction-workspace login.chat.can-unactivate-channel false when the application is started or restarted.	interaction-workspace	keyboard.shortcut.teamle	ad.voice.bargein	
interaction-workspace keyboard.shortcut.teamlead.voice.stop-monitoring When the application is started or restarted. keyboard.shortcut.toaster.aCtdpG When the application is started or restarted. interaction-workspace keyboard.shortcut.toaster.aCtdpG When the application is started or restarted. interaction-workspace kpi.displayed-kpis When the application is started or restarted. interaction-workspace kpi.refresh-time 10 When the application is started or restarted. interaction-workspace kpi.show-agent-groups true When the application is started or restarted. interaction-workspace license.Irm-enabled false When the application is started or restarted. interaction-workspace log.default-filter-type Copy Immediately. interaction-workspace log.expire 10 Immediately. interaction-workspace log.expire 10 Immediately. interaction-workspace log.filter-data.	interaction-workspace	keyboard.shortcut.teamle	ad.voice.coaching	
monitoring started or restarted. Interaction-workspace keyboard.shortcut.toaster.actid=6 Interaction-workspace keyboard.shortcut.toaster.actid=6 Interaction-workspace keyboard.shortcut.toaster.actid=6 Interaction-workspace kpi.displayed-kpis Interaction-workspace kpi.refresh-time 10 When the application is started or restarted. Interaction-workspace kpi.show-agent-groups true When the application is started or restarted. Interaction-workspace license.lrm-enabled false When the application is started or restarted. Interaction-workspace log.default-filter-type Copy Immediately. Interaction-workspace log.expire 10 Immediately. Interaction-workspace log.spire 10 Immediately. Interaction-workspace log.max-age 10 When the application is started or restarted. Interaction-workspace log.spire 10 Immediately. Interaction-workspace log.spire 10 Immediately. Interaction-workspace log.spire 10 Immediately. Interaction-workspace log.spire 10 When the application is started or restarted. Interaction-workspace log.segment 10MB When the application is started or restarted. Interaction-workspace log.segment 10MB When the application is started or restarted. Interaction-workspace log.verbose Trace Immediately. Interaction-workspace log.verbose Trace Immediately. Interaction-workspace login.chat.can- Interaction-workspace	interaction-workspace	keyboard.shortcut.teamle	ad.voice.monitor	
interaction-workspace keyboard.shortcut.toaster.define started or restarted. interaction-workspace kpi.displayed-kpis When the application is started or restarted. interaction-workspace kpi.refresh-time 10 When the application is started or restarted. interaction-workspace kpi.show-agent-groups true When the application is started or restarted. interaction-workspace license.lrm-enabled false When the application is started or restarted. interaction-workspace log.default-filter-type Copy Immediately. interaction-workspace log.ESDK All Immediately. interaction-workspace log.filter-data.keyName> Copy Immediately. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.verbose Trace Immediately. interaction-workspace log.verbose Trace Immediately. interaction-workspace login.chat.auto-not-ready-reason Started or restarted. interaction-workspace login.chat.can-unactivate-channel false Started or restarted.	interaction-workspace		ad.voice.stop-	
interaction-workspace kpi.displayed-kpis started or restarted. kpi.displayed-kpis When the application is started or restarted. kpi.refresh-time 10 When the application is started or restarted. kpi.show-agent-groups true When the application is started or restarted. kpi.show-agent-groups true When the application is started or restarted. interaction-workspace license.lrm-enabled false When the application is started or restarted. interaction-workspace log.default-filter-type Copy Immediately. interaction-workspace log.expire 10 Immediately. interaction-workspace log.spire 10 Immediately. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.pspk Standard Immediately. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.verbose Trace Immediately. interaction-workspace log.verbose Trace Immediately. interaction-workspace log.verbose Trace Immediately. interaction-workspace login.chat.auto-not-ready-reason started or restarted. interaction-workspace login.chat.can-unactivate-channel false When the application is started or restarted.	interaction-workspace	keyboard.shortcut.toaster	.aCtr dp tG	
interaction-workspace kpi.displayed-kpis started or restarted. interaction-workspace kpi.show-agent-groups true When the application is started or restarted. interaction-workspace license.lrm-enabled false When the application is started or restarted. interaction-workspace log.default-filter-type Copy Immediately. interaction-workspace log.expire 10 Immediately. interaction-workspace log.expire 10 Immediately. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.segment 10 When the application is started or restarted. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.verbose Trace Immediately. interaction-workspace log.verbose Trace Immediately. interaction-workspace login.chat.auto-not-ready-reason false When the application is started or restarted.	interaction-workspace	keyboard.shortcut.toaster	. <mark>d@talli#te</mark> Vl	
interaction-workspace kpi.show-agent-groups true Started or restarted. interaction-workspace license.lrm-enabled false When the application is started or restarted. interaction-workspace log.default-filter-type Copy Immediately. interaction-workspace log.expire 10 Immediately. interaction-workspace log.filter-data. <keyname> Copy Immediately. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.psdk Standard Immediately. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.verbose Trace Immediately. interaction-workspace log.verbose Trace Immediately. interaction-workspace log.verbose Trace Immediately. interaction-workspace log.verbose Trace Immediately. interaction-workspace log.nchat.auto-not-ready-reason false When the application is started or restarted. interaction-workspace login.chat.can-unactivate-channel false When the application is started or restarted.</keyname>	interaction-workspace	kpi.displayed-kpis		
interaction-workspace license.lrm-enabled false When the application is started or restarted. interaction-workspace log.default-filter-type Copy Immediately. interaction-workspace log.expire 10 Immediately. interaction-workspace log.max-age 10 Immediately. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.psDK Standard Immediately. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.orace started interaction-workspace log.orace Immediately. interaction-workspace log.orace frace Immediately. interaction-workspace login.chat.auto-not-ready-reason false When the application is started or restarted. When the application is started or restarted or restarted.	interaction-workspace	kpi.refresh-time	10	
interaction-workspace log.default-filter-type Copy Immediately. interaction-workspace log.ESDK All Immediately. interaction-workspace log.expire 10 Immediately. interaction-workspace log.filter-data. <keyname> Copy Immediately. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.PSDK Standard Immediately. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.Trace \$Application.RootApplicationData\$logy. interaction-workspace log.verbose Trace Immediately. interaction-workspace login.chat.auto-not-ready-reason When the application is started or restarted interaction-workspace login.chat.can-unactivate-channel false When the application is started or restarted.</keyname>	interaction-workspace	kpi.show-agent-groups	true	
interaction-workspace log.expire 10 Immediately. interaction-workspace log.expire 10 Immediately. interaction-workspace log.filter-data. <keyname> Copy Immediately. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.PSDK Standard Immediately. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.Trace SApplication.RootApplicationDatas\log\log\log\log\log\log\log\log\log\log</keyname>	interaction-workspace	license.lrm-enabled	false	
interaction-workspace log.expire 10 Immediately. interaction-workspace log.filter-data. <keyname> Copy Immediately. interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.PSDK Standard Immediately. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.Trace \$Application.RootApplicationData\$\log\cdot\cdot\cdot\cdot\cdot\cdot\cdot\cdot</keyname>	interaction-workspace	log.default-filter-type	Сору	Immediately.
interaction-workspace log.max-age 10 When the application is started or restarted. Interaction-workspace log.PSDK Standard Immediately. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.Trace \$Application.RootApplicationData\$log\(\) interaction-workspace log.verbose Trace Immediately. interaction-workspace login.chat.auto-not-ready-reason login.chat.can-unactivate-channel false When the application is started or restarted.	interaction-workspace	log.ESDK	All	Immediately.
interaction-workspace log.max-age 10 When the application is started or restarted. interaction-workspace log.PSDK Standard Immediately. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.Trace SApplication.RootApplicationData\$\log\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\	interaction-workspace	log.expire	10	Immediately.
interaction-workspace log.PSDK Standard Immediately. interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.Trace \$Application.RootApplicationData\$\log\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\	interaction-workspace		Сору	Immediately.
interaction-workspace log.segment 10MB When the application is started or restarted. interaction-workspace log.Trace SApplication.RootApplicationData\$\log\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\	interaction-workspace	log.max-age	10	
interaction-workspace log.Segment log.Segm	interaction-workspace	log.PSDK	Standard	Immediately.
interaction-workspace log.verbose Trace Immediately. login.chat.auto-not-ready-reason When the application is started or restarted login.chat.can-unactivate-channel false When the application is started or restarted.	interaction-workspace	log.segment	10MB	
interaction-workspace	interaction-workspace	log.Trace	\$Application.RootApplicat InteractionWorkspace	ionData\$\log\ Immediately.
ready-reason started or restarted interaction-workspace login.chat.can- unactivate-channel false when the application is started or restarted.	interaction-workspace	log.verbose	Trace	Immediately.
unactivate-channel started or restarted.	interaction-workspace			
Section Option Default Changes Take Effect	interaction-workspace		false	
	Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	login.chat.is-auto-ready	false	When the application is started or restarted.
interaction-workspace	login.default-place		When the application is started or restarted.
interaction-workspace	login.email.auto-not- ready-reason		When the application is started or restarted
interaction-workspace	login.email.can- unactivate-channel	false	When the application is started or restarted.
interaction-workspace	login.email.is-auto- ready	false	When the application is started or restarted.
interaction-workspace	login.enable-login- without-channel	true	When the application is started or restarted.
interaction-workspace	login.enable-place- completion	true	When the application is started or restarted.
interaction-workspace	login.enable-same- agent-place	true	When the application is started or restarted.
interaction-workspace	login.im.auto-not-ready- reason		When the application is started or restarted
interaction-workspace	login.im.available- queues	ACDQueue	When the application is started or restarted.
interaction-workspace	login.im.can-unactivate- channel	false	When the application is started or restarted
interaction-workspace	login.im.is-auto-ready	false	When the application is started or restarted
interaction-workspace	login.im.prompt-agent- login-id	false	When the application is started or restarted.
interaction-workspace	login.im.prompt-dn- password	false	When the application is started or restarted.
interaction-workspace	login.im.prompt-queue	false	When the application is started or restarted.
interaction-workspace	login.prompt-place	false	When the application is started or restarted.
interaction-workspace	login.sip-cluster.phone- number		When the application is started or restarted.
interaction-workspace	login.sip-cluster.store- recent-phone-number	true	When the application is started or restarted.
interaction-workspace	login.sms.auto-not- ready-reason		When the application is started or restarted
interaction-workspace	login.sms.can- unactivate-channel	false	When the application is started or restarted.
interaction-workspace	login.sms.is-auto-ready	false	When the application is started or restarted.
interaction-workspace	login.store-recent-place	true	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	login.voice.auto-not- ready-reason		When the application is started or restarted
interaction-workspace	login.voice.available- queues	ACDQueue	When the application is started or restarted.
interaction-workspace	login.voice.can- unactivate-channel	false	When the application is started or restarted
interaction-workspace	login.voice.force-relogin	false	When the application is started or restarted
interaction-workspace	login.voice.is-auto-ready	false	When the application is started or restarted
interaction-workspace	login.voice.prompt- agent-login-id	false	At the next interaction
interaction-workspace	login.voice.prompt-dn- less-phone-number	false	When the application is started or restarted.
interaction-workspace	login.voice.prompt-dn- password	false	When the application is started or restarted.
interaction-workspace	login.voice.prompt- queue	true	When the application is started or restarted.
interaction-workspace	login.webcallback.auto- not-ready-reason		When the application is started or restarted
interaction-workspace	login.webcallback.can- unactivate-channel	false	When the application is started or restarted.
interaction-workspace	login.webcallback.is- auto-ready	false	When the application is started or restarted.
interaction-workspace	login.workmode	unknown	When the application is started or restarted or if the agent changes place.
interaction-workspace	login. <media- type>.auto-not-ready- reason</media- 	false	When the application is started or restarted.
interaction-workspace	login. <media- type>.can-unactivate- channel</media- 	false	When the application is started or restarted.
interaction-workspace	login. <media-type>.is- auto-ready</media-type>	false	When the application is started or restarted.
interaction-workspace	logout.enable-exit-on- logoff-error	true	When the application is started or restarted.
interaction-workspace	main-window.dockable	true	When the application is started or restarted.
interaction-workspace	main-window.window- title	\$Window.Title\$	Immediately.
interaction-workspace	openmedia.bundle.sms	sms,smssession	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	openmedia.workitem- channels		When the application is started or restarted.
interaction-workspace	options.record-option- locally-only	false	When the application is started or restarted.
interaction-workspace	outbound.call-result- automatically-selected		At the next interaction.
interaction-workspace	outbound.call-result- values	Answered,AnsweringMach	in Act, Bhus yn Abkt Ai n sevrar, tMoro ng N
interaction-workspace	outbound- callback.ringing-bell		At the next interaction.
interaction-workspace	outbound.campaign- stale-timeout	0	When the application is started or restarted.
interaction-workspace	outbound.fields.float- separator-in-db		Immediately.
interaction-workspace	outbound.push- preview.auto-answer	false	At the next interaction.
interaction-workspace	outbound.push- preview.media-types	outboundpreview	When the application is started or restarted.
interaction-workspace	outbound.push- preview.use-combined- channel	true	When the application is started or restarted.
interaction-workspace	outbound.record-information.frame-color	FFDFE8F6	At the next interaction.
interaction-workspace	outbound.record- information.header- foreground-color	FF15428B	At the next interaction.
interaction-workspace	outbound.sound.campaigr updated	1 -	At the next interaction.
interaction-workspace	outbound.treatment- mode	none	Immediately.
interaction-workspace	presence.evaluate- presence	true	When the application is started or restarted.
interaction-workspace	printing.use-print- preview	true	Immediately.
interaction-workspace	security.disable-rbac	false	When the application is started or restarted.
interaction-workspace	security.enable-debug- information	false	Immediately.
interaction-workspace	security.inactivity-not- ready-reason		When the application is started or restarted.
interaction-workspace	security.inactivity-set- agent-not-ready	true	When the application is started or restarted.
interaction-workspace	security.inactivity- timeout	0	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	sip-cluster.data-center- locations		When the application is started or restarted.
interaction-workspace	sip-cluster.reconnect- timeout	10	Immediatly.
interaction-workspace	sipendpoint.audio.headse	t.audio_in_agc_enabled	When the application is started or restarted.
interaction-workspace	sipendpoint.audio.incomir	ngluse_agc	When the application is started or restarted.
interaction-workspace	sipendpoint.authenticate- with-dn-password	false	When the application is started or restarted.
interaction-workspace	sipendpoint.exit-on- voice-logoff	false	At next Log Off operation or at next login.
interaction-workspace	sipendpoint.genesyslab.b	eമൂ ൂൂൂൂ	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.b	edptone.enable_beeptone	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.b	e ⊕ tone.play_locally	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.co	or û rol.auto_answer	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.de	evice.audio_in_device	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.de	evice.audio_out_device	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.de	e 460 .error_code_when_hea	When the application is districted or restarted.
interaction-workspace	sipendpoint.genesyslab.de	evice.headset_name	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.de	e v 0ce.manual_audio_device	When the application is configure started or restarted.
interaction-workspace	sipendpoint.genesyslab.de	ev0ce.reject_call_when_head	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.de	ev0ce.use_headset	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.de	tn 100 ause_start_stop_dtmf	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.de	tn 0 f.play_locally	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_AbstractPho	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_Audio	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ystem.log_level_Auto	When the application is
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
	Configuration		started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_CCM	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_Conferencii	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_Contacts	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_DNS	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_Endpoint	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_litter	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_Licensing	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_Media	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_Privacy	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_RTP	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_Security	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_Storage	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_STUN	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_Transport	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy Devices	ystem.log_level_USB	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_Utilities	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy Quality	ystem.log_level_Voice	When the application is started or restarted.
interaction-workspace	sipendpoint.genesyslab.sy	ys 0 em.log_level_XMPP	When the application is started or restarted.
interaction-workspace	sipendpoint.headset- enforce-configured- usage	false	When the application is started or restarted.
interaction-workspace	sipendpoint.headset- replugged-set-ready	true	When the application is started or restarted.
interaction-workspace	sipendpoint.headset- unplugged.not-ready-		When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
	reason		
interaction-workspace	sipendpoint.headset- unplugged-set-not- ready	true	When the application is started or restarted.
interaction-workspace	sipendpoint.init- attempt-nb	10	When the application is started or restarted.
interaction-workspace	sipendpoint.init- attempt-timer	1	When the application is started or restarted.
interaction-workspace	sipendpoint.log.verbose	Trace	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	0360@ister_in_seconds	When the application is started or restarted.
interaction-workspace	sipendpoint.proxies.proxy	136@gister_in_seconds	When the application is started or restarted.
interaction-workspace	sipendpoint.retain- volume-settings- between-sessions	false	When the application is started or restarted.
interaction-workspace	sipendpoint.rtp.2833.enak	ol ₫ d	When the application is started or restarted.
interaction-workspace	sipendpoint.rtp.2833.hold	_d\00°_time_in_ms	When the application is started or restarted.
interaction-workspace	sipendpoint.rtp.2833.pack	ce6@time_in_ms	When the application is started or restarted.
interaction-workspace	sipendpoint.rtp.2833.payl	ođ @ _lnumber	When the application is started or restarted.
interaction-workspace	sipendpoint.rtp.inactivity.t	:ir 0 .er_enabled	When the application is started or restarted.
interaction-workspace	sipendpoint.sbc- register-address		When the application is started or restarted.
interaction-workspace	sipendpoint.sbc- register-address.peer		When the application is started or restarted.
interaction-workspace	sipendpoint.sbc- register-port		When the application is started or restarted.
interaction-workspace	sipendpoint.sbc- register-port.peer		When the application is started or restarted.
interaction-workspace	sipendpoint.system.diagn	ostics.enable_logging	When the application is started or restarted.
interaction-workspace	sipendpoint.system.diagn	oshinosrlog_level	When the application is started or restarted.
interaction-workspace	sipendpoint.system.dtmf.f	oce_send_in_band	When the application is started or restarted.
interaction-workspace	sipendpoint.system.dtmf.i	m #0 mum_rfc2833_play_tim	e When the application is started or restarted.
interaction-workspace	sipendpoint.system.indial	og_notify.enable_indialogno	ti fy hen the application is
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
			started or restarted.
interaction-workspace	sipendpoint.system.netwo	or 0 .dtx_enabled	When the application is started or restarted.
interaction-workspace	sipendpoint.system.qos.a	udicos 46	When the application is started or restarted.
interaction-workspace	sipendpoint.transport- protocol	UDP	When the application is started or restarted.
interaction-workspace	sipendpoint.tuning.mixer.	al lo w_master_volume_chan	When the application is started or restarted.
interaction-workspace	sms.agent.prompt-color •	FF385078	Immediately.
interaction-workspace	sms.agent.text-color •	FF385078	Immediately.
interaction-workspace	sms.auto-answer	false	At the next interaction.
interaction-workspace	sms.client.prompt-color •	FF166FFF	Immediately.
interaction-workspace	sms.client.text-color •	FF166FFF	Immediately.
interaction-workspace	sms.default-queue		At the next interaction.
interaction-workspace	sms.from-numbers- business-attribute		At the next interaction.
interaction-workspace	sms.max-message- number	8	At the next interaction.
interaction-workspace	sms.other- agent.prompt-color	FFD88000	Immediately.
interaction-workspace	sms.other-agent.text- color	FFD88000	Immediately.
interaction-workspace	sms.outbound-queue		Immediately.
interaction-workspace	sms.prompt-for-done	false	At the next interaction.
interaction-workspace	sms.ringing-bell	Sounds\Ring.mp3	At the next interaction.
interaction-workspace	sms.subject-max-chars	25	At the next interaction.
interaction-workspace	sms.time-stamp	true	Immediately.
interaction-workspace	sms.transcript-time- frame	24	At the next interaction.
interaction-workspace	sounds.preloadfiles	Sounds\Ring.mp3	At the next interaction.
interaction-workspace	spellchecker.corporate- dictionary		When the application is started or restarted.
interaction-workspace	spellchecker.corporate- dictionary-file		When the application is started or restarted.
interaction-workspace	standard-	\$AII\$	At the next interaction.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
	response.categories		
interaction-workspace	standard- response.default- search-type	AnyKeyword	At the next interaction.
interaction-workspace	standard- response.enable-usage- feedback	true	At the next interaction.
interaction-workspace	standard- response.languages	\$AII\$	At the next interaction.
interaction-workspace	standard- response.suggested- responses-min- relevancy	50	At the next interaction.
interaction-workspace	statistics.displayed- statistics		When the application is started or restarted.
interaction-workspace	statistics.queues		When the application is started or restarted.
interaction-workspace	statistics.refresh-time	10	When the application is started or restarted.
interaction-workspace	statistics.routing-points		When the application is started or restarted.
interaction-workspace	system-tray.tooltip	\$Application.Title\$	When the application is started or restarted.
interaction-workspace	teamcommunicator.add- recent-filters.voice		At next interaction event.
interaction-workspace	teamcommunicator.alway clear-textbox-on-new- interaction	S- true	Immediately.
interaction-workspace	teamcommunicator.contactactactactactactactactactactactactact	ct Category, First Name, Last N	When the application is lame Phone Number EmailA started or restarted.
interaction-workspace	teamcommunicator.corpor favorites	rate-	When the application is started or restarted.
interaction-workspace	teamcommunicator.corpor	rate-	When the application is started or restarted.
interaction-workspace		m ₋ Category, First Name, Last N	When the application is lame Phone Number EmailA started or restarted.
interaction-workspace	teamcommunicator.intern favorite-fields	a Čategory, Display Name	When the application is started or restarted.
interaction-workspace	teamcommunicator.list-filter-showing	Agent,AgentGroup,Skill,Rd	When the application is pulling on the application is started or restarted.
interaction-workspace	teamcommunicator.list- status-reachable	NotReady	When the application is started or restarted.
interaction-workspace	teamcommunicator.load- at-startup	true	When the application is started or restarted.

interaction-workspace teamcommunicator.max suggestion-size teamcommunicator.recent 10 started or restarted. interaction-workspace teamcommunicator.recent 10 When the application is started or restarted. interaction-workspace teamcommunicator.request 300 When the application is started or restarted. Interaction-workspace true At the next agent search. Interaction-workspace true At the next agent search. Interaction-workspace true At the next agent search. Interaction-workspace toast case-data content interaction-workspace toast case-data content business-attribute (SContact.FirstNames) interaction-workspace toast case-data content business-attribute (SContact.FirstNames) interaction-workspace toast window-title (SContact.FirstNames) interaction-workspace views.CaseContactRegion and transferormative forms order o	Section	Option	Default	Changes Take Effect	
interaction-workspace teamcommunicator.request 300 When the application is started or restarted. Started or restarted. interaction-workspace teamlead.agent true action-workspace teamlead.agent status.enabled.agent group-security-mode teamlead.monitoring call Immediately. interaction-workspace toast.case-data.content toast.case-data.content business-attribute (\$Contact.FirstNames toast.case-data.content business-attribute (\$Contact.FirstNames toast.window-title \$Contact.LastNames tonteraction-workspace views.CaseContactRegion activates to toast.window-title (\$Contact.FirstNames tonteraction-workspace views.CaseContactRegion activates tonteraction-workspace views.CaseContactRegion activates tonteraction-workspace views.CaseContactRegion activates tonteraction-workspace views.CaseContactRegion activates tonteraction-workspace views.ContactInfoHistoryMuchiRegion.activates tonteraction-workspace views.ContactInfoHistoryMuchiRegion.activates (wiews.ContactInfoHistoryMuchiRegion.activates) with the views.are order views.ContactInfoHistoryMuchiRegion.activates (wiews.ContactInfoHistoryMuchiRegion.activates) with the views.are order views.ContactTabBottomHistoryMuchiRegion.activates (wiews.ContactHistoryCase views.ContactTabBottomHistoryMuchiRegion.activates) with the views.are order views.ContactTabBottomHistoryMuchiRegion.activates (wiews.ContactHistoryCase views.Interaction-workspace views.InteractionDetailsRegionspositionsview,ContactHistoryCase views.InteractionDetailsRegionspositionsview.NotepadvyMistoryContactHistory.WistoryContactHistory.MystoryContactHisto	interaction-workspace	suggestion-size			
interaction-workspace teamlead_agent- status_enabled_agent- status_enabled_agent_ status_enabled_agent_enabled	interaction-workspace	max-records		When the application is started or restarted.	
interaction-workspace teamlead-gent-group-security-mode search. interaction-workspace teamlead-monitoring scope interaction-workspace toast_case_data.content History.CaseData At the next interaction. Immediately. Immediate	interaction-workspace	teamcommunicator.reques start-timer	st 300		
interaction-workspace toast.case-data.content toast.ca	interaction-workspace	status.enabled-agent-	true		
interaction-workspace toast.window-title (\$Contact.FirstName\$ Immediately. Im	interaction-workspace	3	call	Immediately.	
interaction-workspace toast.window-title (\$Contact.FirstName\$ Immediately. interaction-workspace views.CaseContactRegion.activate (Contact.LastName\$ Immediately. interaction-workspace views.CaseContactRegion.activate (ContactInformativate) interaction-workspace views.CaseContactRegion.driteractionContactInformativate (ContactInformativate) interaction-workspace views.CaseViewSideButton Interaction ContactInformativate (ContactInformativate) interaction-workspace views.ContactInfoHistory MutbRegion activate (ContactInfoHistory MutbRegion activate (ContactInfo	interaction-workspace	toast.case-data.content	History,CaseData	At the next interaction.	
interaction-workspace views.CaseContactRegion.activate.nheractionContactInformatingStaffactionContactHistoryView interaction-workspace views.CaseContactRegion.dnteractionContactInformatingStaffactionContactHistoryView interaction-workspace views.CaseContactRegion.dnteractionContactInformatingStaffactionContactHistoryView interaction-workspace views.CaseViewSideButtonNewspace views.ContactInfoHistoryMuttiRegionContactInformationView.CompactivateContactInfoHistoryMuttiRegionContactInfoHistoryCo	interaction-workspace			At the next interaction	
interaction-workspace views. CaseViewSideButton InteractionContactInformationSideButton Interaction-workspace views. ContactInfoHistoryMultiRegion.activate. interaction-workspace views. ContactTabBottomHistoryMultiRegion.activate. interaction-workspace views. ContactTabBottomHistoryMultiRegion.activate. interaction-workspace views. ContactTabBottomHistoryRegion.activate. interaction-workspace views. InteractionDetailsRegion.activate. interaction-workspace views. InteractionDetailsRegion.activate. interaction-workspace views. InteractionDetailsRegion.activate. interaction-workspace views. ToolbarWorkplaceRegion.activate. interaction-workspace views. ToolbarWorkplaceRegion.activate. interaction-workspace views. ToolbarWorkplaceRegion.activate. views. WorkbinsTabBottomHistory.Mistalliated. views. WorkbinsTabBottomHistory.Mistalliat	interaction-workspace	toast.window-title		Immediately.	
interaction-workspace views.ContactInfoHistoryMultiRegion activate interaction-workspace views.ContactInfoHistoryMultiRegion activate order views.ContactTabBottomHistoryMultiRegion activate order views.ContactTabBottomHistoryMultiRegion activate order views.ContactTabBottomHistoryMultiRegion activate order views.ContactTabBottomHistoryMultiRegion activate order views.Interaction-workspace views.InteractionDetailsRegion activate order views.InteractionDetailsRegion activate order views.InteractionDetailsRegion activate order views.InteractionDetailsRegionsview.NotepadView.Mistantiated. views.are order views.InteractionDetailsRegionsview.NotepadView.NotepadView.Mistantiated. views.are interaction-workspace views.ToolbarWorkplaceRegionPlaceStatusView.myCamMistantiated. views.MyContactHistory.MyStantiated. views.ToolbarWorkplaceRegionPlaceStatusView.myCamMistantiated. views.MyContactHistory.MyStantiated. views.ToolbarWorksheetButthyWorkplaceBettutonView.MyContactHistory.MyStantiated. views.ToolbarWorksheetButthyWorkplaceBettutonView.MyContactHistory.MyStantiated. views.ToolbarWorksheetButthyWorkplaceBettutonView.MyContactHistory.MyStantiated. views.WorkbinsTabBottomHistoryCabIstatusView.WorkplaceActivate views.WorkbinsTabBottomHistoryCabIstatusView.WorkplaceActivate views.WorkbinsTabBottomHistoryCabIstatusView.WorkplaceActivate views.WorkbinsTabBottomHistoryCabIstatusView.WorkplaceActivate views.WorkbinsTabBottomHistoryCabIstatusView.WorkplaceActivate views.WorkbinsTabBottomHistoryCabIstatusView.WorkplaceActivate views.WorkbinsTabBottomHistoryCabIstatusView.WorkplaceActivate views.WorkplaceActivate views.WorkplaceActivate views.WorkplaceActivate views.WorkplaceActivate views.WorkplaceActivate views.WorkplaceActivate views.WorkplaceActivate views.WorkplaceActivate v	interaction-workspace	views.CaseContactRegion.order	activate- InteractionContactInforma	When the views are tion view interaction Contact instantiated.	tHistoryView
interaction-workspace views.ContactInfoHistoryMutbiRegion.activate. interaction-workspace views.ContactInfoHistoryMutbiRegion.activate. interaction-workspace views.ContactTabBottomHistoryMutbiRegion.activate. interaction-workspace views.ContactTabBottomHistoryMutbiRegion.activate. interaction-workspace views.ContactTabBottomHistoryMutbiRegion.activate. interaction-workspace views.InteractionDetailsRegion.activate. interaction-workspace views.InteractionDetailsRegion.activate. interaction-workspace views.InteractionDetailsRegion.activate. interaction-workspace views.InteractionDetailsRegion.activate. interaction-workspace views.InteractionDetailsRegion.activate. interaction-workspace views.ToolbarWorkplaceRegion.activate. interaction-workspace views.ToolbarWorkplaceRegion.activate. interaction-workspace views.ToolbarWorkplaceRegion.activate. interaction-workspace views.ToolbarWorkplaceRegion.activate. interaction-workspace views.ToolbarWorkplaceRegion.activate. interaction-workspace views.ToolbarWorksheetButbyWorkplaceBettonView,MyContactHistory,MyStortactInteraction-workspace views.ToolbarWorksheetButbyWorkplaceBettonView,MyContactHistoryCastinteraction-workspace views.WorkbinsTabBottomHistoryMultiRegion.activate. interaction-workspace views.ContactHistoryCastintsTablated.	interaction-workspace	views.CaseContactRegion.	drtter action Contact Informa	When the views are tion view interaction Contaction Con	tHistoryView
interaction-workspace views.ContactInfoHistoryMultiRegion activate instantiated. views.ContactTabBottomHistoryMultiRegion activate instantiated. views.ContactTabBottomHistoryMultiRegion activate instantiated. views.ContactTabBottomHistoryMultiRegion activate instantiated. views.ContactTabBottomHistoryMultiRegion activate instantiated. views.InteractionDetailsRegion activate views.More padview, ContactHistoryCastinteraction-workspace views.InteractionDetailsRegion.activate views.Notepadview, MistoryMultiRegion.activate views.Activate views.InteractionDetailsRegion.activate views.Notepadview, MistoryMultiRegion.activate views.Activate views	interaction-workspace	views.CaseViewSideButtor	n Redgicarcticul © ontainer Side B	When the views are uttonview SRLSideButtonvi	ew
interaction-workspace views.ContactTabBottomHistoryMultiRegion.activate.the views.are order views.ContactTabBottomHistoryMultiRegion.activate.the views.are views.InteractionDetailsRegion.activate.order views.InteractionDetailsRegion.activate.order views.InteractionDetailsRegion.activate.order views.InteractionDetailsRegion.activate.order views.NotepadVoiceNotepadView.NotepadVoiceNotepadView.NotepadVoiceNotepadView.order views.are order views.ToolbarWorkplaceRegion.activate.order views.ToolbarWorkplaceRegion.activate.order views.ToolbarWorkplaceRegion.activate.order views.ToolbarWorkplaceRegion.activate.order views.ToolbarWorkplaceRegion.activate.order views.ToolbarWorkplaceRegion.activate.order views.ToolbarWorkplaceRegion.activate.order views.ToolbarWorkplaceRegion.activate.order views.ToolbarWorkplaceRegion.activate.order views.ToolbarWorksheetButMyWorkplaceBettonView,Mann.the.views.are.order views.ToolbarWorksheetButMyWorkplaceBettonView,Mann.the.views.are.order views.WorkbinsTabBottomHistory.MultiRegion.activate.order views.AccontactHistory.Castintsantiated.order views.WorkbinsTabBottomHistory.MultiRegion.activate.order views.AccontactHistory.Castintsantiated.order views.WorkbinsTabBottomHistory.Order views.WorkbinsTabBottomHistory.Order views.AccontactHistory.Castintsantiated.order views.WorkbinsTabBottomHistory.Order views.AccontactHistory.Order views.WorkbinsTabBottomHistory.Order views.AccontactHistory.Order views.AccontactHistory.Order views.WorkbinsTabBottomHistory.Order views.AccontactHistory.Order views.AccontactHistory.Order views.Order vi	interaction-workspace	views.ContactInfoHistoryMorder	lultiRegion activate- ContactinformationView,C	When the views are ontact History View instantiated.	
interaction-workspace views.InteractionDetailsReqDispositionsView,NotepadView, Use the views are order views.InteractionDetailsReqDispositionsView,NotepadView,ContactHistoryCasViews,NotepadView,ContactHistoryCasViews,NotepadView,ContactHistoryCasViews,NotepadView,ContactHistoryCasViews,NotepadView,ContactHistoryCasViews,NotepadView,ContactHistoryCasViews,NotepadView,ContactHistoryCasViews,NotepadView,ContactHistoryCasViews,NotepadView,ContactHistoryCasViews,NotepadView,ContactHistoryCasViews,NotepadView,ContactHistoryCasViews,NotepadView,ContactHistoryCasViews,NotepadView,ContactHistoryCasViews,NotepadViews,ContactHistoryCasViews,NotepadViews,ContactHistoryCasViews,Cont	interaction-workspace	views.ContactInfoHistoryM	<mark>l Cic Regitlm fordeation View, C</mark>	When the views are ontact listory view instantiated.	
interaction-workspace views.InteractionDetailsRegDispositionsView,NotepadView,When the views are interaction-workspace views.ToolbarWorkplaceRegDispositionsView,NotepadView,MyContactHistory,MySt interaction-workspace views.ToolbarWorkplaceRegMyPlaceStatusView,myCampaignsListView,MyContactHistory,MySt interaction-workspace views.ToolbarWorkplaceRegMyPlaceStatusView,myCampaignsListView,MyContactHistory,MySt interaction-workspace views.ToolbarWorkplaceRegMyPlaceStatusView,myCampaignsListView,MyContactHistory,MySt interaction-workspace views.ToolbarWorksheetButMyWorkplaceBetttonView,Mainstantiated. views.WorkbinsTabBottomHistoryMultiRegion.activate.When the views are ContactHistoryCas instantiated. views.WorkbinsTabBottomHistoryMultiRegion.activate.When the views are ContactHistoryCas instantiated.	interaction-workspace	views.ContactTabBottomH order	istory MultiRegion activate Contact Detail View, Contact	When the views are thistoryNotepadView,Conta instantiated.	ctHistoryCase
interaction-workspace views. ToolbarWorkplaceRegion activate order views. ToolbarWorksheetButMyWarkplaceBerttonView, Mann the views are order views. When the views are order views. WorkbinsTabBottomHistory MultiRegion activate order views. WorkbinsTabBottomHistory MultiRegion activate order views. When the views are order views. WorkbinsTabBottomHistory MultiRegion activate order views. WorkbinsTabBottomHistory MultiRegion activate order views. When the views are order views. WorkbinsTabBottomHistory MultiRegion activate order views. When the views are order views. WorkbinsTabBottomHistory MultiRegion activate order views. When the views are order views. WorkbinsTabBottomHistory MultiRegion activate order views. When the views are order views. WorkbinsTabBottomHistory MultiRegion activate order views. When the views are order views. WorkbinsTabBottomHistory MultiRegion activate order views. When the views are order views. WorkbinsTabBottomHistory MultiRegion activate order views. When the views are order views. WorkbinsTabBottomHistory MultiRegion activate order views. When the views are order views. WorkbinsTabBottomHistory MultiRegion activate order views. When the views are order views. WorkbinsTabBottomHistory MultiRegion activate order views. When the views are order views.	interaction-workspace	views.ContactTabBottomH	istontakttDetegilview,Contac	When the views are thistoryNotepadView,Conta instantiated.	ctHistoryCase
interaction-workspace views. ToolbarWorkplaceRegion activate interaction-workspace views. ToolbarWorkplaceRegion activate interaction-workspace views. ToolbarWorksheetButMyWegkplaceButtonView, MyCampaigns List View, MyContactHistory, MySt interaction-workspace views. ToolbarWorksheetButMyWegkplaceButtonView, Man ToolbarWorksheetButtonView interaction-workspace views. WorkbinsTabBottomHistoryMultiRegion activate When the views are ContactDetailView, ContactHistoryCas instantiated. Views. WorkbinsTabBottomHistoryMultiRegion activate When the views are ContactDetailView, ContactHistoryCas instantiated. Views. WorkbinsTabBottomHistoryMultiRegion activate When the views are contactHistoryCas instantiated.	interaction-workspace				
interaction-workspace views.ToolbarWorkplaceReg/byPtardeStatusView,myCampaignsListView,MyContactHistory,MyStantlated. views.ToolbarWorksheetButMyWegkplaceBerttonView,Main foolbarWorksinsContainerButtonView,Main foolbarWorksinsContainerButtonView	interaction-workspace	views.InteractionDetailsRe	<mark>egDisposiliėo</mark> nsView,Notepad	When the views are VoiceNotepadView Instantiated.	
interaction-workspace views. ToolbarWorksheetButMy/WegkphaoeBerttonView, Main ToolbarWorkshinsContainerButtonView instantiated. views. WorkbinsTabBottomHistoryMultiRegion. activate. When the views are ContactDetailView, ContactHistoryNotepadView, ContactHistoryCas instantiated. views. WorkbinsTabBottomHistory MiletailView of ContactHistory NotepadView, ContactHistoryCas instantiated.	interaction-workspace	views.ToolbarWorkplaceRe order	e <mark>gion activate</mark> MyPlaceStatusView, myCar	When the views are moalgnst ist view, MyContact instantiated.	History,MySt
interaction-workspace views. Workbins Tab Bottom History MultiRegion, activate. When the views are Contact Detail view, Contact History Note pad view, Contact History Cas instantiated. views. Workbins Tab Bottom History MultiRegion, activate. When the views are instantiated.	interaction-workspace	views.ToolbarWorkplaceRe	gwyPlacestatusView,myCar	When the views are moalgnst ist view, MyContact instantiated.	History,MySt
interaction-workspace views. Workbins Tab Bottom HCdoty MDletail View Contact History Note pad View, Contact History Cas	interaction-workspace	views.ToolbarWorksheetBu	utMby\WegkiphaoeBeuttonView,N	When the views are Jain foolbar Workbins Contair Instantiated.	nerButtonViev
	interaction-workspace	views.WorkbinsTabBottom order	HistoryMultiRegion activate ContactDetailView,Contac	When the views are this sory Notepad View, Containstantiated.	ctHistoryCase
Section Option Default Changes Take Effect	interaction-workspace	views.WorkbinsTabBottom	HCooota MD leitaily iew oco et a c	When the views are thistory Notepad View, Conta instantiated.	ctHistoryCase
	Section	Option	Default	Changes Take Effect	

Section	Option	Default	Changes Take Effect
interaction-workspace	voice.auto-answer	false	When the application is started or restarted.
interaction-workspace	voice.dtmf-inactivity- typing-timeout	500	At the next interaction.
interaction-workspace	voice.enable-init- conference	false	At the next interaction.
interaction-workspace	voice.enable-make-call- consultation	false	When the application is started or restarted.
interaction-workspace	voice.mark-done-on- release	false	At the next interaction.
interaction-workspace	voice.one-step-trsf- mode	default	When the application is started or restarted.
interaction-workspace	voice.prompt-for-end	false	At the next interaction.
interaction-workspace	voice.ringing-bell	Sounds\Ring.mp3	At the next interaction.
interaction-workspace	webcallback.auto- answer	false	At the next interaction.
interaction-workspace	webcallback.auto-dial	false	At the next interaction.
interaction-workspace	webcallback.callback- information.content	Subject,PhoneNumber,Typ	eASidhedwexdDaterActionactTi
interaction-workspace	webcallback.callback-information.frame-color	FFDFE8F6	At the next interaction.
interaction-workspace	webcallback.callback- information.header- foreground-color	FF15428B	At the next interaction.
interaction-workspace	webcallback.complete- queue		Immediately.
interaction-workspace	webcallback.park-queue		Immediately.
interaction-workspace	webcallback.reschedule- queue		Immediately.
interaction-workspace	webcallback.ringing-bell	Sounds\Ring.mp3	At the next interaction.
interaction-workspace	webproxy.address		At the next interaction.
interaction-workspace	webproxy.password		At the next interaction.
interaction-workspace	webproxy.username		At the next interaction.
interaction-workspace	workbin.email.draft		When the application is started or restarted.
interaction-workspace	workbin.email.draft.displa columns	<mark>yed-</mark> To,Subject,Submitted	When the application is started or restarted.
interaction-workspace	workbin.email.in- progress		When the application is started or restarted.
interaction-workspace	workbin.email.in- progress.displayed- columns	From,Subject,Received	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
interaction-workspace	workbin. <media- type>.<workbin- nickname></workbin- </media- 		When the application is started or restarted.
interaction-workspace	workbin. <media- type>.<workbin- nickname>.displayed- columns</workbin- </media- 	From,To,Subject,Received	When the application is started or restarted.
interaction-workspace	workbin. <media- type>.in-progress</media- 		When the application is started or restarted.
interaction-workspace	workbin. <media- type>.in- progress.displayed- columns</media- 	From,To,Subject,Received	When the application is started or restarted.
queue-presence	error-level	10	When the application is started or restarted.
queue-presence	statistic-name	CurrNumberWaitingCalls	When the application is started or restarted.
queue-presence	statistic-text	interaction(s) waiting.	When the application is started or restarted.
queue-presence	warning-level	5	When the application is started or restarted.
routing-point-presence	error-level	10	When the application is started or restarted.
routing-point-presence	statistic-name	CurrNumberWaitingCalls	When the application is started or restarted.
routing-point-presence	statistic-text	interaction(s) waiting.	When the application is started or restarted.
routing-point-presence	warning-level	5	When the application is started or restarted.
Section	Option	Default	Changes Take Effect

interaction-workspace Section

These options can be configured on the following Configuration Layer objects:

- · Workspace Application object
- Tenant
- · Agent Group
- User (Agent)

The options are grouped into categories. The Section interaction-workspace topic of the Workspace Deployment Guide breaks down the categories and provides a brief description of each.

The majority of Workspace configuration options are configured in the interaction-workspace section. This is a section that you create in the annex of the object to which you want to apply the option. Most of these options can be configured hierarchically at the Application, Tenant, Agent Group, or User level; some can be configured on other objects such as DNs, skills, and switches. For more information about using Workspace configuration options, refer to Introduction to Configuration Options.

The values specified for many options can also be overridden by Routing Strategies that reference Transaction objects.

Workspace options are grouped by functionality. The first word in the name of the option indicates the functional area to which the option belongs. For example, the option chat.emojis-business-attribute is part of the **chat** functionality group. It enables you to specify the name of the **business attribute** that contains the **emojis** that agents enabled for the Chat channel can use in the Chat window. The options are named to help you know quickly what the option does.

The *Workspace Deployment Guide* contains topics specific to configuring options as a group to manage each functional area. For example, you can read about setting up the Chat channel in the Chat topic.

- <media-type>.auto-answer
- <media-type>.prompt-fordone
- <media-type>.pull-fromhistory-isenabled
- <media-type>.ringing-bell
- <media-type>.toastinformation-key
- accessibility.agent-statechange-bell
- accessibility.interaction-statechange-bell

- accessibility.visualimpairment-profile
- accessibility.warningmessage-bell
- active-recording.screenrecorder-executable
- active-recording.screenrecorder-host
- activerecording.voice.recorder-uri
- activerecording.voice.recording-

type

- agent-status.enabled-actionsby-channel
- agent-status.enabled-actionsglobal
- agent-status.not-readyreasons
- · alert.timeout
- · application.available-layouts
- broadcast.color.high-priority
- · broadcast.color.important-

priority

- broadcast.color.low-priority
- · broadcast.color.minimalpriority
- · broadcast.color.normalpriority
- broadcast.displayed-columns
- broadcast.dn
- broadcast.mark-read-timeout
- broadcast.message-content
- broadcast.preview-timeout
- broadcast.sound.high-priority
- broadcast.sound.importantpriority
- · broadcast.sound.low-priority
- · broadcast.sound.minimalpriority
- broadcast.sound.normalpriority
- broadcast.subscribed.topics
- broadcast.toast-summary
- · broadcast.value-businessattribute
- case-data.float-separator
- · channel-information.windowtitle
- chat.agent.prompt-color
- · chat.agent.text-color
- chat.auto-answer
- chat.client.prompt-color
- chat.client.text-color
- · chat.enable-auto-disconnect
- chat.new-message-bell
- chat.nickname
- chat.other-agent.prompt-color
- chat.other-agent.text-color
- · chat.pending-response-tocustomer

- · chat.prompt-for-end
- chat.reconnect-attempts
- · chat.reconnect-timeout
- chat.ringing-bell
- chat.system.text-color
- chat.time-stamp
- chat.toast-information-key
- chat.typing-isenabled
- chat.typing-timeout
- · contact.available-directorypage-sizes
- contact.cache-timeout-delay
- contact.date-search-types
- · contact.default-directorypage-size
- contact.directory-advanceddefault
- · contact.directory-defaultmode
- contact.directory-displayedcolumns
- contact.directorypermissions. < ContactAttributeName * columns-treeview
- contact.directory-searchattributes
- contact.directory-searchtypes
- contact.displayed-attributes
- · contact.history-advanceddefault
- · contact.history-default-timefilter-main
- contact.history-displayedcolumns
- contact.history-displayedcolumns-treeview
- · contact.history.filters-<attribute>
- contact.history.media-filters
- contact.history-search-

attributes

- contact.last-calledagent.enable
- · contact.last-calledagent.<media-type>.enable
- contact.lookup.enable
- · contact.lookup.enable-createcontact
- · contact.lookup.<mediatype>.enable
- contact.lookup.<mediatype>.enable-create-contact
- contact.mandatory-attributes
- contact.metrics.enableinteractions-in-progress
- contact.metrics.time-framecustomer-notification
- · contact.multiple-valueattributes
- · contact.myhistory-defaulttime-filter-main
- contact.myhistory-displayedcolumns
- · contact.myhistory-displayed-
- contact.threading-ucsinteraction.enable
- contact.timeout-delay
- contact.ucsinteraction.<mediatype>.enable-create
- contact.ucsinteraction.<mediatype>.enable-lookup
- contact.ucsinteraction.<mediatype>.use-server-date
- dial-plan-rule-<name>
- · disaster-recovery.auto-restore
- disaster-recovery.disablelogin-errors
- disaster-recovery.enabled

- disaster-recovery.peer-site
- disaster-recovery.preferredsite
- disaster-recovery.restoreagent-state
- disaster-recovery.timeout
- disaster-recovery.wait-forsipphone-timeout
- display-format.acdqueue.name
- · display-format.agent-name
- · display-format.caller-name
- display-format.case-nameformat
- display-format.chat-agentname
- display-format.current-agentname
- display-format.customername-format
- display-format.interactioncallback-name
- display-format.interactionchat-name
- display-format.interactionemail-name
- display-format.interaction-imname
- display-format.interactionoutbound-pull-preview-name
- display-format.interactionoutbound-push-previewname
- display-format.interactionqueue.name
- display-format.interactionsms-name
- display-format.interactionvoice-name
- display-format.interactionworkitem-name
- display-format.routingpoint.name

- · editor.font-size-units
- email.attachment-downloadtimeout
- email.auto-answer
- · email.default-queue
- · email.forward-queue
- · email.from-addresses
- · email.html-format
- email.include-original-text-inreply
- · email.max-attachments-size
- email.move-inbound-to-inprogress-workbin-on-reply
- · email.outbound-queue
- · email.prompt-for-done
- email.pull-from-historyisenabled
- email.qa-review-dispositionsbusiness-attribute
- · email.quote-char
- · email.reply-format
- email.reply-prefix
- email.restricted-attachmentfile-types
- · email.ringing-bell
- · email.set-ownerid-on-send
- email.signature
- email.toast-information-key
- expression.email-address
- expression.phone-number
- expression.phonenumber.supported-characters
- expression.url
- gadget-statistics.displayedcall-center-statistics
- gadget-statistics.displayedkpis
- gadget-statistics.nb-taggedstats-per-page

- gadget-statistics.show
- gadget.window-title
- general.configuration-updatenotification
- · general.gad.attached-data
- general.non-unicodeconnection-encoding
- im.agent.prompt-color
- · im.agent.text-color
- · im.auto-answer
- · im.new-message-bell
- im.other-agent.prompt-color
- im.other-agent.text-color
- · im.prompt-for-end
- im.ringing-bell
- · im.system.text-color
- · im.time-stamp
- · im.toast-timeout
- interaction-bar.detailtooltip.max-height
- · interaction.case-data.content
- interaction.case-data.enableurl-preview
- interaction.case-data.formatbusiness-attribute
- interaction.case-data.framecolor
- interaction.case-data.headerforeground-color
- interaction.case-data.is-readonly-on-idle
- interaction.consult-user-data
- interaction.disposition.ismandatory
- interaction.disposition.isread-only-on-idle
- interaction.disposition.keyname
- · interaction.disposition.use-

- attached-data
- interaction.disposition.useconnection-id
- interaction.disposition.valuebusiness-attribute
- interaction.evaluate-realparty-for-agent
- interactionmanagement.availableinteraction-page-sizes
- interactionmanagement.filters
- interactionmanagement.interactionsfilter.displayed-columns
- interaction.override-optionkey
- · interaction.reject-route
- interaction.window.popuptopmost-z-order
- interaction.window.showcase-interaction-panel-button
- interaction.window.show-intaskbar
- · interaction.window-title
- interactions.window.allowstransparency-on-winos6
- sip-call
 intercommunication.chat.conference.invitetimeout
 keyboar
- intercommunication.chat.queue
- intercommunication.chat.routingbased-actions
- intercommunication.chat.routingbased-targets
- · intercommunication.email.queue
- intercommunication.email.routingbased-actions
- intercommunication.email.routingbased-targets
- intercommunication.im.routingbased-actions
- intercommunication.im.routingbased-targets

- intercommunication.im.routingpoints
- · intercommunication.sms.queue
- intercommunication.sms.routingbased-actions
- intercommunication.sms.routingbased-targets
- intercommunication.voice.routingbased-actions
- intercommunication.voice.routingbased-targets
- intercommunication.voice.routing- points
- intercommunication.<mediatype>.queue
- intercommunication.<mediatype>.routing-based-actions
- intercommunication.<mediatype>.routing-based-targets
- keyboard.hotkey.agent-notready
- keyboard.hotkey.agent-notready-with-reason.<actioncode>
- keyboard.hotkey.agent-ready
- keyboard.hotkey.decreasemicrophone-volume-activesip-call
- keyboard.hotkey.decreasespeaker-volume-active-sipcall
- keyboard.hotkey.hold-activecall
- keyboard.hotkey.increasemicrophone-volume-activesip-call
- keyboard.hotkey.increasespeaker-volume-active-sipcall
- keyboard.hotkey.mutemicrophone-active-sip-call
- keyboard.hotkey.mutespeaker-active-sip-call
- · keyboard.hotkey.release-

- active-call
- keyboard.hotkey.toaster.accept
- · keyboard.hotkey.toaster.decline
- keyboard.shortcut.action.help
- keyboard.shortcut.contact.assigncontact
- keyboard.shortcut.contact.reset
- keyboard.shortcut.contact.save
- keyboard.shortcut.interaction.chat.conferer
- · keyboard.shortcut.interaction.chat.end
- keyboard.shortcut.interaction.chat.transfer
- keyboard.shortcut.interaction.consult
- keyboard.shortcut.interaction.email.addattachments
- · keyboard.shortcut.interaction.email.delete
- · keyboard.shortcut.interaction.email.forward
- keyboard.shortcut.interaction.email.interim send
- keyboard.shortcut.interaction.email.print
- keyboard.shortcut.interaction.email.reply
- keyboard.shortcut.interaction.email.replyall
- keyboard.shortcut.interaction.email.save
- keyboard.shortcut.interaction.email.savein-workbin
- keyboard.shortcut.interaction.email.send
- keyboard.shortcut.interaction.email.transfe
- keyboard.shortcut.interaction.im.release
- keyboard.shortcut.interaction.markdone
- keyboard.shortcut.interaction.preview.callrecord
- keyboard.shortcut.interaction.preview.cancerecord
- keyboard.shortcut.interaction.preview.mark done
- keyboard.shortcut.interaction.preview.mark done-get-next
- keyboard.shortcut.interaction.preview.rejec record

- keyboard.shortcut.interaction.sms.deketyeboard.shortcut.teamlead.voice.balogeiim.im.available-queues
- keyboard.shortcut.interaction.sms.trakes/board.shortcut.teamlead.voice.coaccimicm.can-unactivate-
- channel keyboard.shortcut.interaction.voice.aksyktoard.shortcut.teamlead.voice.monitor login.im.is-auto-ready keyboard.shortcut.teamlead.voice.stop
- keyboard.shortcut.interaction.voice.hortonitoring call

keyboard.shortcut.toaster.accept

- keyboard.shortcut.interaction.voice.pause-• keyboard.shortcut.toaster.decline
- keyboard.shortcut.interaction.voice.reconfiectayed-kpis · kpi.refresh-time
- keyboard.shortcut.interaction.voice, release
 kpi.show-agent-groups
- license.lrm-enabled
 keyboard.shortcut.interaction.voice.resume-log.default-filter-type
- keyboard.shortcut.interaction.voice.resuraseDK recording-call • log.expire
- keyboard.shortcut.interaction.voice.single-sten-conference
 log.filter-data.<keyName> step-conference
- keyboard.shortcut.interaction.voice.slagienax-age step-transfer log.PSDK
- keyboard.shortcut.interaction.voice.start-log.segment recording-call
- keyboard.shortcut.interaction.voice.stoprecording-call · log.verbose
- keyboard.shortcut.interaction.webcallbark.cadt.auto-not-readycontact reason
- keyboard.shortcut.interaction.webcallbank.cnatkcan-unactivatedone channel
- kevboard.shortcut.interaction.workiteringmovert.is-auto-ready to-workbin
- · login.default-place keyboard.shortcut.interaction.workitem.transfer
- · keyboard.shortcut.state.logout
- keyboard.shortcut.state.notready
- keyboard.shortcut.state.notready-after-call-work
- · keyboard.shortcut.state.ready
- login.email.auto-not-ready-
- · login.email.can-unactivatechannel
- · login.email.is-auto-ready
- login.enable-login-withoutchannel
- keyboard.shortcut.teamlead.chat.barpgin.enable-place-completion
- keyboard.shortcut.teamlead.chat.stopogin.enable-same-agentmonitoring place
- keyboard.shortcut.teamlead.stop- login.im.auto-not-readymonitoring
 - reason

- · login.im.prompt-agent-login-
- login.im.prompt-dn-password
- login.im.prompt-queue
- login.prompt-place
- · login.sip-cluster.phonenumber
- · login.sip-cluster.store-recentphone-number
- login.sms.auto-not-readyreason
- · login.sms.can-unactivatechannel
- login.sms.is-auto-ready
- login.store-recent-place
- login.voice.auto-not-readyreason
- login.voice.available-queues
- login.voice.can-unactivatechannel
- · login.voice.force-relogin
- · login.voice.is-auto-ready
- · login.voice.prompt-agentlogin-id
- login.voice.prompt-dn-lessphone-number
- login.voice.prompt-dnpassword
- login.voice.prompt-queue
- · login.webcallback.auto-notready-reason
- · login.webcallback.canunactivate-channel
- login.webcallback.is-autoready
- login.workmode

- login.<media-type>.auto-notready-reason
- login.<media-type>.canunactivate-channel
- login.<media-type>.is-autoready
- · logout.enable-exit-on-logofferror
- · main-window.dockable
- · main-window.window-title
- openmedia.bundle.sms
- openmedia.workitemchannels
- options.record-option-locallyonly
- · outbound.call-resultautomatically-selected
- · outbound.call-result-values
- · outbound-callback.ringing-
- outbound.campaign-staletimeout
- · outbound.fields.floatseparator-in-db
- · outbound.push-preview.autoanswer
- outbound.pushpreview.media-types
- outbound.push-preview.usecombined-channel
- · outbound.recordinformation.frame-color
- · outbound.recordinformation.headerforeground-color
- · outbound.sound.campaignupdated
- outbound.treatment-mode
- presence.evaluate-presence
- printing.use-print-preview
- security.disable-rbac

- security.enable-debuginformation
- security.inactivity-not-readyreason
- · security.inactivity-set-agentnot-ready
- security.inactivity-timeout
- sip-cluster.data-center**locations**
- · sip-cluster.reconnect-timeout
- sipendpoint.audio.incoming.use agc
- · sipendpoint.authenticatewith-dn-password
- sipendpoint.exit-on-voicelogoff

- sipendpoint.genesyslab.system.log level Er
- sipendpoint.genesyslab.system.log level Jit
- · sipendpoint.genesyslab.system.log_level_Li
 - sipendpoint.genesyslab.system.log_level_M
- sipendpoint.genesyslab.system.log level Pr
- sipendpoint.genesyslab.system.log_level_R^{*}
- sipendpoint.genesyslab.system.log_level_Se
- sipendpoint.genesyslab.system.log_level_St
- sipendpoint.audio.headset.audio_in_agc_enabled
 - sipendpoint.genesyslab.system.log level Tr
 - sipendpoint.genesyslab.system.log_level_U **Devices**
 - sipendpoint.genesyslab.system.log level U
 - sipendpoint.genesyslab.system.log_level_Vo
- sipendpoint.genesyslab.beeptone.beeptone timeout
- sipendpoint.genesyslab.beeptone.enable_beeptone
- sipendpoint.genesyslab.beeptone.playedfigured-usage
- sipendpoint.genesyslab.control.auto_answerpoint.headset-
- sipendpoint.genesyslab.device.audio in plugged-set-ready
- sipendpoint.genesyslab.device.audio sipendpoint.headset-ันทั่งในgged.not-ready-reason
- sipendpoint.genesyslab.device.error_code when headset na sipendpoint.headset-
- sipendpoint.genesyslab.device.headsetnplargged-set-not-ready
- sipendpoint.genesyslab.device.manualpændipoideviridesattenfigtune
- sipendpoint.genesyslab.device.rejectsiqaelnulubeinthieitelsetempt-timer
- sipendpoint.genesyslab.device.use
 heipderet
 point.log.verbose
- sipendpoint.genesyslab.dtmf.pause stipenstppindtppfoxies.proxy0.reregister_in_se
- sipendpoint.genesyslab.dtmf.play_locailyendpoint.proxies.proxy1.reregister_in_se
- sipendpoint.genesyslab.system.logelesipetnAdpatinatct@basimevolume-
- settings-between-sessions
 sipendpoint.genesyslab.system.log_level_Audio
- sipendpoint.genesyslab.system.log_level_Auto

 Configuration Configuration sipendpoint.rtp.2833.hold_over_time_in_ms
- sipendpoint.genesyslab.system.log•lesipetr@pMint.rtp.2833.packet time in ms
- sipendpoint.genesyslab.system.log•lesipetr@profertertpin2g33.payload number
- sipendpoint.genesyslab.system.log•lesipelr@proteststp.inactivity.timer_enabled
- sipendpoint.genesyslab.system.logelesipet@int.sbc-registeraddress

- sipendpoint.sbc-registeraddress.peer
- · sipendpoint.sbc-register-port
- sipendpoint.sbc-registerport.peer
- standard-response.categories
- standard-response.defaultsearch-type
- standard-response.enableusage-feedback
- sipendpoint.system.diagnostics.enabktdndgirdgresponse.languages
- sipendpoint.system.diagnostics.log•lestehdard-
- response.suggested-• sipendpoint.system.dtmf.force_send_ipesponses-min-relevancy
- sipendpoint.system.dtmf.minimum_rfs2833;playstinged-statistics
- sipendpoint.system.indialog_notify.enable_indialognotify
- sipendpoint.system.network.dtx_enabledistics.refresh-time
- sipendpoint.system.qos.audio
- sipendpoint.transportprotocol
- · statistics.routing-points
- · system-tray.tooltip
- teamcommunicator.add-• sipendpoint.tuning.mixer.allow_masterevelytemes
- sms.agent.prompt-color
- · sms.agent.text-color
- sms.auto-answer
- · sms.client.prompt-color
- sms.client.text-color
- · sms.default-queue
- sms.from-numbers-businessattribute
- · sms.max-message-number
- · sms.other-agent.prompt-color
- sms.other-agent.text-color
- · sms.outbound-queue
- · sms.prompt-for-done
- sms.ringing-bell
- sms.subject-max-chars
- · sms.time-stamp
- sms.transcript-time-frame
- sounds.preloadfiles
- spellchecker.corporatedictionary
- spellchecker.corporatedictionary-file

- teamcommunicator.alwaysclear-textbox-on-newinteraction
- teamcommunicator.contactfavorite-fields
- teamcommunicator.corporatefavorites
- teamcommunicator.corporatefavorites-file
- teamcommunicator.customfavorite-fields
- teamcommunicator.internalfavorite-fields
- teamcommunicator.list-filtershowing
- teamcommunicator.liststatus-reachable
- teamcommunicator.load-atstartup
- teamcommunicator.maxsuggestion-size
- teamcommunicator.recentmax-records
- teamcommunicator.requeststart-timer
- teamlead.agent-

- status.enabled-agent-groupsecurity-mode
- teamlead.monitoring-scope
- · toast.case-data.content
- toast.case-data.formatbusiness-attribute
- · toast.window-title
- views.CaseContactRegion.activateorder
- · views.CaseContactRegion.order
- views.CaseViewSideButtonRegion.order
- views.ContactInfoHistoryMultiRegion.activa order
- views.ContactInfoHistoryMultiRegion.order
- views.ContactTabBottomHistoryMultiRegion order
- views.ContactTabBottomHistoryMultiRegion
- views.InteractionDetailsRegion.activateorder
- · views.InteractionDetailsRegion.order
- views.ToolbarWorkplaceRegion.activateorder
- views.ToolbarWorkplaceRegion.order
- views.ToolbarWorksheetButtonRegion.order
- views.WorkbinsTabBottomHistoryMultiRegio order
- · views.WorkbinsTabBottomHistoryMultiRegio
- voice.auto-answer
- voice.dtmf-inactivity-typingtimeout
- voice.enable-init-conference
- voice.enable-make-callconsultation
- voice.mark-done-on-release
- voice.one-step-trsf-mode
- voice.prompt-for-end
- · voice.ringing-bell
- · webcallback.auto-answer
- webcallback.auto-dial

- webcallback.callbackinformation.content
- webcallback.callbackinformation.frame-color
- webcallback.callbackinformation.headerforeground-color
- webcallback.complete-queue
- webcallback.park-queue
- webcallback.reschedulequeue

- webcallback.ringing-bell
- webproxy.address
- webproxy.password
- webproxy.username
- · workbin.email.draft
- workbin.email.draft.displayedcolumns
- workbin.email.in-progress
- workbin.email.inprogress.displayed-columns

- workbin.<mediatype>.<workbin-nickname>
- workbin.<mediatype>.<workbinnickname>.displayedcolumns
- workbin.<media-type>.inprogress
- workbin.<media-type>.inprogress.displayed-columns

For information about how to use these options to configure Genesys Web Services functionality and behavior, refer to the *Workspace Desktop Edition Deployment Guide*.

Tip

The following descriptions were generated by dynamic query and include cached results that may be up to one day old. Click here to refresh the query.

<media-type>.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specify whether a specific workitem interaction is automatically accepted when a Interaction Server Invite event is received. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

<media-type>.prompt-for-done

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies if the application prompts a confirmation message when a user clicks the 'done' button. This option is only available for interaction open media. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

<media-type>.pull-from-history-isenabled

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediately.

Specifies whether it is possible to pull an interaction of the specified media type from Contact History. This option is applicable only if at least one of the following privileges has been granted to the agent: "Contact - Can Pull From Queue", "Contact - Can Pull Interactions In Shared Workbins", "Contact - Can Pull Interactions In Workbins Not Owned By The User".

Before enabling this function for a given workitem media type, ensure with your plug-in vendor that this feature is correctly supported.

>> Back to Top

<media-type>.ringing-bell

Default Value: Sounds\Ring.mp3

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the path of the sound file that is played when interaction of type <media-type> is ringing.

For example: "Sounds\Ring.mp3

>> Back to Top

<media-type>.toast-information-key

Default Value: Subject

Valid Values: Any valid attached data key name. **Changes Take Effect:** At the next interaction.

Specifies whether the information area is displayed in the specified workitem channel interaction notification. This option provides the name of the attached data key that contains the information. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

accessibility.agent-state-change-bell

Default Value:

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the agent state change sound-configuration string. For example: "Sounds\bell.mp3

>> Back to Top

accessibility.interaction-state-change-bell

Default Value:

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the interaction state change sound-configuration string. For example: "Sounds\chord.mp3

>> Back to Top

accessibility.visual-impairment-profile

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the profile for visually impaired users is active. This option enables more interface elements to be focusable (accessible from keyboard navigation and mouse-over) so that they can be navigated from Screen Reader applications.

>> Back to Top

accessibility.warning-message-bell

Default Value:

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the warning message sound-configuration string. For example: "Sounds\warning.mp3

>> Back to Top

active-recording.screen-recorder-executable

Default Value:

Valid Values: A valid command line string. **Changes Take Effect:** At next application start.

The path to the executable of the screen recorder that must be installed on the same workstation as Interaction Workspace.

>> Back to Top

active-recording.screen-recorder-host

Default Value:

Valid Values: A valid command line string. **Changes Take Effect:** At next application start.

The name of the central host of the Screen Recorder database to which the local screen recorder application connects.

>> Back to Top

active-recording.voice.recorder-uri

Default Value:

Valid Values: A string in format sip:host:port **Changes Take Effect:** At application restart.

Specifies the URI of the voice recorder. Use this option if you will use a voice recorder other than the one that is configured in GVP.

>> Back to Top

active-recording.voice.recording-type

Default Value: NETANN

Valid Values: NETANN or MSML

Changes Take Effect: At application restart.

Specifies the type of voice recording to be used. NETANN and MSML are supported.

- NETANN: Legacy call recording using NETANN can be provided by Stream Manager or Genesys Media Server.
- MSML (Active Recording): Call recording through Media Server Markup Language (MSML) is provided through Genesys Media Server only. For details about this type of recording, refer to "Call Recording—MSML-based" in the SIP Server Deployment Guide.

agent-status.enabled-actions-by-channel

Default Value: Ready, NotReady, NotReady Reason, After Call Work, Dnd, Logon, Log Off

Valid Values: Comma-separated list of action names from the following list: Ready, NotReady,

NotReadyReason, AfterCallWork, Dnd, LogOn, LogOff.

Changes Take Effect: Immediately.

Defines the available agent state actions in "My Channels" contextual menu. The actions are displayed in the order in which they appear in the list.

>> Back to Top

agent-status.enabled-actions-global

Default Value: Ready, NotReady, NotReadyReason, After Call Work, Dnd, Logon, Log Off **Valid Values:** Ready, NotReady, Dnd, After Call Work, NotReady Reason, Log Off

Changes Take Effect: Immediately.

Defines the available agent states in the global Status menu. The agent state commands are displayed in the order in which they appear in the list.

>> Back to Top

agent-status.not-ready-reasons

Default Value:

Valid Values: Comma-separated list of Action Code names of type "Not Ready"; empty means all not

ready action codes are considered **Changes Take Effect:** Immediately.

Defines the available reasons in the Agent Status menus (global an My Channels). The reason commands are displayed in the order in which they appear in the list.

>> Back to Top

alert.timeout

Default Value: 10

Valid Values: An integer value greater than or equal to 0.

Changes Take Effect: When the application is started or restarted.

Specifies the duration, in seconds, of the contextual warning messages that are displayed in the windows of the application. The value 0 means that message notifications are not automatically closed and must be closed manually.

application.available-layouts

Default Value: main-window,gadget **Valid Values:** main-window,gadget

Changes Take Effect: When the application is started or restarted.

Specifies which views are available, and which view is displayed on login. If the option is empty, the Main window and the Gadget are not accessible, and Interaction Worskspace starts in the system tray. The order defines the default view on initial login.

>> Back to Top

broadcast.color.high-priority

Default Value:

1. FF663399

Valid Values: Valid Hexidecial (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the border of the Message view frames for high priority messages. Examples: #FFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color.

>> Back to Top

broadcast.color.important-priority

Default Value:

1. FFFF0000

Valid Values: Valid Hexidecial (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the border of the Message view frames for important priority messages. Examples: #FFFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color.

>> Back to Top

broadcast.color.low-priority

Default Value:

1. FF999999

Valid Values: Valid Hexidecial (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the border of the Message view frames for low priority messages. Examples: #FFFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color.

>> Back to Top

broadcast.color.minimal-priority

Default Value:

1. FFCCCCCC

Valid Values: Valid Hexidecial (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the border of the Message view frames for minimal priority messages. Examples: #FFFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color.

>> Back to Top

broadcast.color.normal-priority

Default Value:

1. FFDFE8F6

Valid Values: Valid Hexidecial (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the border of the Message view frames for normal priority messages. Examples: #FFFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color.

>> Back to Top

broadcast.displayed-columns

Default Value: MessageTypeIcon, MessageType, Sender, Subject, Priority, Date, Topic

Valid Values: A comma-separated list of valid object types from the following: MessageTypeIcon,

MessageType, Sender, Subject, Priority, Date, Topic, Id, any key of custom data

Changes Take Effect: When the application is started or restarted.

Specifies the names of the columns that are displayed in the MyMessage view.

broadcast.dn

Default Value:

Valid Values: A comma-separated list of DN and switch names in the following format:

dn name@switch

Changes Take Effect: When the application is started or restarted.

Specifies the list of Communication DNs that are used for Broadcasting. Interaction Workspace registers to the specified DNs when a corresponding TServer connection is configured in the application and then considers all messages sent on these connections.

>> Back to Top

broadcast.mark-read-timeout

Default Value: 5

Valid Values: from 0 to MAXINT

Changes Take Effect: When the application is started or restarted.

Specifies the duration, in seconds, that the broadcast message tooltip is displayed before the message is marked as read. If the duration is 0, this feature is not applied; then, the message is not considered to be read until the agent selects it for reading.

>> Back to Top

broadcast.message-content

Default Value: Subject, Sender, Priority, Date, Topic, Body

Valid Values: A comma-separated list of valid object types from the following: Subject, Sender,

Priority, Date, Topic, Body, MessageType, Id, any key of custom data

Changes Take Effect: At the next message.

Specifies the attributes that are displayed in the Broadcast Message window and in the item tooltip of the MyMessages view.

>> Back to Top

broadcast.preview-timeout

Default Value: 10

Valid Values: from 0 to MAXINT

Changes Take Effect: At the next message.

Defines the duration, in seconds, that the preview of the broadcast message is displayed in the

Information area of the Main Window. The value 0 means the Preview is not displayed.

>> Back to Top

broadcast.sound.high-priority

Default Value:

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the sound configuration string of messages of type important. For example: "Sounds\ HighMessage.mp3

>> Back to Top

broadcast.sound.important-priority

Default Value:

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the sound-configuration string of a message of type important. For example: "Sounds\ ImportantMessage.mp3

>> Back to Top

broadcast.sound.low-priority

Default Value:

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the sound configuration string of messages of type important. For example: "Sounds\ LowMessage.mp3

>> Back to Top

broadcast.sound.minimal-priority

Default Value:

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the sound configuration string of messages of type important. For example: "Sounds\ MinimalMessage.mp3

broadcast.sound.normal-priority

Default Value:

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the sound configuration string of messages of type important. For example: "Sounds\ NormalMessage.mp3

>> Back to Top

broadcast.subscribed.topics

Default Value: All,\$Agent\$,\$AgentGroup\$ **Valid Values:** A comma-separated list of string

Changes Take Effect: When the application is started or restarted.

Specifies the list of topics to which agents can be subscribed. The key \$Agent\$ defines the username of the agent. The key \$AgentGroup\$ defines all agent groups of which the agent is a member.

>> Back to Top

broadcast.toast-summary

Default Value: Sender, Priority, Subject, Few Words

Valid Values: A comma-separated of valid object types from the following: Sender, Priority, Subject,

FewWords, Topic, MessageType, any key of custom **Changes Take Effect:** At the next message.

Determines the attributes display in the broadcast message notification.

>> Back to Top

broadcast.value-business-attribute

Default Value:

Valid Values: A valid Business Attribute name.

Changes Take Effect: When the application is started or restarted.

A character string that specifies the name of the Business Attribute that contains the Attribute Values that are used as an enumerated value for custom attribute of message.

>> Back to Top

case-data.float-separator

Default Value:

Valid Values: A valid float separator. Typical float separators are: '.',',','\'

Changes Take Effect: Immediately.

Specifies the float separator that is used for Case data. This option should be used when the decimal symbol in the regional settings of the agent workstation is different from the one provided by the database.

>> Back to Top

channel-information.window-title

Default Value: \$Window.Title\$

Valid Values:

\$Window.Title\$,\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$

Changes Take Effect: Immediately.

Defines the title of the window that prompts for place and media login data that appears in the Windows Task Bar by specifying a string that contains the following field codes:\$Window.Title\$,\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$. If all field codes are empty, the following field codes are used: \$Window.Title\$.

>> Back to Top

chat.agent.prompt-color

Default Value:

1. FF385078

Valid Values: Valid Hexadecimal (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the prompt for the messages entered by the agent in the Chat view.

>> Back to Top

chat.agent.text-color

Default Value:

1. FF385078

Valid Values: Valid Hexadecimal (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the text of the messages entered by the agent in the Chat view.

>> Back to Top

chat.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether a chat interaction is automatically accepted and joined when a Interaction Server Invite event is received. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

chat.client.prompt-color

Default Value:

1. FF166FFF

Valid Values: Valid Hexadecimal (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the text of the messages entered by the target client in the Chat view.

>> Back to Top

chat.client.text-color

Default Value:

1. FF166FFF

Valid Values: Valid Hexadecimal (HTML) color code

Changes Take Effect: Immediately.

Color of the client text in the Chat view. The HTML format is used to set the value. I.e.: #FFFF0000 for a red color.

>> Back to Top

chat.enable-auto-disconnect

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the chat session is automatically disconnected if the agent is the last party remaining in the chat session.

>> Back to Top

chat.new-message-bell

Default Value:

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: Immediately

Specifies the configuration string for the new Chat Message sound. For example: "Sounds\bell.mp3

>> Back to Top

chat.nickname

Default Value: \$Agent.UserName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list:

\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.FullName\$,\$Agent.EmployeeId\$,\$AttachedData

(Y: attached data key name).

Changes Take Effect: At the next interaction.

Specifies the nickname that is used to join the chat session (presented to the customer) by a string that can contain regular characters and the following field codes:

\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.FullName\$,\$Agent.EmployeeId\$,\$AttachedData (Y: attached data key name).

This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

chat.other-agent.prompt-color

Default Value:

1. FFD88000

Valid Values: Valid Hexadecimal (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the text of the messages entered by the target agent in the Chat view.

>> Back to Top

chat.other-agent.text-color

Default Value:

1. FFD88000

Valid Values: Valid Hexadecimal (HTML) color code

Changes Take Effect: Immediately.

Color of the other agent text in the Chat view. The HTML format is used to set the value. I.e.: #FFFF0000 for a red color.

>> Back to Top

chat.pending-response-to-customer

Default Value: 30,50

Valid Values: A comma-separated list value: warning time, maximum time

Changes Take Effect: At the next interaction.

Defines two alarm thresholds, in seconds, that warn agents that they have a pending response to a chat from a customer. Three levels are displayed: before the warning time, between the warning time and the maximum time, and after the maximum time.

>> Back to Top

chat.prompt-for-end

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies if application prompts a confirmation message when a user clicks the 'end' button. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

chat.reconnect-attempts

Default Value: 5

Valid Values: from 0 to MAXINT

Changes Take Effect: At the next interaction.

Defines the number of reconnection attemps to the chat session to make in the case of a connection loss.

>> Back to Top

chat.reconnect-timeout

Default Value: 5

Valid Values: from 0 to MAXINT

Changes Take Effect: At the next interaction.

Specifies the duration, in seconds, between each attemp to reconnect to the chat session in the case of a connection loss.

>> Back to Top

chat.ringing-bell

Default Value: Sounds\Ring.mp3

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the path of the sound file that is played when Chat interaction is ringing. For example:

"Sounds\Ring.mp3

>> Back to Top

chat.system.text-color

Default Value:

1. FF8C8C8C

Valid Values: Valid Hexadecimal (HTML) color code.

Changes Take Effect: Immediately.

Specifies the color of the text for system messages in the Chat view.

>> Back to Top

chat.time-stamp

Default Value: true

Valid Values: true, false

Changes Take Effect: Immediately.

Specifies whether the time stamp is displayed in the Chat transcript area.

>> Back to Top

chat.toast-information-key

Default Value: Subject

Valid Values:

Changes Take Effect: At the next interaction.

Specifies whether the Information area is displayed in the Chat interaction notification. The option specifies the name of the attached data key that contains the information. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

chat.typing-isenabled

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether typing notification is enabled. It should be disabled for Chat Server lower than 8.0.1.

>> Back to Top

chat.typing-timeout

Default Value: 10

Valid Values: from 0 to MAXINT

Changes Take Effect: At the next interaction.

Defines the duration, in seconds, that the typing notification is displayed after the last keystroke and before the agent or contact sends their message.

>> Back to Top

contact.available-directory-page-sizes

Default Value: 5,10,25,50

Valid Values: A comma-separated list of numbers that define the number of rows per result page

from which the agent can make selections.

Changes Take Effect: When the application is started or restarted.

The possible values for number of rows per page in the contact directory search result view.

>> Back to Top

contact.cache-timeout-delay

Default Value: 600

Valid Values: An integer from 1 through 3600.

Changes Take Effect: When the application is started or restarted.

The delay, in seconds, before the cache of the result of a Universal Contact Server request is cleared.

>> Back to Top

contact.date-search-types

Default Value: On.OnOrAfter.Before

Valid Values: Select at least one from the list.

Changes Take Effect: When the application is started or restarted.

The list of search types that are available for the agent to use to search the contact database by date.

>> Back to Top

contact.default-directory-page-size

Default Value: 10

Valid Values: An integer from 1 through 50.

Changes Take Effect: When the application is started or restarted.

The default value for the number of rows per page in the contact directory search result view. The value must be defined in the option contact.available-directory-page-size

>> Back to Top

contact.directory-advanced-default

Default Value: LastName, Phone Number

Valid Values: A comma-separated value list of Attribute Value names that correspond to searchable

contact field names.

Changes Take Effect: When the application is started or restarted.

The list of Contact fields that can be used in an advanced search.

>> Back to Top

contact.directory-default-mode

Default Value: ListView

Valid Values: A value from the following list: ListView, GridView

Changes Take Effect: Immediately.

Specifies which view of the Contact Directory is displayed by default.

- · ListView: Quicker search performance and tokenized search items, but no sort on the result.
- GridView: Results are sortable result, but the search is less powerful, and the search items are nontokenized.

>> Back to Top

contact.directory-displayed-columns

Default Value: LastName,FirstName,PhoneNumber,EmailAddress

Valid Values: A comma-separated value list of Attribute Value names corresponding to contact field

names, for example: LastName, FirstName, PhoneNumber, EmailAddress. **Changes Take Effect:** When the application is started or restarted.

The list of contact fields displayed when the results of a contact search is rendered.

>> Back to Top

contact.directory-permissions.<ContactAttributeName>

Default Value:

Valid Values: In a key, a valid searchable contact attribute name. In a value, a comma-separated list of strings applicable to the specified contact attribute.

Changes Take Effect: At the next contact search.

This option can be used as a template to specify a contact attribute name (in a key) and the associated values (in a value) that is used to restrict the access of specific agents to the contact directory.

>> Back to Top

contact.directory-search-attributes

Default Value: LastName,FirstName,PhoneNumber,EmailAddress

Valid Values: A comma-separated value list of Attribute Value names that correspond to searchable contact field names.

Changes Take Effect: When the application is started or restarted.

The list of Contact fields that can be used as search parameters

>> Back to Top

contact.directory-search-types

Default Value: contains, begins-with, is

Valid Values: Select at least one item from the list.

Changes Take Effect: When the application is started or restarted.

The list of search types that are available for the agent to use to search the contact database. Specifying the value contains may have a performace impact.

>> Back to Top

contact.displayed-attributes

Default Value: Title,FirstName,LastName,PhoneNumber,EmailAddress

Valid Values: A comma-separated value list of Attribute Value names that correspond to contact

field names, for example: LastName, FirstName, PhoneNumber, EmailAddress.

Changes Take Effect: When the application is started or restarted.

The list of Contact fields that are displayed when a Contact record is rendered.

>> Back to Top

contact.history-advanced-default

Default Value: Status, Start Date

Valid Values: A comma-separated value list of Contact History items to display in the interaction

view, for example: Status, StartDate

Changes Take Effect: When the application is started or restarted.

Defines the list of Contact History items that can be used in an advanced search.

>> Back to Top

contact.history-default-time-filter-main

Default Value: 1M

Valid Values: A value from the following list: All, 1M, 1W, 1D

Changes Take Effect: When the application is started or restarted, or at the next interaction.

Specifies which Time Filter is selected by default in the Contact History view when an agent accesses the main history data source.

- · All: all interactions from Main UCS Data Base.
- 1M: interactions from Main UCS Data Base that were created less than 1 month ago.
- 1W: interactions from Main UCS Data Base that were created less than 1 week ago.
- 1D: interactions from Main UCS Data Base that were created less than 1 day ago.

>> Back to Top

contact.history-displayed-columns

Default Value: Status, Subject, Start Date, End Date, Ownerld

Valid Values: A comma-separated value list of Contact History items to display in the interaction

view, for example: Status, Subject, StartDate, EndDate, Ownerld. **Changes Take Effect:** When the application is started or restarted.

Defines the list of Contact History items that are displayed in the interaction view.

>> Back to Top

contact.history-displayed-columns-treeview

Default Value: Subject, Status, Start Date

Valid Values: A comma-separated value list of Contact History items to display in the threaded view

of interactions, for example: Status, Subject, StartDate, EndDate, Ownerld.

Changes Take Effect: When the application is started or restarted.

Specifies the list of Contact History items that are displayed in the threaded view of interactions.

>> Back to Top

contact.history.filters-<attribute>

Default Value:

Valid Values: In a key, a valid searchable interaction attribute name. In a value, a comma-separated list of strings that are applicable to the specified interaction attribute. In the value, a comma-separated list of strings applicable to the specified interaction attribute. Use the \$All\$ and \$0ther\$ keywords to enable filtering on "all" or "other" values for this attribute.

Changes Take Effect: At the next contact search.

This option can be used as a template to specify an interaction attribute name (in a key) and the associated values (in a value) that is used to automatically filter the contact history.

contact.history.media-filters

Default Value: voice, email, chat, sms

Valid Values: A comma-separated value of valid media type names including (but not limited to): voice, email, chat, sms, facebook, facebooksession, facebookprivatemessage, twitter, twitterdirect,

workitem

Changes Take Effect: When the application is started or restarted.

Specifies the list of media types that can be used to filter the Contact History.

>> Back to Top

contact.history-search-attributes

Default Value: Status, Start Date, End Date, Subject

Valid Values: A comma-separated value list of Interaction attributes to display in the interaction

view, for example: Status, StartDate, EndDate, Subject

Changes Take Effect: When the application is started or restarted.

Defines the list of Interaction attributes that an agent can use to search the History database.

>> Back to Top

contact.last-called-agent.enable

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

When set to true, the the attributes LastCalledAgent_EmployeeID, LastCalledAgent_TimeStamp, LCA_EmplID_<interaction-media-type> and LCA_TimeStamp_<interaction-media-type> of the contact are set in contact profile when an interaction is presented to the Agent. This option can be overridden by a routing strategy as described in Deployment Guide. Note: This option is taken into account only when the option 'contact.last-called-agent.<media-type>.enable' is not defined for the applicable media type.

>> Back to Top

contact.last-called-agent.<media-type>.enable

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

This option can be used as a template to a create a media specific option. When set to true, the attributes LastCalledAgent_EmployeeID, LastCalledAgent_TimeStamp, LCA_EmplID_<interaction-media-type> and LCA_TimeStamp_<interaction-media-type> of the contact are set in contact profile when an interaction of the given media type is presented to the Agent.

This option can be overridden by a routing strategy as described in Deployment Guide.

Note: This option overwrites the contact.last-called-agent.enable option.

Use the 'voice-campaign' media-type to define the lookup behavior in the context of outbound campaign interactions.

>> Back to Top

contact.lookup.enable

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Activates the Interaction Workspace features that rely on Universal Contact Server (UCS) for lookup contact when an interaction is presented to the Agent.

This option can be overridden by a routing strategy as described in Deployment Guide.

Note: This option is taken into account only when attached data 'IdentifyCreateContact' is not set in the interaction and the option 'contact.lookup.<media-type>.enable' is not defined for the applicable media type.

>> Back to Top

contact.lookup.enable-create-contact

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

When contact look-up is enabled in the context of the current interaction, this option specifies that the Universal Contact Server (UCS) can create a contact if the initial search can not find any existing contact

This option can be overridden by a routing strategy as described in Deployment Guide.

Note: This option is taken into account only when attached data 'IdentifyCreateContact' is not set in the interaction and the option 'contact.lookup.<media-type>.enable-create-contact' is not defined for the applicable media type.

>> Back to Top

contact.lookup.<media-type>.enable

Default Value: true **Valid Values:** true,false

Changes Take Effect: Immediately.

Activates the Interaction Workspace features that rely on Universal Contact Server (UCS) for contact lookup when an interaction of the given media type is presented to the Agent.

This option can be overridden by a routing strategy as described in Deployment Guide.

Note: This option overwrites the contact.lookup.enable option. It is not taken into account when the attached data 'IdentifyCreateContact' is set in the interaction.

Use the 'voice-campaign' media-type to define the lookup behavior in the context of outbound campaign interactions.

>> Back to Top

contact.lookup.<media-type>.enable-create-contact

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

When contact lookup is enabled in the context of the current interaction, this option specifies that the Universal Contact Server (UCS) can create a contact if the initial search cannot find any existing contact.

This option can be overridden by a routing strategy as described in Deployment Guide. Note: This option overwrites the contact.lookup.enable-create-contact option. It is not taken into account when the attached data 'IdentifyCreateContact' is set in the interaction. Use the 'voice-campaign' media-type to define the lookup and create behavior in the context of outbound campaign interactions.

>> Back to Top

contact.mandatory-attributes

Default Value: FirstName, LastName

Valid Values: A comma-separated value list of Attribute Value names that correspond to contact

field names, for example: LastName, FirstName, PhoneNumber, EmailAddress.

Changes Take Effect: When the application is started or restarted.

The list of Contact fields that must be completed for a contact.

>> Back to Top

contact.metrics.enable-interactions-in-progress

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Activates the Interaction Workspace features that display the number of eServices interaction that are in progress in the current contact history.

contact.metrics.time-frame-customer-notification

Default Value: 1

Valid Values: An integer value meaning a number of days. If set to 0, no metrics area .

Changes Take Effect: When the application is started or restarted.

Specifies the search timeframe, in days, from which existing in-progress interactions are to be reported. If the value is set to θ , the feature is disabled. If the value is set to a number that is greater than θ , the feature that displays in the interaction view the number of interactions that were sent or received by the contact for the specified number of days is activated.

>> Back to Top

contact.multiple-value-attributes

Default Value: EmailAddress,PhoneNumber

Valid Values: A comma separated value list of Attribute Value names that correspond to contact

field names.

Changes Take Effect: When the application is started or restarted.

A list of contact attributes that can support multiple values.

>> Back to Top

contact.myhistory-default-time-filter-main

Default Value: 1W

Valid Values: A value from the following list: All, 1M, 1W, 1D **Changes Take Effect:** When the application is started or restarted.

Specifies which Time Filter is selected by default in the My History view when an agent accesses the main history data source.

- · All: all interactions from Main UCS Data Base.
- 1M: interactions from Main UCS Data Base that were created less than 1 month ago.
- 1W: interactions from Main UCS Data Base that were created less than 1 week ago.
- 1D: interactions from Main UCS Data Base that were created less than 1 day ago.

>> Back to Top

contact.myhistory-displayed-columns

Default Value: Status, Subject, Start Date, End Date

Valid Values: A comma-separated value list of Contact History items to display in the interaction

view MyHistory, for example: Status, Subject, StartDate, EndDate. **Changes Take Effect:** When the application is started or restarted.

Defines the list of Contact History items that are displayed in MyHistory view.

>> Back to Top

contact.myhistory-displayed-columns-treeview

Default Value: Subject, Status, Start Date

Valid Values: A comma-separated value list of Contact History items to be displayed in the threaded

view of interactions in the MyHistory view, for example: Status, Subject, StartDate, EndDate,

Ownerld.

Changes Take Effect: When the application is started or restarted.

Specifies the list of Contact History items that are displayed in the threaded mode of the MyHistory view.

>> Back to Top

contact.threading-ucs-interaction.enable

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Activates the Interaction Workspace feature that associates interactions that are submitted during multi-channel contact communication, such as smssession, in threads in Universal Contact Server history.

>> Back to Top

contact.timeout-delay

Default Value: 60

Valid Values: An integer from 1 through 3600.

Changes Take Effect: When the application is started or restarted.

The delay, in seconds, before a UCS request times out.

>> Back to Top

contact.ucs-interaction.<media-type>.enable-create

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Activates the Interaction Workspace feature that generates the interaction history in Universal Contact Server (UCS) based on the inbound and outbound interactions of type <media-type> handled by Interaction Workspace.

Note: The option is forced to the value false for the media-types email, chat, and smssession, as Media Server is responsible for submitting those interactions in UCS.

This option can be overridden by a routing strategy as described in Deployment Guide.

This option replaces contact.ucs-interaction.enable

>> Back to Top

contact.ucs-interaction.<media-type>.enable-lookup

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Activates the Interaction Workspace feature that looks up the history of existing interactions of the given <media-type> in Universal Contact Server (UCS) in order to update their content and status according to live interaction lifecycle.

Note: For the media type 'email', this option is forced to 'true'.

This option can be overridden by a routing strategy as described in Deployment Guide

>> Back to Top

contact.ucs-interaction.<media-type>.use-server-date

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies for the specified <media-type> whether Interaction Workspace sets the start and end dates of interactions by using the time of the local agent workstation, or uses the date and time specified by Universal Contact Server (UCS) when it creates or updates an interaction record in UCS. Use this option as a template and modify its name by replacing the <media-type> by an actual media type defined in Management Framework.

Note: Depending on which UCS version you are using, setting this option to 'true' might generate an additional request to UCS when 'mark done' is set.

dial-plan-rule-<name>

Default Value:

Valid Values: pattern => digit translation # comment

Changes Take Effect: When the application is started or restarted.

Specifies a dial plan rule. This dial plan rules allows IW to transform the received digits into the actual digits that it uses to make the call. See description in deployment guide chapter XXX

Sample:

'5XXX=>4351707{\$DIGITS} # This rule matches any 4-digit number starting with 5 and translates it to the number 43517075XXX'

'5002=>43517075002 # This rule matches the dialed number 5002' and translates it to the number 43517075002'

>> Back to Top

disaster-recovery.auto-restore

Default Value: true **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted

Specifies whether agent should relogged in to the Preferred site as soon as it is avalable.

>> Back to Top

disaster-recovery.disable-login-errors

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether Interaction Workspace should display media voice login errors in the Login window.

>> Back to Top

disaster-recovery.enabled

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted

Specifies whether Disaster Recovery functionality is activated or not.

disaster-recovery.peer-site

Default Value: DRPeer

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore, @ and space

characters.

Changes Take Effect: When the application is started or restarted

Specifies the Site name to be used as secondary when connecting to any back-end server.

>> Back to Top

disaster-recovery.preferred-site

Default Value: Preferred

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore, @ and space

characters.

Changes Take Effect: When the application is started or restarted

Specifies the site name to be used as preferred when connecting to any back-end server.

>> Back to Top

disaster-recovery.restore-agent-state

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether Interaction Workspace should restore last agent state after logging on to the reserved site after the current site fails.

>> Back to Top

disaster-recovery.timeout

Default Value: 60

Valid Values: valid integer

Changes Take Effect: When the application is started or restarted

Specifies time in seconds to wait after Preferred Site HA Pair disconnection is detected before switching connection to the Disaster Recovery site.

disaster-recovery.wait-for-sipphone-timeout

Default Value: 0

Valid Values: valid integer 0 - means infinite

Changes Take Effect: When the application is started or restarted

Specifies time in seconds during which an agent should wait for SipEndpoint before a disaster is considered. A value of 0 means no limit.

>> Back to Top

display-format.acd-queue.name

Default Value: \$ACDQueue.Alias\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list: \$ACDQueue.Number\$,\$ACDQueue.Alias\$,\$ACDQueue.Location\$

Changes Take Effect: Immediately.

Defines the display format of ACD Queues by specifying a string that contains the following field codes: \$ACDQueue.Number\$,\$ACDQueue.Alias\$,\$ACDQueue.Location\$. If all field codes are empty, the following field codes are used: \$ACDQueue.Number\$@\$ACDQueue.Location\$.

>> Back to Top

display-format.agent-name

Default Value: \$Agent.FullName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

IIST:

\$Agent.FullName\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$.

Changes Take Effect: Immediately.

Defines the display format of other agents tby specifying a string that contains the following field codes: \$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$.

>> Back to Top

display-format.caller-name

Default Value: \$Contact.FirstName\$ \$Contact.LastName\$

Valid Values: A string that contains a composition of characters and field codes from the following list: \$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X:

name of contact attribute, Y: attached data key name).

Changes Take Effect: Immediately.

Defines the content of the voice interaction call history, based on the contact data items and

attached data types that are specified by a string that contains the following field codes: \$Interaction.CaseId\$,\$Interaction.Id\$, \$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X: name of contact attribute, Y: attached data key name). If all field codes are empty, the following field codes are used: \$Interaction.MainParty\$.

>> Back to Top

display-format.case-name-format

Default Value: \$Contact.FirstName\$ \$Contact.LastName\$

Valid Values: A string that contains a compilation of characters and field codes from the following list: \$Case.Id\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X: name of

contact attribute, Y: attached data key name)

Changes Take Effect: Immediately

Defines the display format of the case label that is currently used by the application by specifying a string that contains the following field codes:

\$Case.Id\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X: name of contact attribute, Y: attached data key name). This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

display-format.chat-agent-name

Default Value: \$ChatAgent.FullName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list:

\$ChatAgent.FullName\$,\$ChatAgent.Nickname\$,\$ChatAgent.UserName\$,\$ChatAgent.LastName\$,\$ChatAgent.FirstN

Changes Take Effect: Immediately.

Defines the display format of other agents by specifying a string that can contain regular characters as well as the following field codes: \$ChatAgent.FullName\$, \$ChatAgent.Nickname\$, \$ChatAgent.UserName\$, \$ChatAgent.LastName\$, \$ChatAgent.FirstName\$, \$ChatAgent.EmployeeId\$. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

display-format.current-agent-name

Default Value: \$Agent.FullName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

ist:

Agent.FullName,Agent.UserName,Agent.LastName,Agent.FirstName,Agent.Employeeld.

Changes Take Effect: Immediately.

Defines the display format of the agent that is currently using the application by specifying a string that contains the following field codes:

\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$. If all field codes are empty, the following field codes are used: \$Agent.UserName\$.

>> Back to Top

display-format.customer-name-format

Default Value: \$Contact.FirstName\$ \$Contact.LastName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list: \$Contact.X\$ (X: name of contact attribute)

Changes Take Effect: Immediately

Defines the display format of the customer label that is currently used by the application by specifying a string that contains the following field codes:\$Contact.X\$,\$AttachedData.Y\$ (X: name of contact attribute, Y: attached data key name). This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

display-format.interaction-callback-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$

Valid Values: A string that contains a compilation of characters and field codes from the following list:

\$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X: name of contact attribute, Y: attached data key name).

Changes Take Effect: Immediately.

If the media type of the main interaction is Web Callback, this option defines the format of the tooltip presented when hovering the 'case' tab at the top of the window. It is specified by a string that contains the field codes listed in the valid description.

>> Back to Top

display-format.interaction-chat-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$ **Valid Values:** A string that contains a compilation of characters and field codes from the following

\$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X: name of contact attribute, Y: attached data key name).

Changes Take Effect: Immediately.

If the media type of the main interaction is Chat, this option specifies the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by a string that contains the field codes listed in the valid description.

display-format.interaction-email-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list:

\$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X: name of contact attribute, Y: attached data key name).

Changes Take Effect: Immediately.

If the media type of the main interaction is E-Mail, this option defines the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by a string that contains the field codes listed in the valid description.

>> Back to Top

display-format.interaction-im-name

Default Value: \$Interaction.Type\$ \$Interaction.MainParty\$

Valid Values: A string that contains a compilation of characters and field codes from the following list:

\$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$AttachedData.Y\$(Y: attached data key name).

Changes Take Effect: Immediately.

If the media type of the main interaction is Instant Messaging, this option defines the format of the tooltip presented when hovering the 'case' tab at the top of the window. It is specified by a string that contains the field codes listed in the valid description.

>> Back to Top

display-format.interaction-outbound-pull-preview-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$ **Valid Values:** A string that contains a compilation of characters and field codes from the following

\$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X: name of contact attribute, Y: attached data key name).

Changes Take Effect: Immediately.

If the main interaction is an Outbound Pull Preview, this option defines the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by a string that contains the field codes listed in the valid description.

display-format.interaction-outbound-push-preview-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list:

\$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X: name of contact attribute, Y: attached data key name).

Changes Take Effect: Immediately.

If the main interaction is an Outbound Push Preview, this option defines the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by a string that contains the field codes listed in the valid description.

>> Back to Top

display-format.interaction-queue.name

Default Value: \$InteractionQueue.DisplayName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list: \$InteractionQueue.DisplayName\$,\$InteractionQueue.Name\$,\$InteractionQueue.Media\$

Changes Take Effect: When the application is started or restarted.

Defines the display format of Interaction Queues by specifying a string that contains the following field codes: \$InteractionQueue.Name\$,\$InteractionQueue.Media\$. If all field codes are empty, the following field codes are used: \$InteractionQueue.Media\$@\$InteractionQueue.Name\$.

>> Back to Top

display-format.interaction-sms-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$

Valid Values: A string that contains a compilation of characters and field codes from the following list:

\$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X: name of contact attribute, Y: attached data key name).

Changes Take Effect: Immediately.

If the media type of the main interaction is SMS, this option defines the format of the tooltip that is displayed when you place you mouse on the 'Case' tab at the top of the window. It is specified by a string that contains the field codes listed in the valid description.

>> Back to Top

display-format.interaction-voice-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list:

\$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X: name of contact attribute, Y: attached data key name).

Changes Take Effect: Immediately.

If the media type of the main interaction is Voice, this option defines the format of the tooltip presented when hovering the 'case' tab at the top of the window. It is specified by a string that contains the field codes listed in the valid description.

>> Back to Top

display-format.interaction-workitem-name

Default Value: \$Interaction.Type\$ (\$Contact.FirstName\$ \$Contact.LastName\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list:

\$Interaction.Type\$,\$Interaction.CaseId\$,\$Interaction.Id\$,\$Interaction.MainParty\$,\$Contact.X\$,\$AttachedData.Y\$ (X: name of contact attribute, Y: attached data key name).

Changes Take Effect: Immediately.

If the main interaction is a Workitem, this option defines the format of the tooltip that is displayed when you place your mouse pointer on the 'Case' tab at the top of the window. It is specified by a string that contains the field codes listed in the valid description.

>> Back to Top

display-format.routing-point.name

Default Value: \$RoutingPoint.Alias\$

Valid Values: A string that contains a compilation of characters and field codes from the following

list: \$RoutingPoint.Number\$,\$RoutingPoint.Alias\$,\$RoutingPoint.Location\$

Changes Take Effect: Immediately.

Defines the display format of Routing Points by specifying a string that contains the following field codes: \$RoutingPoint.Number\$,\$RoutingPoint.Alias\$,\$RoutingPoint.Location\$. If all field codes are empty, the following field codes are used: \$RoutingPoint.Number\$@\$RoutingPoint.Location\$.

>> Back to Top

editor.font-size-units

Default Value: point

Valid Values: A valid font size unit. The following units are supported: 'pixel', 'point'.

Changes Take Effect: At the next interaction.

Specifies whether points or pixels are used for the units of font size in the Rich Editor view for e-mail and other rich text based interactions.

email.attachment-download-timeout

Default Value: 20

Valid Values: An integer value between -1 and 3600.

Changes Take Effect: Immediately.

Defines the maximum duration, in seconds, of the download of an attachment. The value -1 means that there is no maximum time.

>> Back to Top

email.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether an e-mail interaction is automatically accepted when a Interaction Server Invite event is received. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

email.default-queue

Default Value:

Valid Values: A valid name of a Script of type Interaction Queue.

Changes Take Effect: At the next interaction.

Specifies the Interaction queue in which new or reply outbound e-mails are submitted.

>> Back to Top

email.forward-queue

Default Value:

Valid Values: Name of a valid Script of type Interaction Queue.

Changes Take Effect: Immediately.

Specifies the Interaction Queue in which inbound e-mails are placed when an agent forwards an inbound e-mail to an External Resource.

email.from-addresses

Default Value: \$EMAILSERVER\$

Valid Values: A valid Business Attribute name or \$EMAILSERVER\$.

Changes Take Effect: At the next interaction.

A character string that specifies the name of the Business Attribute that contains the Attribute Values that are used as available 'from addresses' of E-Mail interactions. The value \$EMAILSERVER\$ specifies that 'from addresses' are populated from the 'POP client' sections of Email Server applications.

>> Back to Top

email.html-format

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies the format of a new outbound e-mail. When set to 'true', new e-mail will be formatted in HTMI.

>> Back to Top

email.include-original-text-in-reply

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the text of the original incoming e-mail is included in the reply. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

email.max-attachments-size

Default Value: 0

Valid Values: Any valid positive integer. 0 means no maximum.

Changes Take Effect: At the next interaction.

The total maximum number of megabytes of files that agents can attach to an outbound e-mail interaction. An error message is displayed to the agent if the total number of megabytes for all attached files exceeds this value. The value 0 means that there is no restriction.

email.move-inbound-to-in-progress-workbin-on-reply

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

If the value of this option is set to 'true', when an agent replies or replies-all to an inbound e-mail interaction that is stored either in a personal in-progress or a shared workbin or in the Contact History, the inbound e-mail interaction is moved to the workbin that is configured as the in-progress workbin (refer to the 'workbin.email.in-progress' option).

>> Back to Top

email.outbound-queue

Default Value:

Valid Values: Name of a valid Script of type Interaction Queue.

Changes Take Effect: Immediately.

Specifies the Interaction Queue in which outbound e-mails are placed when agents click 'Send' or 'Send Interim'. This options is used only when Interaction Workflow does not set 'Queue for New Interactions' when it is routing Inbound E-mails to Agents.

>> Back to Top

email.prompt-for-done

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies if application prompts a confirmation message when a user clicks the 'done' button. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

email.pull-from-history-isenabled

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Specifies whether it is possible to pull an E-Mail interaction from Contact History. This option is applicable only if at least one of the following privileges has been granted to the agent: "Contact - Can Pull From Queue", "Contact - Can Pull Interactions In Shared Workbins", "Contact - Can Pull Interactions In Workbins Not Owned By The User".

email.qa-review-dispositions-business-attribute

Default Value:

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters. **Changes Take Effect:** At the next interaction.

A character string that specifies the name of the Business Attribute that contains the Attribute Values that are used to populate the E-Mail QA Review Dispositions drop-down button (on the reviewer's desktop). This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

email.quote-char

Default Value: >

Valid Values: Any valid character string. **Changes Take Effect:** Immediately.

For plain text formatted outbound e-mails, specifies the characters that are used to quote the contents of the inbound e-mail interaction in the outbound e-mail interaction body.

>> Back to Top

email.reply-format

Default Value: auto

Valid Values: Select a value from the following list: auto, html, plain-text.

Changes Take Effect: At the next interaction.

Specifies the format of an outbound e-mail reply.

auto: outbound e-mail reply format is the same as corresponding inbound e-mail.

html: outbound e-mail reply format is forced to html.

plain-text: outbound e-mail reply format is forced to plain text.

>> Back to Top

email.reply-prefix

Default Value: Re:<SPACE>

Valid Values: Any valid character string. **Changes Take Effect:** Immediately.

Modified: 8.5.116.10

Specifies the reply-prefix that should show up at the beginning of the subject of the outbound email reply edited by the agent.

- This option can be overridden by a routing strategy, as described in the Deployment Guide. The routing strategy can be used to identify the language of the email interaction and the reply prefix used by customers, and then to apply the same prefix to contact center replies in the email thread.
- Workspace removes the sequence of reply prefixes (occurrences of the current option and the default option value "Re: ") at the beginning of the subject and appends either the prefix specified by the routing strategy, the prefix specified by this option, or the default prefix if no prefix is configured.
- Agents can manually edit the subject prefix of a reply email interaction.

email.restricted-attachment-file-types

Default Value: No default value

Valid Values: A comma-separated list of file extensions that represent file types that are to be restricted. For example, use txt to restrict plain-text files, htm to restrict HTML files, and so on.

Changes Take Effect: At the next interaction.

Specifies the list of file extensions that represent file types that are to be prevented from being used as attachments. An error message is displayed to an agent who tries to attach a file that is not on the list of restricted types.

>> Back to Top

email.ringing-bell

Default Value: Sounds\Ring.mp3

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the path of the sound file that is played when E-Mail interaction is ringing. For example: "Sounds\Ring.mp3

>> Back to Top

email.set-ownerid-on-send

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the owner id of the interaction should be updated with the dbid of the agent when the e-mail is sent. This option can be overridden by a routing strategy as described in Deployment Guide.

email.signature

Default Value:

Valid Values: "file:" followed by the file path or "response:" followed by the reponse path in the SRL. **Changes Take Effect:** At the next interaction.

Specifies the type and the location of the signature template that is to be added to outbound e-mails. The value has two components that are separated by the character ':':

- 1) The type of signature template:
 - a) "file" for a file.
 - b) "response" for a response from the Standard Response Library.
- 2) The location of the signature template:
 - a) The file name and folder relative to the application folder. For example, "file:Signatures\Signature.txt".
 - b) The response name and full path of the parent category in the Standard Response Library. For example, "response:Signatures\Classic".

This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

email.toast-information-key

Default Value: Subject

Valid Values: Any valid character string. **Changes Take Effect:** At the next interaction.

Specifies whether the Information area is displayed in the E-Mail interaction notification. This option provides the name of the attached data key that contains the information. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

expression.email-address

Default Value: \w+([-+.]\w+)*@\w+([-.]\w+)*\.\w+([-.]\w+)*

Valid Values: A regular expression

Changes Take Effect: At the next interaction.

Specifies the regular expression to identify an e-mail address in the chat or SMS transcript. This option can be overridden by a routing strategy as described in Deployment Guide.

expression.phone-number

Default Value: (?:(?:[\+]?([\d]{1,3}(?:[]* **Valid Values:** A regular expression

Changes Take Effect: At the next interaction.

Specifies the regular expression to identify a phone number in the chat or SMS transcript. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

expression.phone-number.supported-characters

Default Value: 0123456789#*

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. All special characters that are valid

Windows file names.

Changes Take Effect: At the next interaction.

Specifies the characters that are considered when building a request to the T-Server that relies on a phone number. Any other characters from the original string coming from the User Interface are removed. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

expression.url

Default Value:

 $Domains)(?:com|org|net|gov|mil|biz|info|mobi|name|aero|jobs|museum|travel|[a-z]{2}))(?\#Port)(?::[\d]{1,5})?(?\#Directories)(?:(?:(?:(?:(?:/(?:[-\w~!$+].,=]|%[a-fA-F\w~!$+].,=])%[a-fA-F\w~!$+].$

 $d]\{2\})+)+|/)+)?(?\#Query)(?:(?:\(?:\[-\w\sim!\$+|.,*:])\%[a-fA-F\d]\{2\})+=(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{2\})+(?:\[-\w\sim!\$+|.,*:=])\%[a-fA-F\d]\{a-fA-F\$

 $d]{2})*)(?:&(?:[-\w\sim!$+|.,*:]]%[a-fA-F\d]{2})+=(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+(?:[-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim!$+|.,*:=]]%[a-fA-F\d]{2})+([-\w\sim$

 $d[\{2\}\})*)*)*(?#Anchor)(?:#(?:[-\w~!$+|.,*:=]|%[a-fA-F\d]{2})*)?$

Valid Values: A regular expression representing a URL.

Changes Take Effect: At the next interaction.

Specifies the regular expression to identify an URL in Case Information area. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

gadget-statistics.displayed-call-center-statistics

Default Value:

Valid Values: A comma-separated list of Statistic names.

Changes Take Effect: When the application is started or restarted.

Specifies the statistics that are displayed in the Statistic Gadget. The statistics name refers to the names of the Application Options Sections that define the statistics.

>> Back to Top

gadget-statistics.displayed-kpis

Default Value:

Valid Values: A comma-separated list of KPI names.

Changes Take Effect: When the application is started or restarted.

Specifies the KPIs that are displayed to the agent in the Statistic Gadget. The KPI names refer to the names of the Application Option Sections that are defining the KPIs.

>> Back to Top

gadget-statistics.nb-tagged-stats-per-page

Default Value: 5

Valid Values: an integer value

Changes Take Effect: When the application is started or restarted.

Defines the number of statistics that can be displayed in the non-scrolling region of the tagged statistics in the Statistics Gadget. If the number of statistics displayed is greater than this defined number, the remaining statistics are displayed in separate panels. The maximum value for this option is 10.

>> Back to Top

gadget-statistics.show

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Set to true to show the gadget of statistics.

>> Back to Top

gadget.window-title

Default Value: \$Window.Title\$

Valid Values:

\$Window.Title\$,\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$

Changes Take Effect: Immediately.

Defines the title of the window in which the Gadget is rendered by specifying a string that contains the following field

codes:\$Window.Title\$,\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.Firstl If all field codes are empty, the default string is \$Window.Title\$. This title is visible in the Task Bar only.

>> Back to Top

general.configuration-update-notification

Default Value: All

Valid Values: A comma-separated value list of items that are to be notifed, for example:

None, All, This Agent, This Application, This Tenant, Transactions, Persons, Skills, Agent Groups, Business Attributes, Business

Changes Take Effect: When the application is started or restarted.

Defines the list of configuration server objects that require notification when there is an update.

>> Back to Top

general.gad.attached-data

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether attached data is added to the equivalent of a Genesys Agent Desktop key. If routing is used, then Interaction Workspace adds the following keys:

GD_TransferTargetType,GD_TransferTargetId,...

>> Back to Top

general.non-unicode-connection-encoding

Default Value:

Valid Values: .Net Name of Code Page Identifier

Changes Take Effect: When the application is started or restarted

This option specifies the code page encoding that is used to connect to back-end servers that do not rely on Unicode communication (all back-end servers except UCS).

The possible values can be obtained from the ".Net Name" column of the Code Page Identifier that is defined in the following web page: http://msdn.microsoft.com/en-us/library/windows/desktop/dd317756(v=vs.85).aspx.

When this option is empty the applied encoding corresponds to the 'language for non unicode programs', that is also known as the 'system locale' of the agent Workstation.

im.agent.prompt-color

Default Value:

1. FF385078

Valid Values: Valid Hexidecial (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the prompt for the messages entered by the agent in the IM view.

>> Back to Top

im.agent.text-color

Default Value:

1. FF385078

Valid Values: Valid Hexidecial (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the text of the messages entered by the agent in the IM view.

>> Back to Top

im.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specify whether a instant messaging interaction is automatically answered when a TServer Ringing event is received

>> Back to Top

im.new-message-bell

Default Value:

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: Immediately

Specifies the sound configuration string for a new Instant Message. For example: "Sounds\bell.mp3

im.other-agent.prompt-color

Default Value:

1. FFD88000

Valid Values: Valid Hexidecial (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the text of the messages entered by the target agent in the IM view.

>> Back to Top

im.other-agent.text-color

Default Value:

1. FFD88000

Valid Values: Valid Hexidecial (HTML) color code

Changes Take Effect: Immediately.

Color of the other agent text in the IM view. The HTML format is used to set the value. I.e.: #FFFF0000 for a red color.

>> Back to Top

im.prompt-for-end

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specify if application prompts a confirmation message when user clicks the 'end' button. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

im.ringing-bell

Default Value: Sounds\Ring.mp3

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the im channel ringing sound-configuration string. For example: "Sounds\Ring.mp3

>> Back to Top

im.system.text-color

Default Value:

1. FF8C8C8C

Valid Values: Valid Hexidecial (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the text for the system messages in the IM view.

>> Back to Top

im.time-stamp

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Specify whether the time stamp is displayed in the transcript area.

>> Back to Top

im.toast-timeout

Default Value: 10

Valid Values: from 0 to MAXINT

Changes Take Effect: At the next interaction.

Defines the duration, in seconds, that the IM interaction notification is displayed in the Information area of the Main Window before the IM is rejected. The value 0 means the interaction notification is displayed until the agent accepts the interaction.

>> Back to Top

interaction-bar.detail-tooltip.max-height

Default Value: 164

Valid Values: An integer value greater than or equal to 0.

Changes Take Effect: Immediately.

Sets the maximum height, in pixels, of the tooltip for interaction details of Interaction Bar items. The tooltip can contain the chat transcript, the body of an e-mail and so on.

>> Back to Top

interaction.case-data.content

Default Value: History, Case Data

Valid Values:

Changes Take Effect: At the next interaction.

Specifies the content of the Case Information area in the interaction preview.

- The CaseData key enables the display of the attached data that is defined by the interaction.casedata.format-business-attribute option; the relative order of case data keys can be specified in the configured Business Attribute object as described in that option.
- The History key enables the display of interaction history information such as 'origin', 'queue', 'call type'. The content displayed in the 'history' block is controlled by the application and the list of keys depends on the context. Administrators do not have control over this content.
- The order of the values in the option defines the order of the Case Data (as a block) and History (as another block) information in the Case Information area of the interaction preview.
- This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy. Starting from the 8.1.1 release, this option no longer controls the display of case information in the toast view. Please refer to the toast.case-data.content option for this purpose.

>> Back to Top

interaction.case-data.enable-url-preview

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Enables the display of a preview of the web page that is linked from URLs that are part of the case information. See also the 'expression.url' option.

This option can be overridden by a routing strategy, as described in the Interaction Workspace 8.1 Deployment Guide."

>> Back to Top

interaction.case-data.format-business-attribute

Default Value:

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters. **Changes Take Effect:** At the next interaction

Specifies the name of the Business Attribute that contains the Business Attribute Values that are used to filter and render attached data in the interaction.

This option can be overridden by a routing strategy as described in Deployment Guide.

You can define the display order of Business Attribute Values by creating an interaction-workspace section in the annex of the Business Attribute, then add the interaction.case-data.order option. This option is a comma-separated list of Business Attributes Value Names that specifies the order of the Business Attribute Values. The Attributes Values that are not listed in interaction.case-data.order option are put at the bottom of the list.

Starting from 8.1.1 release this option does not control anymore the display of case information in the toast view. Please refer to option toast.case-data.format-business-attribute for this purpose.

>> Back to Top

interaction.case-data.frame-color

Default Value:

1. FFFFBA00

Valid Values: Valid Hexidecial (HTML) color code **Changes Take Effect:** At the next interaction.

Specifies the color of the border of the Case Data view frame. Examples: #FFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

interaction.case-data.header-foreground-color

Default Value:

1. FF15428B

Valid Values: Valid Hexidecial (HTML) color code **Changes Take Effect:** At the next interaction.

Specifies the color of the foregroung of the Case Data view header. Example #FFFFFFF for white color This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

interaction.case-data.is-read-only-on-idle

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

If the value of this option is true, changes to the case data after a voice interaction has been released are prevented. When some values are modified or added after the voice call is released, the update is pushed to back-end as a User Event when agent clicks 'Mark Done'. This option can be overridden by a routing strategy as described in the Deployment Guide.

>> Back to Top

interaction.consult-user-data

Default Value: public

Valid Values: Select a value from the following list: public, private, none

Changes Take Effect: Immediately.

Defines if and how the business data (original interaction user data, contact identifier,...) of the customer interaction is shared in a consultation interaction.

- · none: No data is shared in the consultation.
- public: User data of the customer interaction is shared in the consultation. The user data is copied at the root level of the consultation user data.
- private: User data of the customer interaction is shared in the consultation. The user data is copied in a sub-list of the consultation user data, named 'SharedInformation'. This is Interaction Workspace 8.1.0 compatibility mode.

This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

interaction.disposition.is-mandatory

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediatly.

Specify whether it is mandatory for the agent to set a disposition code before Marking Done an interaction. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

interaction.disposition.is-read-only-on-idle

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediatly.

Prevents changes to the disposition code after a voice interation has been released. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

interaction.disposition.key-name

Default Value: DispositionCode

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters.

Changes Take Effect: Immediatly

The key that is used to populate attached data or a user event when a disposition code is submitted to the back-end system, such as T-Server, Interaction Server, and Contact Server. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

interaction.disposition.use-attached-data

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Enables the adding of attached data from the interaction in UserEvent. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

interaction.disposition.use-connection-id

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediatly.

Specifies whether the connection id is sent as part of the user event that is sent for disposition code. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

interaction.disposition.value-business-attribute

Default Value: DispositionCode

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters.

Changes Take Effect: Immediatly

A character string that specifies the name of the Business Attribute that contains the Attribute Values that are used as an enumerated value for a disposition code.

This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

interaction.evaluate-real-party-for-agent

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether Interaction Workspace attempts to transform the name of the party DN into an Agent name during a voice interaction.

>> Back to Top

interaction-management.available-interaction-page-sizes

Default Value: 5,10,25,50

Valid Values: A comma-separated list of numbers that define the number of rows per result page

from which the agent can make selections.

Changes Take Effect: When the application is started or restarted.

The possible values for the number of rows per page in the Interaction Filters content view.

>> Back to Top

interaction-management.filters

Default Value:

Valid Values: A comma-separated list of Filter names.

Changes Take Effect: When the application is started or restarted.

Defines the filters that are displayed to the supervisor for interaction management. The filter names refer to the names of the Application Option sections that are defining the Filters.

>> Back to Top

interaction-management.interactions-filter.displayedcolumns

Default Value: MessageType,From,To,Subject,Received

Valid Values: A comma-separated list of Interaction Server interaction properties, for example:

From, Subject, Received

Changes Take Effect: When the application is started or restarted.

The list of interaction fields that are displayed as columns in the Interaction Queue Filters view.

>> Back to Top

interaction.override-option-key

Default Value: IW OverrideOptions

Valid Values: Comma separated list of transaction object

Changes Take Effect: At the next interaction.

Enables overriding of certain application options by using a transaction oject. This option provides the key name of the attached data that contains the list of transaction objects."

>> Back to Top

interaction.reject-route

Default Value:

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore, @ and space

characters.

Changes Take Effect: At the next interaction.

Specifies the routing that is to be used for rejected interactions. Format for the route is <DN>@<SWITCH>

>> Back to Top

interaction.window.popup-topmost-z-order

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction if the value is changed to 'true' or when the

application is started or restarted if the value is changed to 'false'.

Specifies whether the interaction window can "steal" focus from other active applications when autoanswer is enabled. When set to 'false', the Interaction Window tries to gracefully get the focus; however, due to certain Windows Operating System settings, this attempt might not result in moving the interaction window to the front.

>> Back to Top

interaction.window.show-case-interaction-panel-button

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the collapse/expand button on interaction windows is enabled. If the value of this option is set to true, the button is enabled, and agents can collapse and expand the interaction view (left panel). The interaction view contains the controls and content of the interaction. If this view is collapsed, only the right panel is displayed. This is typically the Contact Information and Contact History view or Standard Responses view or any available customized view. If the value of this option is set to false, the button is not enabled, and the interaction view cannot be collapsed.

>> Back to Top

interaction.window.show-in-taskbar

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Indicates whether the interaction window has a task bar button. If not, when minimized the window can be restored from the Interaction Bar.

>> Back to Top

interaction.window-title

Default Value: (\$Contact.FirstName\$ \$Contact.LastName\$

Valid Values:

\$Window.Title\$,\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$

Changes Take Effect: When the application is started or restarted.

Defines the title of the interaction window that appears in the Windows Task Bar by specifying a string that contains the following field

codes:\$Window.Title\$,\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.Firstloption can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

interactions.window.allows-transparency-on-winos6

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the interaction window is presented in transparent style on Windows OS version 6 or higher. Unmanaged controls, such as web browsers, are not able to function in Windows Vista and Windows 7 if non-transparent windows are used. Set the value to false to permit the display of unmanaged controls.

intercommunication.chat.conference.invite-timeout

Default Value: 30

Valid Values: from 30 to MAXINT

Changes Take Effect: At the next interaction.

Specifies the time-out interval for a chat conference or chat consultation invitation to a skill, agent group, or interaction queue.

>> Back to Top

intercommunication.chat.queue

Default Value:

Valid Values: Name of a valid Script object of type Interaction Queue

Changes Take Effect: At the next interaction.

Specifies the name of the Interaction Queue that is used by the 'routing based' feature for Chat. The following attached data are added by Interaction Worskpace:

 $IW_Routing Based Original Employee Id, IW_Routing Based Target Id, IW_Routing Based Target Type, IW_Routing Based Required For the Foundation of the Foundation For the Foundation Foundat$

>> Back to Top

intercommunication.chat.routing-based-actions

Default Value:

Valid Values: A comma-separated list of valid operation names from the following list:

OneStepTransfer.

Changes Take Effect: At the next interaction.

Specifies the list of 'routing based' actions that an agent is allowed to perform.

>> Back to Top

intercommunication.chat.routing-based-targets

Default Value:

Valid Values: A comma-separated list of valid object types from the following list: Agent,

InteractionQueue

Changes Take Effect: At the next interaction.

Defines the list of targets that are contacted through the 'routing based' mechanism for the requests that are defined in the option 'intercommunication.chat.routing-based-actions'. Note: The targets 'AgentGroup' and 'Skill' are always addressed through routing; therefore, they are not affected by this option.

intercommunication.email.queue

Default Value:

Valid Values: Name of a valid Script object of type Interaction Queue

Changes Take Effect: At the next interaction.

Specifies the name of the Interaction Queue that is used by the 'routing based' feature for E-Mail. The following attached data are added by Interaction Worskpace:

 $IW_Routing Based Original Employee Id, IW_Routing Based Target Id, IW_Routing Based Target Type, IW_Routing Based Required For the Foundation of the Foundation For the Foundation Foundat$

>> Back to Top

intercommunication.email.routing-based-actions

Default Value:

Valid Values: A comma-separated list of valid operation names from the following list:

OneStepTransfer.

Changes Take Effect: At the next interaction.

Specifies the list of 'routing based' actions that an agent is allowed perform.

>> Back to Top

intercommunication.email.routing-based-targets

Default Value:

Valid Values: A comma-separated list of valid object types from the following list: Agent,

InteractionQueue

Changes Take Effect: At the next interaction.

Specifies the list of targets that are contacted through the 'routing based' mechanism for the requests that are defined in the option 'intercommunication.email.routing-based-actions'. Note: The targets 'AgentGroup' and 'Skill' are always addressed through routing; therefore, they are not affected by this option.

>> Back to Top

intercommunication.im.routing-based-actions

Default Value: MakelM

Valid Values: Comma separated list of valid operation names from the following: MakelM

Changes Take Effect: When the application is started or restarted.

Defines the list of Routing Based actions.

intercommunication.im.routing-based-targets

Default Value:

Valid Values: Comma separated list of valid object types from the following: Agent, ACDQueue,

RoutingPoint

Changes Take Effect: At the next interaction.

Defines the list of targets that are contacted through the 'routing based' mechanism for requests that are defined by the following option: 'intercommunication.voice.routing-based-actions'. Note: The targets 'AgentGroup' and 'Skill' are always addressed through routing; therefore, these are not considered by this option.

>> Back to Top

intercommunication.im.routing-points

Default Value:

Valid Values: A comma-separated list of call number names in the following format:

\$dn name@switch\$

Changes Take Effect: At the next interaction.

Determines the call number that is used by the Routing Base feature. The following attached data are added by Interaction Worskpace:

IW_RoutingBasedOriginalEmployeeld,IW_RoutingBasedTargetId,IW_RoutingBasedTargetType,

IW_RoutingBasedRequestType, IW_RoutingBasedLocation.

>> Back to Top

intercommunication.sms.queue

Default Value:

Valid Values: Name of a valid Script object of type Interaction Queue

Changes Take Effect: At the next interaction.

Specifies the name of the Interaction Queue that is used by the 'routing based' feature for SMS. The following attached data are added by Interaction Worskpace:

 $IW_Routing Based Original Employee Id, IW_Routing Based Target Id, IW_Routing Based Target Type, IW_Routing Based Required For the Franchisch Formula of the Franchisch Formula of the Franchisch Fr$

>> Back to Top

intercommunication.sms.routing-based-actions

Default Value: OneStepTransfer

Valid Values: A comma-separated list of valid operation names from the following list:

OneStepTransfer.

Changes Take Effect: At the next interaction.

Defines the list of 'routing based' actions that an agent is allowed to perform.

>> Back to Top

intercommunication.sms.routing-based-targets

Default Value:

Valid Values: A comma-separated list of valid object types from the following list: Agent,

InteractionQueue

Changes Take Effect: At the next interaction.

Defines the list of targets that are contacted through the 'routing based' mechanism for the requests that are defined in the option 'intercommunication.sms.routing-based-actions'. Note: The targets 'AgentGroup' and 'Skill' are always addressed through routing; therefore, they are not affected by this option.

>> Back to Top

intercommunication.voice.routing-based-actions

Default Value: MakeCall,OneStepConference,InitConference,OneStepTransfer,InitTransfer **Valid Values:** A comma-separated list of valid operation names from the following list: MakeCall,

OneStepTransfer, InitTransfer, InitConference, OneStepConference.

Changes Take Effect: At the next interaction.

Defines the list of Routing Based Actions that an agent may perform.

>> Back to Top

intercommunication.voice.routing-based-targets

Default Value:

Valid Values: A comma-separated list of valid object types from the following list: Agent, ACDQueue, RoutingPoint, Contact, TypeDestination.

Changes Take Effect: At the next interaction.

Defines the list of targets that are contacted through the 'routing based' mechanism for the requests that are defined in the option 'intercommunication.voice.routing-based-actions'. Note: The targets 'AgentGroup' and 'Skill' are always addressed through routing; therefore, they are not affected by this option.

intercommunication.voice.routing-points

Default Value:

Valid Values: A comma-separated list of call number names in the following format:

\$dn name@switch\$

Changes Take Effect: At the next interaction.

Determines the call number that is used by the Routing Base feature. The following attached data are added by Interaction Worskpace:

IW RoutingBasedOriginalEmployeeId,IW RoutingBasedTargetId,IW RoutingBasedTargetType,IW_RoutingBasedRequ IW RoutingBasedLocation.

>> Back to Top

intercommunication.<media-type>.queue

Default Value:

Valid Values: Name of a valid Script object of type Interaction Queue

Changes Take Effect: At the next interaction.

Use this option as a template for any specific workitem media-type to specify the name of the Interaction Queue that is used by the 'routing based' feature for the specified workitem media-type. The following attached data are added by Interaction Worskpace:

IW RoutingBasedOriginalEmployeeId,IW RoutingBasedTargetId,IW RoutingBasedTargetType,IW RoutingBasedRequ

>> Back to Top

intercommunication. < media-type > . routing-based-actions

Default Value:

Valid Values: A comma-separated list of valid operation names from the following list: OneStepTransfer.

Changes Take Effect: At the next interaction.

Use this option as a template for any specific workitem media type to define the list of 'routing based' actions that an agent is allowed to perform for the specified workitem media-type.

>> Back to Top

intercommunication. < media-type > . routing-based-targets

Default Value:

Valid Values: A comma-separated list of valid object types from the following list: Agent, InteractionQueue

Changes Take Effect: At the next interaction.

Use this option as a template for any specific workitem media type to define the list of targets that are contacted through the 'routing based' mechanism for the requests that are defined in the option 'intercommunication.<media-type>.routing-based-actions'. Note: The targets 'AgentGroup' and 'Skill' are always addressed through routing; therefore, they are not affected by this option.

>> Back to Top

keyboard.hotkey.agent-not-ready

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a Window Hotkey to set the agent Not Ready.

>> Back to Top

keyboard.hotkey.agent-not-ready-with-reason.<action-code>

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

This option allows you to associate a combination of keys that can be used as a Window Hotkey to set agent status to a particular Not-Ready Reason Code. You need to use this option as a template and modify its name by replacing the string <action-code> by the 'Code' attribute of the Action Code defined in Management layer. For example if your Action Code name is 'Meeting' and the corresponding code is '1012', you will set the option like this: keyboard.hotkey.agent-not-ready-with-reason.1012=Ctrl+Alt+M.

>> Back to Top

keyboard.hotkey.agent-ready

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a Window Hotkey to set the agent Ready.

keyboard.hotkey.decrease-microphone-volume-active-sip-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a Window Hotkey to decrease the volume of the microphone.

>> Back to Top

keyboard.hotkey.decrease-speaker-volume-active-sip-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a Window Hotkey to decrease the volume of the speaker.

>> Back to Top

keyboard.hotkey.hold-active-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a Window Hotkey to put the active voice call on hold.

>> Back to Top

keyboard.hotkey.increase-microphone-volume-active-sip-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a Window Hotkey to increase the volume of the microphone.

>> Back to Top

keyboard.hotkey.increase-speaker-volume-active-sip-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a Window Hotkey to increase the volume of the speaker.

>> Back to Top

keyboard.hotkey.mute-microphone-active-sip-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a Window Hotkey to mute the microphone.

>> Back to Top

keyboard.hotkey.mute-speaker-active-sip-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a Window Hotkey to mute the speaker.

keyboard.hotkey.release-active-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a Window Hotkey to release the active voice call.

>> Back to Top

keyboard.hotkey.toaster.accept

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a Window Hotkey to accept the last incoming interaction.

>> Back to Top

keyboard.hotkey.toaster.decline

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a Window Hotkey to decline the last incoming interaction.

>> Back to Top

keyboard.shortcut.action.help

Default Value: F1

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to display contextual help.

>> Back to Top

keyboard.shortcut.contact.assigncontact

Default Value: Ctrl+A

Valid Values: A key combination that begins with a modifier key name (Ctrl, Shift, Alt, Win) and ends

with a key name, separated by the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to assign a new contact to the interaction.

>> Back to Top

keyboard.shortcut.contact.reset

Default Value: Ctrl+R

Valid Values: A key combination that begins with a modifier key name (Ctrl, Shift, Alt, Win) and ends

with a key name, separated by the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to reset contact settings to their initial values.

>> Back to Top

keyboard.shortcut.contact.save

Default Value: Ctrl+S

Valid Values: A key combination that begins with a modifier key name (Ctrl, Shift, Alt, Win) and ends

with a key name, separated by the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to save the contact modifications.

>> Back to Top

keyboard.shortcut.interaction.chat.conference

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to execute the instant conference operation on the chat interaction.

>> Back to Top

keyboard.shortcut.interaction.chat.end

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to exit the chat session.

>> Back to Top

keyboard.shortcut.interaction.chat.transfer

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to transfer the chat session.

>> Back to Top

keyboard.shortcut.interaction.consult

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to start a consultation.

>> Back to Top

keyboard.shortcut.interaction.email.add-attachments

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to add attachments to the outbound e-mail.

>> Back to Top

keyboard.shortcut.interaction.email.delete

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to delete the outbound e-mail.

>> Back to Top

keyboard.shortcut.interaction.email.forward

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to forward the inbound e-mail to an external resource.

>> Back to Top

keyboard.shortcut.interaction.email.interim-send

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to execute the Interim Send operation on the outbound e-mail.

keyboard.shortcut.interaction.email.print

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to print the e-mail.

>> Back to Top

keyboard.shortcut.interaction.email.reply

Default Value: Ctrl+R

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to execute the Reply operation on an inbound e-mail.

>> Back to Top

keyboard.shortcut.interaction.email.reply-all

Default Value: Ctrl+Shift+A

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to execute the Reply All operation on an inbound e-mail.

>> Back to Top

keyboard.shortcut.interaction.email.save

Default Value: Ctrl+S

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to save the outbound e-mail.

>> Back to Top

keyboard.shortcut.interaction.email.save-in-workbin

Default Value: Ctrl+Shift+W

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to store the e-mail in the default workbin.

>> Back to Top

keyboard.shortcut.interaction.email.send

Default Value: Ctrl+Return

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to send the outbound e-mail.

>> Back to Top

keyboard.shortcut.interaction.email.transfer

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to transfer the e-mail.

>> Back to Top

keyboard.shortcut.interaction.im.release

Default Value: Ctrl+D

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to end Instant Messaging session.

>> Back to Top

keyboard.shortcut.interaction.mark-done

Default Value: Ctrl+E

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to mark the interaction done.

>> Back to Top

keyboard.shortcut.interaction.preview.call-record

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to dial the Outbound preview contact number.

>> Back to Top

keyboard.shortcut.interaction.preview.cancel-record

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to decline (do not call this contact for this campaign) the outbound preview record.

keyboard.shortcut.interaction.preview.mark-done

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to mark the outbound preview record done

>> Back to Top

keyboard.shortcut.interaction.preview.mark-done-getnext

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to get next record from the outbound preview campaign.

>> Back to Top

keyboard.shortcut.interaction.preview.reject-record

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to decline (call the contact later) the outbound preview record.

>> Back to Top

keyboard.shortcut.interaction.sms.delete

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to delete the outbound SMS interaction.

>> Back to Top

keyboard.shortcut.interaction.sms.transfer

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to transfer the SMS interaction.

>> Back to Top

keyboard.shortcut.interaction.voice.answer-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to answer the voice call.

>> Back to Top

keyboard.shortcut.interaction.voice.hold-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to put the voice call on hold.

>> Back to Top

keyboard.shortcut.interaction.voice.pause-recording-call

Default Value:

Valid Values: Only the name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to pause the recording of the voice call.

>> Back to Top

keyboard.shortcut.interaction.voice.reconnect-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to reconnect the voice call.

>> Back to Top

keyboard.shortcut.interaction.voice.release-call

Default Value: Ctrl+D

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to release the voice call.

>> Back to Top

keyboard.shortcut.interaction.voice.resume-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to resume the voice call.

keyboard.shortcut.interaction.voice.resume-recording-call

Default Value:

Valid Values: Only the name of a key or a key combination that begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to resume the recording of the voice call.

>> Back to Top

keyboard.shortcut.interaction.voice.single-stepconference

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to instant conference the voice call.

>> Back to Top

keyboard.shortcut.interaction.voice.single-step-transfer

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to instant transfer the voice call.

>> Back to Top

keyboard.shortcut.interaction.voice.start-recording-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to start recording the voice call.

>> Back to Top

keyboard.shortcut.interaction.voice.stop-recording-call

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to stop the recording of the voice call.

>> Back to Top

keyboard.shortcut.interaction.webcallback.call-contact

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to dial the web callback contact number.

>> Back to Top

keyboard.shortcut.interaction.webcallback.mark-done

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to mark the web callback interaction done.

>> Back to Top

keyboard.shortcut.interaction.workitem.move-to-workbin

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following

modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to move the workitem interaction into the default workbin.

>> Back to Top

keyboard.shortcut.interaction.workitem.transfer

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to transfer the workitem interaction.

>> Back to Top

keyboard.shortcut.state.logout

Default Value: Ctrl+Alt+X

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to logout from the application.

>> Back to Top

keyboard.shortcut.state.not-ready

Default Value: Ctrl+Alt+N

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to make the agent globally not ready.

keyboard.shortcut.state.not-ready-after-call-work

Default Value: Ctrl+Alt+Z

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to set the agent in after call work.

>> Back to Top

keyboard.shortcut.state.ready

Default Value: Ctrl+Alt+R

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to make the agent globally ready.

>> Back to Top

keyboard.shortcut.teamlead.chat.bargein

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to barge in the supervised chat interaction.

>> Back to Top

keyboard.shortcut.teamlead.chat.stop-monitoring

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to stop the supervision of the chat

interaction.

>> Back to Top

keyboard.shortcut.teamlead.stop-monitoring

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to stop supervising the multichannel conversation.

>> Back to Top

keyboard.shortcut.teamlead.voice.bargein

Default Value:

Valid Values: The name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to barge-in the supervised voice interaction.

>> Back to Top

keyboard.shortcut.teamlead.voice.coaching

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to start coaching the voice interaction.

>> Back to Top

keyboard.shortcut.teamlead.voice.monitor

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following

modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to switch from coaching to monitoring the voice call. Works only for Cisco Call Manager switch.

>> Back to Top

keyboard.shortcut.teamlead.voice.stop-monitoring

Default Value:

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to stop the supervision of the voice interaction.

>> Back to Top

keyboard.shortcut.toaster.accept

Default Value: Ctrl+G

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to accept the incoming interaction.

>> Back to Top

keyboard.shortcut.toaster.decline

Default Value: Ctrl+M

Valid Values: Only the name of a key or a key combination the begins with one of the following modifier key names: Ctrl, Shift, Alt, and Win, and ends with a character key. Separate the modifier

key name from the character key with the '+' character.

Changes Take Effect: When the application is started or restarted.

The combination of keys that can be used as a keyboard shortcut to decline the incoming interaction.

kpi.displayed-kpis

Default Value:

Valid Values: A comma-separated list of KPI names.

Changes Take Effect: When the application is started or restarted.

Defines the KPIs that are displayed to the agent. The KPI names refer to the names of the Application Option sections that are defining the KPIs.

>> Back to Top

kpi.refresh-time

Default Value: 10

Valid Values: An integer value greater than 0.

Changes Take Effect: When the application is started or restarted.

Defines the frequency of notification (in seconds) for statistics.

>> Back to Top

kpi.show-agent-groups

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specify if agent group KPI information is displayed to the agent for all groups to which the agent is a member.

>> Back to Top

license.lrm-enabled

Default Value: false **Valid Values:** true.false

Changes Take Effect: When the application is started or restarted.

Specifies whether the Interaction Workspace signature is recognized by Genesys License Reporting Manager.

log.default-filter-type

Default Value: Copy

Valid Values: Select a value from the following list:

- copy
- skip
- hide
- hide-first, <n>
- unhide-last.<n>
- unhide-first, <n>
- unhide-last,<n>
- custom-filter,<KeyPrefix>,<KeyPost>,<ValuePrefix>,<ValuePost>

The filter 'custom-filter' enables you to define some KeyPrefix, KeyPost, ValuePrefix, ValuePost.

Example: log.default-filter-type: custom-filter,<,>,<#,#>

Changes Take Effect: Immediately.

Specifies the default view of KVList information (including UserData, Extensions, and Reasons) in the log.

It is applied to the attributes of all KVList pairs except those that are explicitly defined in the log-filterdata key.

>> Back to Top

log.ESDK

Default Value: All

Valid Values: One value from this list: All, Debug, Trace, Interaction, Alarm

Changes Take Effect: Immediately.

Defines the level of logging for API ESDK.

>> Back to Top

log.expire

Default Value: 10

Valid Values: An integer value from 1 through 100.

Changes Take Effect: Immediately.

Specifies if log files are stored. If they are stored, specifies the maximum number of files (segments) to be stored before the oldest file is removed. \$number\$ Sets the maximum number of log files to store.

>> Back to Top

log.filter-data.<keyName>

Default Value: Copy

Valid Values: Select a value from the following list:

- copy
- skip
- hide
- hide-first,<n>
- unhide-last,<n>
- unhide-first.<n>
- unhide-last,<n>
- custom-filter,<KeyPrefix>,<KeyPost>,<ValuePrefix>,<ValuePost>

The filter 'custom-filter' enables you to define KeyPrefix, KeyPost, ValuePrefix, and ValuePost.

Example: log.filter-data.Subject: custom-filter,>,<,>#,#<

Changes Take Effect: Immediately.

Defines the treatment of specific data in the log.

It overrides the general settings specified by the log.default-filter-type option.

>> Back to Top

log.max-age

Default Value: 10

Valid Values: An integer value from 0 in days

Changes Take Effect: When the application is started or restarted.

Specifies the maximum number of days for which Interaction Workspace log files are kept. If the option value is greater than 0, the application deletes the old log files (older than the value of this option) at startup. If the option value is set to 0, log files are not deleted at startup.

>> Back to Top

log.PSDK

Default Value: Standard

Valid Values: One value from this list: All, Debug, Trace, Interaction, Standard, Alarm

Changes Take Effect: Immediately.

Define the level of logging for the PSDK API.

>> Back to Top

log.segment

Default Value: 10MB

Valid Values: \$number\$ KB or \$number\$ Sets the maximum segment size, in kilobytes. The minimum segment size is 100 KB. \$number\$ MB Sets the maximum segment size, in megabytes.

Changes Take Effect: When the application is started or restarted.

If set, specifies that there is a segmentation limit for a log file and defines the limit size in either kilobytes (KB) or megabytes (MB). If the current log segment exceeds the defined size, the file is closed and a new one is created.

>> Back to Top

log.Trace

Default Value: \$Application.RootApplicationData\$\log\InteractionWorkspace

Valid Values: A valid URL.

Changes Take Effect: Immediately.

Defines the full path of the log file. The file name uses the following extension: ?.%date{yyyyMMdd_HHmmss_fff}.log?. The full path can also contain the following field codes:

\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.Employeeld\$,\$Application.Exe\$,\$Application.Application.Application.Exe\$,\$Application.Application.Application.Application.Exe\$,\$Application.Exe\$,\$Application.Application.Application.Exe\$,\$Application.Exe\$,\$Application.Exe\$,\$Application.Application.Exe\$,\$Applic

>> Back to Top

log.verbose

Default Value: Trace

Valid Values: Select a value from the following list: All, Debug, Trace, Interaction, Standard, Alarm,

None

Changes Take Effect: Immediately.

Defines the level of logging. If set to None, the trace is turn off in the Interaction Workspace log file. For the other value, if the Interaction Workspace log file doesn't exist, it is created by the application.

>> Back to Top

login.chat.auto-not-ready-reason

Default Value:

Valid Values: A valid not ready reason

Changes Take Effect: When the application is started or restarted

If the Chat channel is automatically set to NotReady when an agent logs in, this option defines the NotReady Reason code.

>> Back to Top

login.chat.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can select and unselect (auto-login or not) the chat channel.

>> Back to Top

login.chat.is-auto-ready

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the chat channel is automatically set to the Ready state at login.

>> Back to Top

login.default-place

Default Value:

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters. **Changes Take Effect:** When the application is started or restarted.

Specifies the place name that is populated by default during login. This option can use the \$Agent.DefaultPlace\$ variable. If the agent has a default place that is specified in the agent configuration, then that place is used. However, if no default place exists, then the agent must enter their place in the Place field).

>> Back to Top

login.email.auto-not-ready-reason

Default Value:

Valid Values: A valid not ready reason

Changes Take Effect: When the application is started or restarted

If the E-Mail channel is automatically set to NotReady when an agent logs in, this option defines the NotReady Reason code.

>> Back to Top

login.email.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can select and unselect (auto-login or not) the e-mail channel.

>> Back to Top

login.email.is-auto-ready

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the e-mail channel is automatically set to the Ready state at login.

>> Back to Top

login.enable-login-without-channel

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether agents can login to the Interaction Workspace application without being logged in to any channels.

>> Back to Top

login.enable-place-completion

Default Value: true **Valid Values:** true or false

Changes Take Effect: When the application is started or restarted.

This option is used for performance issue at login time (when a lot of agents logs in at the same time). Set this option to false to disable the load of all the places when the Interaction Workspace is started. This improves the performance if there are a lot of places in your environment. The

restriction with this option set to false is that there is no longer a list of available places in the 2nd login panel.

>> Back to Top

login.enable-same-agent-place

Default Value: true

Valid Values: true, false, prompt

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can login on the same Place from different workstations.

The value **prompt** allows the agent to login on the same Place from different workstations, but the

agent is first prompted for confirmation before an additional login is permitted.

>> Back to Top

login.im.auto-not-ready-reason

Default Value:

Valid Values: A valid not ready reason

Changes Take Effect: When the application is started or restarted

If the Instant Messaging channel is automatically set to NotReady when the agent logs in, this option defines the NotReady Reason code.

>> Back to Top

login.im.available-queues

Default Value: ACDQueue

Valid Values: A comma-separated list of valid object types from the following list: ACDQueue,

RoutingPoint, VirtualQueue

Changes Take Effect: When the application is started or restarted.

Enables agents to choose a login queue from a drop-down list or to enter the login queue manually. If this option is empty, agents can type any valid login queue name. If set to "ACDQueue", "RoutingPoint", "VirtualQueue" or "ACDQueue,RoutingPoint" agents can select one of the defined queues or routing points from a drop-down list.

>> Back to Top

login.im.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted

Specifies whether the agent can select and unselect (activate and deactivate) Instant Messaging channels.

>> Back to Top

login.im.is-auto-ready

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted

In case Instant Messaging channel is automatically set to NotReady at login, this option defines the NotReady Reason code.

>> Back to Top

login.im.prompt-agent-login-id

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can select a login id from the configured ones for the IM channel in the login window.

>> Back to Top

login.im.prompt-dn-password

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent must enter his password for the IM channel in the login window.

>> Back to Top

login.im.prompt-queue

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent must enter the ACD Queue for the IM channel in the login window.

>> Back to Top

login.prompt-place

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent must enter his place in the login window.

>> Back to Top

login.sip-cluster.phone-number

Default Value:

Valid Values: Any valid device number or a string that contains one of the following field codes: \$Agent.EmployeeId\$.

Changes Take Effect: When the application is started or restarted.

Specifies the device number that is used to log an agent to the SIP Cluster. This option can use the \$Agent.EmployeeId\$ variable. If the value of the option is empty, the agent must enter her or his phone number for the voice channel in the Login view.

>> Back to Top

login.sip-cluster.store-recent-phone-number

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the phone number that was typed during the most recent login to SIP Cluster infrastructure is stored in the user profile so that it can be restored during the next login. This option is available if the login.sip-cluster.phone-number option is empty.

>> Back to Top

login.sms.auto-not-ready-reason

Default Value:

Valid Values: A valid not ready reason

Changes Take Effect: When the application is started or restarted

If the SMS channel is automatically set to NotReady when an agent logs in, this option defines the NotReady Reason code.

>> Back to Top

login.sms.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can select and unselect (activate and deactivate) the SMS channel.

>> Back to Top

login.sms.is-auto-ready

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the SMS channel is automatically in the ready state at agent login.

>> Back to Top

login.store-recent-place

Default Value: true **Valid Values:** true. false

Changes Take Effect: When the application is started or restarted.

Specifies whether the most recently used Place is stored. This option is available if the login.defaultplace option is not set to \$Agent.DefaultPlace\$.

>> Back to Top

login.voice.auto-not-ready-reason

Default Value:

Valid Values: A valid not ready reason

Changes Take Effect: When the application is started or restarted

If the Voice channel is automatically set to NotReady when the agent logs in, this option defines the NotReady Reason code.

login.voice.available-queues

Default Value: ACDQueue

Valid Values: A comma-separated list of valid object types from the following list: ACDQueue,

RoutingPoint, VirtualQueue

Changes Take Effect: When the application is started or restarted.

Enables agents to choose a login queue from a drop-down list or to enter the login queue manually. If this option is empty, agents can type any valid login queue name. If set to "ACDQueue", "RoutingPoint", "VirtualQueue" or "ACDQueue,RoutingPoint" agents can select one of the defined queues or routing points from a drop-down list.

>> Back to Top

login.voice.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted

Specifies whether the agent can select and unselect (activate and deactivate) voice channels.

>> Back to Top

login.voice.force-relogin

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted

Specifies whether the voice channels should be re-logged on automatically if logged off from outside the application.

>> Back to Top

login.voice.is-auto-ready

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted

Specifies whether the voice channels are in the Ready state at login.

login.voice.prompt-agent-login-id

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction

Specifies whether the agent can select a login id from the configured ones for the voice channel in the login window.

>> Back to Top

login.voice.prompt-dn-less-phone-number

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether a DN-less phone number is prompted for in the login window. This option is specific to SIP Server environment.

>> Back to Top

login.voice.prompt-dn-password

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent must enter his password for the voice channel in the login window.

>> Back to Top

login.voice.prompt-queue

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent must enter the ACD Queue for the voice channel in the login window.

>> Back to Top

login.webcallback.auto-not-ready-reason

Default Value:

Valid Values: A valid not ready reason

Changes Take Effect: When the application is started or restarted

Specifies the Not Ready Reason that is displayed after an agent logs in on a channel that is not automatically set to Ready. The Not Ready Reason corresponds to the name of a Not Ready Action Code. If the reason is empty, no Not Ready Reason is displayed for the channel at log in time if the channel is in the Not Ready state. This option is ignored if the option login.webcallback.is-auto-ready is set to 'true'.

>> Back to Top

login.webcallback.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can select and unselect (auto-login or not) the Web Callback channel.

>> Back to Top

login.webcallback.is-auto-ready

Default Value: false **Valid Values:** true.false

Changes Take Effect: When the application is started or restarted.

Specifies whether the Web Callback channel is automatically set to the Ready state at login.

>> Back to Top

login.workmode

Default Value: unknown

Valid Values: unknown, auto-in, manual-in

Changes Take Effect: When the application is started or restarted or if the agent changes place.

Specifies the workmode that is applied when the voice DN logs in. If set to 'auto-in', the agent is automatically in Ready state. If set to 'manual-in', the agent must manually activate the Ready state. To determine whether your switch supports the workmode, refer to the Deployment Guide of the relevant T-Server.

login.<media-type>.auto-not-ready-reason

Default Value: false

Valid Values: A valid not ready reason

Changes Take Effect: When the application is started or restarted.

If the indicated workitem channel is automatically set to NotReady when an agent logs in, this option defines the NotReady Reason code.

>> Back to Top

login.<media-type>.can-unactivate-channel

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can select and unselect (auto-login or not) the specified Workitem channel.

>> Back to Top

login.<media-type>.is-auto-ready

Default Value: false **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the indicated workitem channel is automatically set to the Ready state at login.

>> Back to Top

logout.enable-exit-on-logoff-error

Default Value: true

Valid Values: true, false, prompt

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent can log out from the application even if one of the voice channel log offs resulted in an error.

The value **prompt** allows the agent to log out of the application if a log off channel error occurs. The agent is first prompted for confirmation before logging out the application.

main-window.dockable

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Enables the docking feature of the Main Window. If set to true, the Main Window can be docked to the top or the bottom of the display. If set to false, the Main Window is not dockable.

>> Back to Top

main-window.window-title

Default Value: \$Window.Title\$

Valid Values:

\$Window. Title\$, \$Application. Title\$, \$Application. Name\$, \$Agent. User Name\$, \$Agent. Last Name\$, \$Agent. First Name\$, \$Agent. Title\$, \$Agent. First Name\$, \$Agent. Last Name\$, \$Agent. First Name\$, \$Agent. Title\$, \$Agent. First Name\$, \$Agent. Last Name\$, \$Agent. Last Name\$, \$Agent. First Name\$, \$Agent. Last Name\$, \$Agent. First Name\$, \$Agent. Last Name\$, \$Agent

Changes Take Effect: Immediately.

Defines the title of the Main Window that appears in the Windows Task Bar by specifying a string that contains the following field

codes:\$Window.Title\$,\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$,

\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$. If all field codes are empty, the following field codes are used: \$Window.Title\$.

>> Back to Top

openmedia.bundle.sms

Default Value: sms,smssession

Valid Values: A comma-separated list of valid media type names **Changes Take Effect:** When the application is started or restarted.

Defines the list of media types that are used to implement the SMS channel. This list can contain 'sms' (SMS Page mode) and/or smssession (SMS Session Mode)

>> Back to Top

openmedia.workitem-channels

Default Value:

Valid Values: A comma-separated list of valid Media Types.

Changes Take Effect: When the application is started or restarted.

Specifies the list of Workitem channels that are used by the agent.

options.record-option-locally-only

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the display settings for the agent are stored locally or in the agent annex.

>> Back to Top

outbound.call-result-automatically-selected

Default Value:

Valid Values: Select one value from the list. **Changes Take Effect:** At the next interaction.

Specifies the call result to be selected by default for outbound records. The specified call result must be defined by the values that are specified for the 'outbound.call-result-values' option. If set to an empty value, the current call result of the outbound record is selected, or 'unknown' is selected if there is no current value.

>> Back to Top

outbound.call-result-values

Default Value: Answered, Answering Machine, Busy, No Answer, Wrong Number

Valid Values: Select at least one item from the list. **Changes Take Effect:** At the next interaction.

The list of call results that are available for the agent to use for outbound interaction. The call results are displayed in the order in which they appear in the list.

>> Back to Top

outbound-callback.ringing-bell

Default Value:

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the sound-configuration string of a scheduled callback pushed to the agent as a preview. For example: "Sounds\Ring.mp3

outbound.campaign-stale-timeout

Default Value: 0

Valid Values: An integer value

Changes Take Effect: When the application is started or restarted.

Records remain editable for a specified period of time after a campaign is unloaded, to reflect the Outbound Contact Server (OCS) OCServer section stale_clean_timeout option. A value of 0 means that the outbound record becomes read-only when the campaign is unloaded. A positive value is the duration, in minutes, during which the outbound record remains editable. A value of -1 means that the outbound record is always editable (however, this action may fail in the OCS).

>> Back to Top

outbound.fields.float-separator-in-db

Default Value:

Valid Values: A valid float separator. Typical float separators are: '.',',','\'

Changes Take Effect: Immediately.

Specifies the separator that is used for floating point numbers in the database for outbound fields. This option should be used when the decimal symbol in the regional settings of the agent workstation is different from the one provided by the database.

>> Back to Top

outbound.push-preview.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether a push preview outbound interaction is automatically accepted when Interaction Server Invite event is received. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

outbound.push-preview.media-types

Default Value: outboundpreview

Valid Values:

Changes Take Effect: When the application is started or restarted.

The list of media types that are available for the agent to use for outbound push-preview interactions.

>> Back to Top

outbound.push-preview.use-combined-channel

Default Value: true **Valid Values:** true,false

Changes Take Effect: When the application is started or restarted.

Specifies whether the outboundpreview channel is combined with the voice channel in the User Interface. If set to 'true', only the voice channel is presented, and any change in the status of one channel is applied to the other channel

>> Back to Top

outbound.record-information.frame-color

Default Value:

1. FFDFE8F6

Valid Values: Valid Hexadecimal (HTML) color code **Changes Take Effect:** At the next interaction.

Specifies the color of the border of the Record Information view frame of Outbound interactions. Examples: #FFFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

outbound.record-information.header-foreground-color

Default Value:

1. FF15428B

Valid Values: Valid Hexadecimal (HTML) color code **Changes Take Effect:** At the next interaction.

Specifies the color of the foreground of the Record Information view frame of Outbound interactions. Example #FFFFFFF for white color. This option can be overridden by a routing strategy as described in Deployment Guide.

outbound.sound.campaign-updated

Default Value:

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the sound-configuration string when the campaign status is updated. For example: "Sounds\ Ring.mp3

>> Back to Top

outbound.treatment-mode

Default Value: none

Valid Values: Select one value from the following list: personal,campaign,none. none: The application never applies any treatment to mark processed requests.

 $campaign: The \ treatment \ Record Treat Campaign \ is \ applied \ to \ the \ record \ when \ a \ mark \ processed$

action is executed.

personal: The treatment RecordTreatPersonal is applied to the record when a mark processed action

is executed.

Note: campaign and personal are valid unless a call has been rescheduled by the agent.

Changes Take Effect: Immediately.

Specifies the type of treatment to be applied for the outbound record after it is marked as processed. If set to none, no treatment is applied for the outbound record.

>> Back to Top

presence.evaluate-presence

Default Value: true **Valid Values:** true or false

Changes Take Effect: When the application is started or restarted.

Specify whether to evaluate presence or not. Set this option to true if the presence must be evaluated for agents, agent groups, T-Server queues, routing points, and interation queues.

>> Back to Top

printing.use-print-preview

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Specifies whether a print preview is shown when the user request to print a document.

>> Back to Top

security.disable-rbac

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Disables role based access (RBAC). If this option is set to true, all the Interaction Workspace tasks are available to the agents. If this option is set to false, the list of agent tasks must be defined in Genesys Administrator.

>> Back to Top

security.enable-debug-information

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediately.

Specifies if the agent is able to display the Debug part (with buttons 'Exe', 'Logs', 'GC',...) in the about window.

>> Back to Top

security.inactivity-not-ready-reason

Default Value:

Valid Values: A valid not ready reason

Changes Take Effect: When the application is started or restarted.

Specify the not-ready reason if the status of an agent is automatically set to not-ready following agent inactivity detection.

>> Back to Top

security.inactivity-set-agent-not-ready

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies if the agent status is automatically set to not-ready when agent inactivity is detected.

>> Back to Top

security.inactivity-timeout

Default Value: 0

Valid Values: An integer value. If set to 0, inactivity is not taken into account.

Changes Take Effect: When the application is started or restarted.

Specifies the agent-inactivity timeout interval, in minutes. If the agent has been inactive (not using the mouse or keyboard) for longer than the inactivity timeout interval, the agent must reauthenticate to be able to use the Interaction Workspace application.

>> Back to Top

sip-cluster.data-center-locations

Default Value: Valid Values:

Changes Take Effect: When the application is started or restarted.

Specifies the list of data center locations that are available for SIP Clustering.

>> Back to Top

sip-cluster.reconnect-timeout

Default Value: 10

Valid Values: from 0 to MAXINT Changes Take Effect: Immediatly.

In SIP Cluster environment, specifies the duration, in seconds, between each attempt to reconnect to SIP Server (TController) and/or Stat Server in the case of a connection loss.

>> Back to Top

sipendpoint.audio.headset.audio_in_agc_enabled

Default Value: 1 **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether AGC (automatic gain control) is enabled for headset audio (outgoing audio stream).

sipendpoint.audio.incoming.use_agc

Default Value: 1

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether AGC (automatic gain control) is enabled for incoming calls.

>> Back to Top

sipendpoint.authenticate-with-dn-password

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the DN password that is specified in the Login window is used to authenticate at the SIP Endpoint level.

>> Back to Top

sipendpoint.exit-on-voice-logoff

Default Value: false **Valid Values:** true, false

Changes Take Effect: At next Log Off operation or at next login.

Specifies whether Interaction Workspace SIP Endpoint is unregistered and stopped if the voice channel is logged off manually by an agent. If the value of this option is set to 'true', the corresponding voice DN is also unregistered from SIP Server and therefore Interaction Workspace does not get notifications of any activity that occurs on it. If an agent manually Logs On to the voice channel, the corresponding DN is registered again and Interaction Workspace SIP Endpoint is restarted.

>> Back to Top

sipendpoint.genesyslab.beeptone.beeptone_timeout

Default Value: 30000

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the timeout interval, in milliseconds, for the beep tone.

sipendpoint.genesyslab.beeptone.enable_beeptone

Default Value: 1

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the beep tone is enabled.

>> Back to Top

sipendpoint.genesyslab.beeptone.play_locally

Default Value: 0

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the beep tone is played locally.

>> Back to Top

sipendpoint.genesyslab.control.auto_answer

Default Value: 0

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether inbound calls are answered automatically.

>> Back to Top

sipendpoint.genesyslab.device.audio_in_device

>> Back to Top

sipendpoint.genesyslab.device.audio out device

>> Back to Top

sipendpoint.genesyslab.device.error code when headset na

Default Value: 480

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the error code that is sent when the call is rejected because of unavailability of a headset.

>> Back to Top

sipendpoint.genesyslab.device.headset_name

>> Back to Top

sipendpoint.genesyslab.device.manual_audio_devices_configure

Default Value: 0

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies that the agent is using a non-USB headset.

>> Back to Top

sipendpoint.genesyslab.device.reject_call_when_headset_na

Default Value: 0

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether incoming calls are rejected if the headset is unavailable.

>> Back to Top

sipendpoint.genesyslab.device.use_headset

Default Value: 0

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether a USB headset is used by the agent.

>> Back to Top

sipendpoint.genesyslab.dtmf.pause_start_stop_dtmf

Default Value: 100

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the time interval, in milliseconds, between each DTMF.

>> Back to Top

sipendpoint.genesyslab.dtmf.play_locally

Default Value: 0

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether dtmf are played locally.

>> Back to Top

sipendpoint.genesyslab.system.log_level_AbstractPhone

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for the abstract phone.

>> Back to Top

sipendpoint.genesyslab.system.log_level_Audio

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for audio.

>> Back to Top

sipendpoint.genesyslab.system.log_level_Auto Configuration

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for auto configuration.

sipendpoint.genesyslab.system.log_level_CCM

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for CCM.

>> Back to Top

sipendpoint.genesyslab.system.log_level_Conferencing

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for conferencing.

>> Back to Top

sipendpoint.genesyslab.system.log_level_Contacts

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for contacts.

>> Back to Top

sipendpoint.genesyslab.system.log_level_DNS

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for DNS.

>> Back to Top

sipendpoint.genesyslab.system.log level Endpoint

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for endpoint.

>> Back to Top

sipendpoint.genesyslab.system.log level Jitter

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for Jitter.

>> Back to Top

sipendpoint.genesyslab.system.log_level_Licensing

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for licensing.

>> Back to Top

sipendpoint.genesyslab.system.log_level_Media

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for media.

>> Back to Top

sipendpoint.genesyslab.system.log_level_Privacy

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for privacy.

sipendpoint.genesyslab.system.log level RTP

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for RTP.

>> Back to Top

sipendpoint.genesyslab.system.log_level_Security

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for security.

>> Back to Top

sipendpoint.genesyslab.system.log_level_Storage

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for storage.

>> Back to Top

sipendpoint.genesyslab.system.log_level_STUN

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for STUN.

>> Back to Top

sipendpoint.genesyslab.system.log level Transport

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for transport.

>> Back to Top

sipendpoint.genesyslab.system.log_level_USB Devices

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for USB devices.

>> Back to Top

sipendpoint.genesyslab.system.log_level_Utilities

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for utilities.

>> Back to Top

sipendpoint.genesyslab.system.log_level_Voice Quality

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for voice quality.

>> Back to Top

sipendpoint.genesyslab.system.log level XMPP

Default Value: 0

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

Specifies the log level for XMPP.

sipendpoint.headset-enforce-configured-usage

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the SIP Endpoint must wait for the detection of the headset that is configured in the 'sipendpoint.genesyslab.device.headset_name' option before finalizing initialization. The agent remains logged out until the headset is detected.

>> Back to Top

sipendpoint.headset-replugged-set-ready

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent SIP DN is set automatically to Ready when the headset that is used by the agent is plugged back in.

>> Back to Top

sipendpoint.headset-unplugged.not-ready-reason

Default Value:

Valid Values: A valid not ready reason

Changes Take Effect: When the application is started or restarted.

Specifies the Not Ready reason that is to be set for the SIP DN when the headset that is used by the agent is unplugged and 'sipendpoint.headset-unplugged-set-not-ready' option is set to 'true'.

>> Back to Top

sipendpoint.headset-unplugged-set-not-ready

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the agent SIP DN is set automatically to Not Ready when the headset that is configured for the agent is unplugged.

sipendpoint.init-attempt-nb

Default Value: 10

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

The maximum number of communication attempts between Interaction Workspace and Interaction Workspace SIP Endpoint during initialization. This option works in conjunction with the 'interaction-workspace'/'sipendpoint.init-attempt-timer' option.

>> Back to Top

sipendpoint.init-attempt-timer

Default Value: 1

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

The interval of time, in seconds, between attempts to communicate with the Interaction Workspace SIP Endpoint during initialization. This option works in conjunction with the 'interaction-workspace'/'sipendpoint.init-attempt-nb' option.

>> Back to Top

sipendpoint.log.verbose

Default Value: Trace

Valid Values: Select a value from the following list: All, Debug, Trace, Interaction, Standard, Alarm,

None.

Changes Take Effect: When the application is started or restarted.

Defines the global level of logging for the SIP Endpoint Application. If set to None, there is no log file created for the Interaction Workspace SIP Endpoint

>> Back to Top

sipendpoint.proxies.proxy0.reregister_in_seconds

Default Value: 3600

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

The interval of time, in seconds, before SIP Endpoint tries reregistration of line 1.

sipendpoint.proxies.proxy1.reregister in seconds

Default Value: 3600

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

The interval of time, in seconds, before SIP Endpoint tries reregistration of line 2.

>> Back to Top

sipendpoint.retain-volume-settings-between-sessions

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the headset and microphone volume settings are restored from the settings at the previous session login when Interaction Workspace SIP Endpoint starts.

>> Back to Top

sipendpoint.rtp.2833.enabled

Default Value: 1

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether local support for RFC 2833 out-of-band DTMF is enabled. This option works with the system:dtmf:force_send_in_band option as shown in the following table, where (a) is this option and (b) is the system:dtmf:force_send_in_band option. (a) (b) Result 1 1 Send out-of-band 2833; if that is not acceptable, fall back to in-band. 1 0 Send out-of-band 2833; if that is not acceptable, fall back to INFO . 0 1 Send in-band DTMF. 0 0 Send out-of-band INFO. In-band means that the application encodes the DTMF signals in the audio stream as regular sound. Typically, DTMF is not sent in-band, and is only used in specific situations. See system:dtmf:force_send_in_band for examples.

>> Back to Top

sipendpoint.rtp.2833.hold over time in ms

Default Value: 100

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

If Dtmf.force_send_in_band is set to false and rtp2833enabled is set to true, specifies the minimum length of time, in milliseconds, to send 2833 packets. This setting is useful in the scenario where the agent presses a key for a very short time, to ensure that the packet time is longer than the key press

time.

>> Back to Top

sipendpoint.rtp.2833.packet_time_in_ms

Default Value: 60

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

If Dtmf.force_send_in_band is set to false and rtp2833enabled is set to true, specifies the time, in milliseconds, between 2833 packets. During this time, only audio is sent. This setting is useful in scenarios where back-to-back 2833 packets are handled.

>> Back to Top

sipendpoint.rtp.2833.payload_number

Default Value: 101

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

If Dtmf.force send in band is set to false, specifies the payload number for DTMF.

>> Back to Top

sipendpoint.rtp.inactivity.timer_enabled

Default Value: 0 **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the application should hangup when it detects that the RTP session is inactive.

>> Back to Top

sipendpoint.sbc-register-address

Default Value:

Valid Values: Any valid host name (either with or without a Fully Qualified Domain Name) or IP

Changes Take Effect: When the application is started or restarted.

Specifies the host name or IP Address of the Session Border Controller where the SIP REGISTER request will be sent by Interaction Workspace SIP Endpoint. If this option is empty, the SIP REGISTER request will be sent to the address specified in the option TServer\sip-address of the SIP Server that

monitors this agent's DN. In Business Continuity environment this corresponds to the preferred site registration.

>> Back to Top

sipendpoint.sbc-register-address.peer

Default Value:

Valid Values: Any valid host name (either with or without a Fully Qualified Domain Name) or IP Address.

Changes Take Effect: When the application is started or restarted.

In a Business Continuity environment, specifies the port number on the host of the Session Border Controller where the peer SIP REGISTER request will be sent by Interaction Workspace SIP Endpoint. If this option is empty, the SIP REGISTER request will be sent to the address specified in the option TServer\sip-address of the SIP Server that monitors the peer agent DN.

>> Back to Top

sipendpoint.sbc-register-port

Default Value:

Valid Values: Any valid port number on the host.

Changes Take Effect: When the application is started or restarted.

Specifies the port of the Session Border Controller where the SIP REGISTER request will be sent by Interaction Workspace SIP Endpoint. If the value of this option is empty, the SIP REGISTER request will be sent to the port that is specified by the TServer\sip-port (or TServer\sip-port-tls) option of the SIP Server that monitors the DN of this agent. In a Business Continuity environment, this corresponds to the preferred site registration.

>> Back to Top

sipendpoint.sbc-register-port.peer

Default Value:

Valid Values: Any valid port number on the host.

Changes Take Effect: When the application is started or restarted.

In a Business Continuity environment, this option specifies the port of the Session Border Controller where the peer SIP REGISTER request will be sent by Interaction Workspace SIP Endpoint. If the value of this option is empty, the SIP REGISTER request will be sent to the port that is specified by the TServer\sip-port (or TServer\sip-port-tls) option of the SIP Server that monitors the DN of the peer agent.

sipendpoint.system.diagnostics.enable_logging

Default Value: 1

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether logging is enabled for SIP Endpoint.

>> Back to Top

sipendpoint.system.diagnostics.log_level

Default Value: Error

Valid Values: Specify a value from the following list:

Changes Take Effect: When the application is started or restarted.

Specifies the Log level for SIP Endpoint.

>> Back to Top

sipendpoint.system.dtmf.force_send_in_band

Default Value: 0

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Set this option as described in the option RTP:2833:enabled. Consider sending in-band if you own your gateways, and one or more of your gateways does not support 2833, or does not handle it completely, or your gateway is using codecs that reproduce DTMF tones well. In this scenario, set this option to true to ensure that DTMF tones are passed through (bypass the gateway) and that they reproduce accurately at the receiving end. Also consider sending in-band if one or more of your gateways does not support 2833 or does not handle it completely, or your gateway is using codecs that do not reproduce DTMF tones well because they are designed to handle human voice rather than artificial sounds. In this scenario, setting this option to true will not help to ensure that DTMF tones get through.

>> Back to Top

sipendpoint.system.dtmf.minimum_rfc2833_play_time

Default Value: 40

Valid Values: An integer value.

Changes Take Effect: When the application is started or restarted.

If the Dtmf.ForceSendInBand option is set to false, then use this option to specify the minimum play duration, in milliseconds, for DTMF tones.

>> Back to Top

sipendpoint.system.indialog_notify.enable_indialognotify

Default Value: 1

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether in-dialog Notify is enabled.

>> Back to Top

sipendpoint.system.network.dtx_enabled

Default Value: 0

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether DTX is enabled. When DTX is enabled, transmission to a remote party is suspended when the application detects that the local user is not speaking (silence is not transmitted). If this option is set to False (the default), then non-speaking audio (silence) is transmitted.

>> Back to Top

sipendpoint.system.qos.audio

Default Value: tos 46 **Valid Values:** A valid QOS

Changes Take Effect: When the application is started or restarted.

Specifies the type of QOS (quality of service) that is supported for audio, and if so, whether bandwidth is reserved.

>> Back to Top

sipendpoint.transport-protocol

Default Value: UDP

Valid Values: A value from the following list: UDP.TCP.TLS.

Changes Take Effect: When the application is started or restarted.

Specifies the transport protocol that is used by Interaction Workspace SIP Endpoint for SIP Communication. This option can be used with Interaction Workspace SIP Endpoint 8.0.204 and above.

sipendpoint.tuning.mixer.allow_master_volume_change

Default Value: 0

Valid Values: true, false

Changes Take Effect: When the application is started or restarted.

Specifies whether the master volume is set when the speaker volume is set. If this option is set to false, the wave volume is set instead of the master volume.

>> Back to Top

sms.agent.prompt-color

Default Value:

1. FF385078

Valid Values: Valid Hexadecimal (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the prompt for the messages entered by the agent in the SMS view.

>> Back to Top

sms.agent.text-color

Default Value:

1. FF385078

Valid Values: Valid Hexadecimal (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the text of the messages entered by the agent in the SMS view.

>> Back to Top

sms.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether a SMS interaction is automatically accepted and joined if necessary when a Interaction Server Invite event is received. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

sms.client.prompt-color

Default Value:

1. FF166FFF

Valid Values: Valid Hexadecimal (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the text of the messages entered by the target client in the SMS view.

>> Back to Top

sms.client.text-color

Default Value:

1. FF166FFF

Valid Values: Valid Hexadecimal (HTML) color code

Changes Take Effect: Immediately.

Color of the client text in the SMS view. The HTML format is used to set the value. I.e.: #FFFF0000 for a red color.

>> Back to Top

sms.default-queue

Default Value:

Valid Values: A valid name of a Script of type Interaction Queue.

Changes Take Effect: At the next interaction.

Specifies the Interaction Queue in which new or reply outbound SMS are submitted when an agent clicks Send and before the interaction is placed in outbound queue.

>> Back to Top

sms.from-numbers-business-attribute

Default Value:

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters. **Changes Take Effect:** At the next interaction.

A character string that specifies the name of the Business Attribute that contains the Attribute Values that are used as 'from numbers' of outbound SMS interactions.

>> Back to Top

sms.max-message-number

Default Value: 8

Valid Values: Any valid positive integer. 0 means no maximum.

Changes Take Effect: At the next interaction.

Specifies the maximum number of SMS allowed per message.

>> Back to Top

sms.other-agent.prompt-color

Default Value:

1. FFD88000

Valid Values: Valid Hexadecimal (HTML) color code

Changes Take Effect: Immediately.

Specifies the color of the text of the messages entered by the target agent in the SMS view.

>> Back to Top

sms.other-agent.text-color

Default Value:

1. FFD88000

Valid Values: Valid Hexadecimal (HTML) color code

Changes Take Effect: Immediately.

Color of the other agent text in the SMS view. The HTML format is used to set the value. I.e.: #FFFF0000 for a red color.

>> Back to Top

sms.outbound-queue

Default Value:

Valid Values: Name of a valid Script of type Interaction Queue.

Changes Take Effect: Immediately.

Specifies the Interaction Queue in which outbound SMS are placed when agents click 'Send' (Page mode only). This options is used only when Interaction Workflow does not set 'Queue for New Interactions' when it is routing Inbound SMS to Agents.

>> Back to Top

sms.prompt-for-done

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies if the application prompts a confirmation message when a user clicks the 'done' button. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

sms.ringing-bell

Default Value: Sounds\Ring.mp3

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the path of the sound file that is played when SMS interaction is ringing. For example:

"Sounds\Ring.mp3

>> Back to Top

sms.subject-max-chars

Default Value: 25

Valid Values: An integer value. If set to 0, no subject.

Changes Take Effect: At the next interaction.

Specifies the maximum number of characters from the SMS message that are used to create the message subject in the contact history if the history doesn't contain subject.

>> Back to Top

sms.time-stamp

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

Specifies whether the time stamp is displayed in the SMS transcript area.

>> Back to Top

sms.transcript-time-frame

Default Value: 24

Valid Values: An integer value. If set to 0, no historic area .

Changes Take Effect: At the next interaction.

Specifies the range of time, in hours, in which to search for previous interactions by the same contact to populate the SMS transcript from the contact history. A value of 0 means nothing is added to the contact history.

>> Back to Top

sounds.preloadfiles

Default Value: Sounds\Ring.mp3

Valid Values: A comma-separated list of valid Windows directory paths and file names.

Changes Take Effect: At the next interaction.

Specifies the name and location in the application folder of audio files that are to be pre-loaded when an agent logs in. For Example: "Sounds\Ring.mp3,Sounds\bell.mp3,Sounds\chord.mp3,Sounds\ warning.mp3". The audio files are defined by the options that control sounds, such as voice.ringing-bell and chat.new-message-bell. Files that are not specified by this option are loaded whenever they are needed.

>> Back to Top

spellchecker.corporate-dictionary

Default Value:

Valid Values: Comma-separated list of words

Changes Take Effect: When the application is started or restarted.

Specifies a comma-separated list of dictionary words that conform to the limitations of allowable characters in the configuration layer. Typically you would use this list to specify common words in your company, such as your company name or product name.

spellchecker.corporate-dictionary-file

Default Value:

Valid Values: Absolute or relative path to a text file.

Changes Take Effect: When the application is started or restarted.

Specifies the name and the path to your corporate dictionary file. The path can be relative to the Interaction Workspace working directory (for example: Dictionaries\CorporateDictionary.txt) or an absolute path (for example: C:\PathToDictionaries\CorporateDictionary.txt). The file must consist of a list of words (one word per line) with ANSI, Unicode, UTF-8 encoding (any encoding accepted by Microsoft .NET).

>> Back to Top

standard-response.categories

Default Value: \$All\$

Valid Values: A comma-separated value list of category names or full path category starting at the

root category. \$All\$ to display Standard Responses from all categories.

Changes Take Effect: At the next interaction.

Specifies the list of categories that are used to filter the Standard Responses. Agents see only those standard responses that are part of the subtree of those categories.

>> Back to Top

standard-response.default-search-type

Default Value: AnyKeyword

Valid Values: One of the following values: AnyKeyword, AllKeywords, or ExactText

Changes Take Effect: At the next interaction.

Specifies the default search type that is used to search for text in the Standard Response Library. If empty, the default search type is "AnyKeywords".

>> Back to Top

standard-response.enable-usage-feedback

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the usage information of the Standard Response Library is populated in the interaction record in UCS so that it can be read by the Training Server.

>> Back to Top

standard-response.languages

Default Value: \$All\$

Valid Values: A comma-separated value list of languages. \$All\$ to display Standard Responses from

all languages.

Changes Take Effect: At the next interaction.

Specifies the list of languages that are used to filter the Standard Responses. Agents see only those standard responses that are part of the subtree of the root categories of the specified languages.

>> Back to Top

standard-response.suggested-responses-min-relevancy

Default Value: 50

Valid Values: from 0 to 100

Changes Take Effect: At the next interaction.

Specifies the minimum level of relevancy above which Suggested Responses will be shown from the Standard Response Library.

>> Back to Top

statistics.displayed-statistics

Default Value:

Valid Values: A comma-separated list of Statistic names.

Changes Take Effect: When the application is started or restarted.

Specifies the statistics that are displayed in the Contact Center Statistics tab. The statistics specified by this option match the names of the statistics defined in the options of the Application sections.

>> Back to Top

statistics.queues

Default Value:

Valid Values: A comma-separated list of queue identifiers in the following format:

(<queueNumber>@<switchName>)

Changes Take Effect: When the application is started or restarted.

Specifies the list of queues for which queue statistics are calculated. List of queues can be set through a variable: \$AGENT.LOGINQUEUE\$ (the queue on which the agent logged in), \$AGENTGROUP.ORIGINATIONDNS\$ (the queues set as the origination DNs in the agent groups to

which this agent belongs).

>> Back to Top

statistics.refresh-time

Default Value: 10

Valid Values: An integer value greater than 0.

Changes Take Effect: When the application is started or restarted.

Defines the frequency of notification (in seconds) for statistics.

>> Back to Top

statistics.routing-points

Default Value:

Valid Values: A comma-separated list of Routing Point identifiers in the following format:

(<routingPointNumber>@<switchName>)

Changes Take Effect: When the application is started or restarted.

Specifies the list of routing points for which routing point statistics are calculated.

>> Back to Top

system-tray.tooltip

Default Value: \$Application.Title\$

Valid Values:

\$Application.Title\$,\$Application.Name\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.Employ

Changes Take Effect: When the application is started or restarted.

Defines the tooltip of the Interaction Workspace system tray icon by specifying a string that contains the following field codes: \$Application.Title\$, \$Application.Name\$, \$Agent.UserName\$, \$Agent.EastName\$, \$Agent.FirstName\$, \$Agent.EmployeeId\$. If all field codes are empty, the following field codes are used:\$Application.Title\$.

>> Back to Top

teamcommunicator.add-recent-filters.voice

Default Value:

Valid Values: A comma-separated list of interaction types taken from the following values: internal, external, consultation.

Changes Take Effect: At next interaction event.

Specifies the list of interaction types that composes the filter of voice interactions distributed to the agent that are used to populate the Recent area of Team Communicator. The main party (agent, contact, phone number) of the incoming voice interactions that match this filter will be added to the Recent area of Team Communicator. It is possible to consult the details of the corresponding interactions when hovering the party name in recent area.

>> Back to Top

teamcommunicator.always-clear-textbox-on-new-interaction

Default Value: true **Valid Values:** true, false

Changes Take Effect: Immediately.

When this option is set to true, Interaction Workspace clears the teamcommunicator search textbox when the interaction is initiated by pressing "Enter" or by clicking on one of the medias of teamcommunicator results. When it is set to false, this option clears the teamcommunicator search textbox only when the interaction is initiated by pressing "Enter"

>> Back to Top

teamcommunicator.contact-favorite-fields

Default Value: Category, FirstName, LastName, PhoneNumber, EmailAddress

Valid Values: A comma-separated list of values from the following list: CategoryContact,

FirstName, LastName, PhoneNumber, EmailAddress.

Changes Take Effect: When the application is started or restarted.

The list of fields that are displayed to an agent when adding or editing a favorite that is created from a Contact.

>> Back to Top

teamcommunicator.corporate-favorites

Default Value:

Valid Values: A comma-separated list of favorite names (section names) defined in the Interaction Workspace application.

Changes Take Effect: When the application is started or restarted.

Specifies the favorites that are pre-assigned to the agents. Those favorites will be 'read only' for the agents.

teamcommunicator.corporate-favorites-file

Default Value:

Valid Values: Absolute or relative path to an XML file.

Changes Take Effect: When the application is started or restarted.

Specifies the name and the path to your corporate favorites definition file. The path can be relative to the Interaction Workspace working directory (for example: Favorites\CorporateFavorites.txt) or an absolute path (for example: C:\PathToFavorites\CorporateFavorites.txt). The file must be in XML format. Overrides the teamcommunicator.corporate-favorites option.

>> Back to Top

teamcommunicator.custom-favorite-fields

Default Value: Category, FirstName, LastName, PhoneNumber, EmailAddress

Valid Values: A comma-separated list of values from the following list: Category, FirstName,

LastName, PhoneNumber, EmailAddress.

Changes Take Effect: When the application is started or restarted.

The list of fields that are displayed to an agent when adding or editing a favorite created from a typed phone number or e-mail address.

>> Back to Top

teamcommunicator.internal-favorite-fields

Default Value: Category, DisplayName

Valid Values: A comma-separated value list of values from the following list: Category,

DisplayName.

Changes Take Effect: When the application is started or restarted.

The list of fields that are displayed to an agent when adding or editing a favorite that is created from a named resource.

>> Back to Top

teamcommunicator.list-filter-showing

Default Value: Agent,AgentGroup,Skill,RoutingPoint,Queue,InteractionQueue,Contact **Valid Values:** A comma-separated value list of filter items to be displayed in the team communicator, for example: Agent,AgentGroup,Skill,RoutingPoint,Queue,Contact,InteractionQueue **Changes Take Effect:** When the application is started or restarted.

Specifies the list of filters that an agent can use to search for contacts and internal targets by using the team communicator. The object types are presented in the specified order.

>> Back to Top

teamcommunicator.list-status-reachable

Default Value: NotReady

Valid Values: A comma-separated list of agent status from the following list: NotReady, LoggedOff,

Busy

Changes Take Effect: When the application is started or restarted.

Specifies the list of not-ready statuses for which a target agent can be contacted for consultation, transfer, and conference, requests. If the not-ready status of the target agent is not in the list of allowed statuses, the target agent will not be listed as available for consultation, transfer, and conference requests.

>> Back to Top

teamcommunicator.load-at-startup

Default Value: true **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

This option is used for performance issue at login time (when a lot of agents logs in at the same time). Specifies if all the configuration elements (Agents, Agent Groups, Queues, Routing Points, Skills) needed by Teamcommunicator are loaded at login time. If this option is set to false, the elements are no longer loaded at login time, but the 1st time the focus is placed in the Team Communicator.

>> Back to Top

teamcommunicator.max-suggestion-size

Default Value: 10

Valid Values: An integer value from 1 through 50.

Changes Take Effect: When the application is started or restarted.

Maximum size of the suggestion list that is displayed while an agent is entering a contact or target name.

>> Back to Top

teamcommunicator.recent-max-records

Default Value: 10

Valid Values: An integer value from 1 through 50.

Changes Take Effect: When the application is started or restarted.

The number of recent internal targets to display in the list of recent targets.

>> Back to Top

teamcommunicator.request-start-timer

Default Value: 300

Valid Values: An integer value from 1 through 5000.

Changes Take Effect: When the application is started or restarted.

Request start timer wait interval, in milliseconds, between the last key pressed and the beginning of the search through the contact database.

>> Back to Top

teamlead.agent-status.enabled-agent-group-securitymode

Default Value: true **Valid Values:** true, false

Changes Take Effect: At the next agent search.

Introduced: 8.5.130.04

Specifies that a Team Lead may change the status of an agent only if the agent is a member of an Agent Group that the Team Lead supervises. When set to false, any Team Lead can change the agent's status. Relies on the 'Team Lead - Can Change Agent Status' privilege being granted.

>> Back to Top

teamlead.monitoring-scope

Default Value: call

Valid Values: Select a value from the following list: agent, call

Changes Take Effect: Immediately.

Specifies the scope of monitoring that is to be used for voice interactions in environments that use SIP Server.

- call: The supervisor remains on the call until it is finished. This mode enables barge-in.
- agent: System disconnects the supervisor automatically from the call when the monitored agent leaves the call. In this mode, the barge-in operation is not possible.

toast.case-data.content

Default Value: History, Case Data

Valid Values:

Changes Take Effect: At the next interaction.

Specifies the content of the Case Information area in the interaction preview. The CaseData key enables the display of the attached data that is defined by the interaction.case-data.format-business-attribute option. The History key enables the display of interaction history information. The order of the values defines the order of the Case Data and History information in the Case Information area of the interaction preview. This option can be overridden by a routing strategy, as described in Overriding Options by Using a Routing Strategy.

>> Back to Top

toast.case-data.format-business-attribute

Default Value:

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters. **Changes Take Effect:** At the next interaction

Specifies the name of the Business Attribute that contains the Business Attribute Values that are used to filter and render attached data in the toast interaction preview.

This option can be overridden by a routing strategy as described in Deployment Guide.

You can define the display order of Business Attribute Values by creating an interaction-workspace section in the annex of the Business Attribute, then add the toast.case-data.order option. This option is a comma-separated list of Business Attributes Value Names that specifies the order of the Business Attribute Values. The Attributes Values that are not listed in option toast.case-data.order are put at the bottom of the list.

>> Back to Top

toast.window-title

Default Value: (\$Contact.FirstName\$ \$Contact.LastName\$

Valid Values:

\$Window.Title\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$,\$Interaction.Case (X: name of contact attribute, Y: attached data key name).

Changes Take Effect: Immediately.

Defines the title of the Toast window by specifying a string that contains the following field codes:\$Window.Title\$,\$Agent.UserName\$,\$Agent.LastName\$,\$Agent.FirstName\$,\$Agent.EmployeeId\$,\$Interaction (X: name of contact attribute, Y: attached data key name). If all field codes are empty, the following field codes are used: '\$Window.Title\$ - \$Interaction.MainParty\$'.

views.CaseContactRegion.activate-order

Default Value: InteractionContactInformationView,InteractionContactHistoryView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom

views): InteractionContactInformationView,InteractionContactHistoryView,...

Changes Take Effect: When the views are instantiated.

Specifies the selected (or default) view in the specified region or specifies the order of a list view. If it exists, the first view is the default view. The following URL enumerates all the views and regions: http://docs.genesyslab.com/wiki/index.php?title=Category:Views and Regions

>> Back to Top

views.CaseContactRegion.order

Default Value: InteractionContactInformationView,InteractionContactHistoryView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom

 $views): Interaction Contact Information View, Interaction Contact History View, \dots \\$

Changes Take Effect: When the views are instantiated.

Specifies the order of the views in the specified region. The following URL enumerates all the views and regions: http://docs.genesyslab.com/wiki/index.php?title=Category:Views_and_Regions

>> Back to Top

views.CaseViewSideButtonRegion.order

Default Value: InteractionContainerSideButtonView,SRLSideButtonView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom

views): InteractionContainerSideButtonView,SRLSideButtonView,...

Changes Take Effect: When the views are instantiated.

Specifies the order of the views in the specified region. The following URL enumerates all the views and regions: http://docs.genesyslab.com/wiki/index.php?title=Category:Views_and_Regions

>> Back to Top

views.ContactInfoHistoryMultiRegion.activate-order

Default Value: ContactInformationView,ContactHistoryView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom

views): ContactInformationView,ContactHistoryView,... **Changes Take Effect:** When the views are instantiated.

Specifies the selected (or default) view in the specified region or specifies the order of a list view. If it exists, the first view is the default one. The following URL enumerates all the views and regions:

http://docs.genesyslab.com/wiki/index.php?title=Category:Views and Regions

>> Back to Top

views.ContactInfoHistoryMultiRegion.order

Default Value: ContactInformationView,ContactHistoryView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom

views): ContactInformationView,ContactHistoryView,... **Changes Take Effect:** When the views are instantiated.

Specifies the order of the views in the specified region. The following URL enumerates all the views and regions: http://docs.genesyslab.com/wiki/index.php?title=Category:Views_and_Regions

>> Back to Top

views.ContactTabBottomHistoryMultiRegion.activate-order

Default Value: ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView **Valid Values:** A comma-separated list of valid view names from the following list (plus the custom views): ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView,... **Changes Take Effect:** When the views are instantiated.

Specifies the selected (or default) view in the specify region or specifies the order of a list of view. If it exists, the first view is the default one. The following URL enumerates all the views and regions: http://docs.genesyslab.com/wiki/index.php?title=Category:Views and Regions

>> Back to Top

views.ContactTabBottomHistoryMultiRegion.order

Default Value: ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView **Valid Values:** A comma-separated list of valid view names from the following list (plus the custom views): ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView,... **Changes Take Effect:** When the views are instantiated.

Specifies the order of the views in the specified region. The following URL enumerates all the views and regions: http://docs.genesyslab.com/wiki/index.php?title=Category:Views and Regions

>> Back to Top

views.InteractionDetailsRegion.activate-order

Default Value: NotepadVoiceNotepadView.DispositionsView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom

views): NotepadVoiceNotepadView,DispositionsView,... **Changes Take Effect:** When the views are instantiated.

Specifies the selected (or default) view in the specified region or specifies the order of a list view. If it exists, the first view is the default view. The following URL enumerates all the views and regions: http://docs.genesyslab.com/wiki/index.php?title=Category:Views_and_Regions

>> Back to Top

views.InteractionDetailsRegion.order

Default Value: DispositionsView,NotepadVoiceNotepadView

Valid Values: A comma-separated list of valid view names from the following list (plus the custom

views): DispositionsView,NotepadVoiceNotepadView,... **Changes Take Effect:** When the views are instantiated.

Specifies the order of the views in the specified region. The following URL enumerates all the views and regions: http://docs.genesyslab.com/wiki/index.php?title=Category:Views_and_Regions

>> Back to Top

views.ToolbarWorkplaceRegion.activate-order

Default Value:

MyPlaceStatusView,myCampaignsListView,MyContactHistory,MyStatisticsView,MyCallCenterStatisticsView **Valid Values:** A comma-separated list of valid view names from the following list (plus the custom views):

MyPlaceStatusView,myCampaignsListView,MyContactHistory,MyStatisticsView,MyCallCenterStatisticsView,... **Changes Take Effect:** When the views are instantiated.

To indicate the selected (or default) view in the specified region, specifies an ordered list of view. If it exists, the first view is the default one. The following URL enumerates all the views and regions: http://docs.genesyslab.com/wiki/index.php?title=Category:Views_and_Regions

>> Back to Top

views.ToolbarWorkplaceRegion.order

Default Value:

MyPlaceStatusView,myCampaignsListView,MyContactHistory,MyStatisticsView,MyCallCenterStatisticsView **Valid Values:** A comma-separated list of valid view names from the following list (plus the custom views):

MyPlaceStatusView,myCampaignsListView,MyContactHistory,MyStatisticsView,MyCallCenterStatisticsView,... **Changes Take Effect:** When the views are instantiated.

Specifies the order of the views in the specified region. The following URL enumerates all the views and regions: http://docs.genesyslab.com/wiki/index.php?title=Category:Views and Regions

views.ToolbarWorksheetButtonRegion.order

Default Value:

MyWorkplaceButtonView,MainToolbarWorkbinsContainerButtonView,MainToolbarContainerButtonView,M

MyWorkplaceButtonView,MainToolbarWorkbinsContainerButtonView,MainToolbarContainerButtonView,M

Specifies the order of the views in the specified region. The following URL enumerates all the views and regions: http://docs.genesyslab.com/wiki/index.php?title=Category:Views and Regions

>> Back to Top

views.WorkbinsTabBottomHistoryMultiRegion.activateorder

Default Value: ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView **Valid Values:** A comma-separated list of valid view names from the following list (plus the custom views): ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView,... **Changes Take Effect:** When the views are instantiated.

Specifies the selected (or default) view in the specify region or specifies the order of a list view. If it exists, the first view is the default one. The following URL enumerates all the views and regions: http://docs.genesyslab.com/wiki/index.php?title=Category:Views_and_Regions

>> Back to Top

views.WorkbinsTabBottomHistoryMultiRegion.order

Default Value: ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView **Valid Values:** A comma-separated list of valid view names from the following list (plus the custom views): ContactDetailView,ContactHistoryNotepadView,ContactHistoryCaseDataView,... **Changes Take Effect:** When the views are instantiated.

Specifies the order of the views in the specified region. The following URL enumerates all the views and regions: http://docs.genesyslab.com/wiki/index.php?title=Category:Views and Regions

>> Back to Top

voice.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specify whether a voice interaction is automatically answered when a TServer Ringing event is received. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

voice.dtmf-inactivity-typing-timeout

Default Value: 500

Valid Values: from 0 to MAXINT

Changes Take Effect: At the next interaction.

Defines the inactivity duration, in milliseconds, after which any buffered digits will be sent. A value of 0 means that each digit will be sent individually.

>> Back to Top

voice.enable-init-conference

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether the 'Initiate Transfer' and 'Initiate Conference' functions are displayed as separate actions to the Agent in the 'Consultation' area. When this option is set to 'false', the single menu item 'Start Voice Consultation' is displayed. This menu item triggers the 'Initiate Transfer' function.

>> Back to Top

voice.enable-make-call-consultation

Default Value: false **Valid Values:** true, false

Changes Take Effect: When the application is started or restarted.

Specify whether a voice consultation is done through a MakeCall event instead of an InitTransfer/InitConference when the primary call is already held.

>> Back to Top

voice.mark-done-on-release

Default Value: false **Valid Values:** true. false

Changes Take Effect: At the next interaction.

Specify if an interaction should be closed automatically if a TServer Release event is received. This

option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

voice.one-step-trsf-mode

Default Value: default

Valid Values: Select at least one item from the list.

Changes Take Effect: When the application is started or restarted.

Specifies the type of one-step transfer. If you specify default, the one step transfer operation is 'single-step-transfer' when it is supported by your switch, or 'mute-transfer' if single step transfer is not supported by your switch.

>> Back to Top

voice.prompt-for-end

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether Interaction Workspace displays a confirmation message when the agent clicks 'End'. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

voice.ringing-bell

Default Value: Sounds\Ring.mp3

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the voice channel ringing sound-configuration string. For example: "Sounds\Ring.mp3

>> Back to Top

webcallback.auto-answer

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether a Web Callback interaction is automatically accepted when Interaction Server Invite event is received. This option can be overridden by a routing strategy as described in Deployment Guide.

. -

>> Back to Top

webcallback.auto-dial

Default Value: false **Valid Values:** true, false

Changes Take Effect: At the next interaction.

Specifies whether Callback Phone Number is automatically dialed when an Interaction Web Callback is accepted. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

webcallback.callback-information.content

Default Value: Subject, Phone Number, Type, Scheduled Date, Contact Time, Local Time, Former Attempts **Valid Values:** A comma separated list of items within the following list: Subject, Phone Number, Type,

ScheduledDate, ContactTime, LocalTime, FormerAttempts, Result.

Changes Take Effect: At the next interaction.

Defines the callback data that is displayed in the Callback Information Area. The callback data entries are displayed in the order in which they appear in the list.

>> Back to Top

webcallback.callback-information.frame-color

Default Value:

1. FFDFE8F6

Valid Values: Valid Hexadecimal (HTML) color code **Changes Take Effect:** At the next interaction.

Specifies the color of the border of the Callback Information view frame of Web Callback interactions. Examples: #FFFFBA00 for a Gold color, #FF6F7074 for a Silver color, #FFB8400B for a Bronze color. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

webcallback.callback-information.header-foreground-color

1. FF15428B

Valid Values: Valid Hexadecimal (HTML) color code **Changes Take Effect:** At the next interaction.

Specifies the color of the foreground of the Callback Information view frame of Web Callback interactions. Example #FFFFFFFF for white color. This option can be overridden by a routing strategy as described in Deployment Guide.

>> Back to Top

webcallback.complete-queue

Default Value:

Valid Values: Name of a valid Script of type Interaction Queue.

Changes Take Effect: Immediately.

Specifies the Interaction Queue in which Web Callback interactions are placed when an agent marks one as processed.

>> Back to Top

webcallback.park-queue

Default Value:

Valid Values: Name of a valid Script of type Interaction Queue.

Changes Take Effect: Immediately.

Specifies the Interaction Queue in which the parent Web Callback interaction is placed when an agent transfers a voice call that is created from a Web Callback interaction.

>> Back to Top

webcallback.reschedule-queue

Default Value:

Valid Values: Name of a valid Script of type Interaction Queue.

Changes Take Effect: Immediately.

Specifies the Interaction Queue in which Web Callback interactions are placed when an agent reschedules one and marks it as processed.

>> Back to Top

webcallback.ringing-bell

Default Value: Sounds\Ring.mp3

Valid Values: All special characters that are valid Windows file path, '

Changes Take Effect: At the next interaction.

Specifies the path of the sound file that is played when Web Callback interaction is delivered to the agent. For example: "Sounds\Ring.mp3

>> Back to Top

webproxy.address

Default Value:

Valid Values: An empty address to specify the default proxy configuration of Microsoft Internet Explorer, a valid proxy address (for example: http://my-proxy-server:3128), "None", or an invalid address to use no proxy at all.

Changes Take Effect: At the next interaction.

Specifies the web proxy host address that is used to download content from external web sites. This applies for example to the images that are contained in the e-mail body or to the pushed chat pages.

>> Back to Top

webproxy.password

Default Value:

Valid Values: The password of the proxy credentials. Leave empty to not use any credentials. **Changes Take Effect:** At the next interaction.

Specifies the password to be used to access the web proxy that is used to download content from external web sites. This applies for example to the images that are contained in the e-mail body or to the pushed chat pages.

>> Back to Top

webproxy.username

Default Value:

Valid Values: The username of the proxy credentials. Leave empty to not use any credentials. **Changes Take Effect:** At the next interaction.

Specifies the username to be used to access the web proxy that is used to download content from external web sites. This applies for example to the images that are contained in the e-mail body or to the pushed chat pages.

>> Back to Top

workbin.email.draft

Default Value:

Valid Values: The name of a valid Script object of type Interaction Workbin that is owned by Agents. **Changes Take Effect:** When the application is started or restarted.

The name of the Workbin to be used to store draft e-mail.

>> Back to Top

workbin.email.draft.displayed-columns

Default Value: To, Subject, Submitted

Valid Values: A comma-separated list of Interaction Server interaction properties, for example:

From, Subject, Received

Changes Take Effect: When the application is started or restarted.

The list of interaction fields that are displayed as columns of the workbin that stores Draft e-mail interactions.

>> Back to Top

workbin.email.in-progress

Default Value:

Valid Values: The name of a valid Script object of type Interaction Workbin that is owned by Agents. **Changes Take Effect:** When the application is started or restarted.

The name of the workbin that is to be used to store inbound e-mail for later processing, after an agent explicitly saved the e-mail or submitted an outbound reply.

>> Back to Top

workbin.email.in-progress.displayed-columns

Default Value: From, Subject, Received

Valid Values: A comma-separated list of Interaction Server interaction properties, for example:

From.Subject.Received

Changes Take Effect: When the application is started or restarted.

The list of interaction fields that are displayed as columns of the workbin that stores In-Progress email interactions.

>> Back to Top

workbin.<media-type>.<workbin-nickname>

Default Value:

Valid Values: The name of a valid Script object of type Interaction Workbin.

Changes Take Effect: When the application is started or restarted.

The name of the workbin that is to be used to store interactions of a particular workitem media type. Agents can open interactions from this workbin but not save interactions in it.

>> Back to Top

workbin.<media-type>.<workbin-nickname>.displayed-columns

Default Value: From, To, Subject, Received

Valid Values: A comma-separated list of Interaction Server interaction properties, for example:

From, Subject, Received

Changes Take Effect: When the application is started or restarted.

The list of interaction fields that are displayed as columns of the specified workbin.

>> Back to Top

workbin.<media-type>.in-progress

Default Value:

Valid Values: The name of a valid Script object of type Interaction Workbin, that is owned by Agents. **Changes Take Effect:** When the application is started or restarted.

The name of the workbin to be used to store In-Progress workitems of the specified media type.

>> Back to Top

workbin.<media-type>.in-progress.displayed-columns

Default Value: From, To, Subject, Received

Valid Values: A comma-separated list of Interaction Server interaction properties, for example:

From, Subject, Received

Changes Take Effect: When the application is started or restarted.

The list of interaction fields that are displayed as columns of the workbin that stores In Progress workitems of specified media type.

>> Back to Top

Team Communicator Presence Options

The following option groups enable agents to view queue, interaction queue, and routing point statistics information in Team Communicator. Refer to the Enabling Team Communicator Calling Features and Enabling the E-Mail Channel for information about how to use these options.

- interaction-queue-presence
- queue-presence
- routing-point-presence

interaction-queue-presence Section

The interaction queue presence options enable agents to view interaction queue statistics information in Team Communicator. Refer to the Enabling Team Communicator Calling Features and Enabling the E-Mail Channel for information about how to use these options.

error-level

statistic-text

statistic-name

warning-level

For information about how to use these options to configure Genesys Web Services functionality and behavior, refer to the *Workspace Desktop Edition Deployment Guide*.

error-level

Default Value: 10

Valid Values: An integer or a double value.

Changes Take Effect: When the application is started or restarted.

The value at which a statistic is considered to be at the upper threshold level.

statistic-name

Default Value:

Valid Values: A valid name of a Stat Server's statistic.

Changes Take Effect: When the application is started or restarted.

The name of the statistic that is used to evaluate interaction queue presence.

statistic-text

Default Value: interaction(s) waiting.

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters.

Changes Take Effect: When the application is started or restarted.

The text displayed beside the statistic value.

warning-level

Default Value: 5

Valid Values: An integer or a double value.

Changes Take Effect: When the application is started or restarted.

The value at which a statistic is considered to be at the warning level.

queue-presence Section

The queue presence options enable agents to view queue statistics information in Team Communicator. Refer to the Enabling Team Communicator Calling Features and Enabling the E-Mail Channel for information about how to use these options.

error-level

statistic-text

statistic-name

· warning-level

For information about how to use these options to configure Genesys Web Services functionality and behavior, refer to the *Workspace Desktop Edition Deployment Guide*.

error-level

Default Value: 10

Valid Values: An integer or a double value.

Changes Take Effect: When the application is started or restarted.

The value at which a statistic is considered to be at the upper threshold level.

statistic-name

Default Value: CurrNumberWaitingCalls

Valid Values: A valid name of a statistic server statistic queue. **Changes Take Effect:** When the application is started or restarted.

The name of the statistic used to evaluate presence for queues.

statistic-text

Default Value: interaction(s) waiting.

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters.

Changes Take Effect: When the application is started or restarted.

The text that is displayed beside the statistic value for queues.

warning-level

Default Value: 5

Valid Values: An integer or a double value.

Changes Take Effect: When the application is started or restarted.

The value at which a statistic is considered to be at the warning level.

routing-point-presence Section

The routing point presence options enable agents to view routing point statistics information in Team Communicator. Refer to the Enabling Team Communicator Calling Features and Enabling the E-Mail Channel for information about how to use these options.

error-level

statistic-text

statistic-name

· warning-level

For information about how to use these options to configure Genesys Web Services functionality and behavior, refer to the *Workspace Desktop Edition Deployment Guide*.

error-level

Default Value: 10

Valid Values: An integer or a double value.

Changes Take Effect: When the application is started or restarted.

The value at which a statistic is considered to be at the upper threshold level.

statistic-name

Default Value: CurrNumberWaitingCalls

Valid Values: A valid name of a statistic server statistic queue. **Changes Take Effect:** When the application is started or restarted.

The name of the statistic used to evaluate the presence for Routing Points.

statistic-text

Default Value: interaction(s) waiting.

Valid Values: Letters A to Z and a to z. Numbers 0 through 9. The underscore and space characters.

Changes Take Effect: When the application is started or restarted.

The text displayed beside the statistic value.

warning-level

Default Value: 5

Valid Values: An integer or a double value.

Changes Take Effect: When the application is started or restarted.

The value at which a statistic is considered to be at the warning level.

Change History

Content under development