

## **GENESYS**

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Engage Digital (eServices)

**SMS Server** 

## SMS Server

Options for this component are contained in the following configuration sections:

- channel-any name for mms mm7
- channel-any\_name\_for\_sms
- endpoints:tenant\_dbid
- log

- log-filter
- log-filter-data
- settings

## Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

**Power users: Download a CSV file** containing default and valid values and descriptions.

The following options are configured at the application level (in other words, on the application object).

Section	Option	Default	Changes Take Effect
channel- any_name_for_mms_mm7	driver-classname	com.genesyslab.mcr.smse	erA&techæstæltsms_mms.jsm
channel- any_name_for_mms_mm7		tenant_dbid:endpoint_nam	ne <u>Aft<b>er_Me</b>MS</u> art
channel- any_name_for_mms_mm7		180	After restart
channel- any_name_for_mms_mm7		false	Immediately
channel- any_name_for_mms_mm7		jsms-mm7.conf	After restart
channel- any_name_for_sms	default-reply-address	No default value	After restart
channel- any_name_for_sms	driver-classname	com.genesyslab.mcr.smse	er <b>Aébechæstær</b> ksms_mms.ope
channel-	inbound-route	No default value	After restart
Section	Option	Default	<b>Changes Take Effect</b>

Section	Option	Default	<b>Changes Take Effect</b>
any_name_for_sms			
channel- any_name_for_sms	password	No default value	After restart
channel- any_name_for_sms	reconnection-timeout	180	After restart
channel- any_name_for_sms	session-by-address	No default value	After restart
channel- any_name_for_sms	session-by-text	No default value	After restart
channel- any_name_for_sms	x-debug-mode	false	Immediately
channel- any_name_for_sms	x-smpp-address-range	No default value	After restart
channel- any_name_for_sms	x-smpp-bind-mode	auto	After restart
channel- any_name_for_sms	x-smpp-comms-timeout	60	After restart
channel- any_name_for_sms	x-smpp-delivery-report	noreports	After restart
channel- any_name_for_sms	x-smpp-dest-addr-npi	1	After restart
channel- any_name_for_sms	x-smpp-dest-addr-ton	1	After restart
channel- any_name_for_sms	x-smpp-empty-message	No default value	After restart
channel- any_name_for_sms	x-smpp-enquire-link- timeout	60	After restart
channel- any_name_for_sms	x-smpp-extraopt	No default value	After restart
channel- any_name_for_sms	x-smpp-host	No default value	After restart
channel- any_name_for_sms	x-smpp-inbound-enc- default	301	After restart
channel- any_name_for_sms	x-smpp-outbound-enc- default	301	After restart
channel- any_name_for_sms	x-smpp-port	No default value	After restart
channel- any_name_for_sms	x-smpp-receive-timeout	60	After restart
channel- any_name_for_sms	x-smpp-response-max- waiting-time	30000	After restart
channel- any_name_for_sms	x-smpp-sar-max- segments	255	After restart
Section	Option	Default	<b>Changes Take Effect</b>

Section	Option	Default	<b>Changes Take Effect</b>
channel- any_name_for_sms	x-smpp-sar-prompt- responses	false	After restart
channel- any_name_for_sms	x-smpp-service-type	No default value	After restart
channel- any_name_for_sms	x-smpp-src-addr-npi	1	After restart
channel- any_name_for_sms	x-smpp-src-addr-ton	1	After restart
channel- any_name_for_sms	x-smpp-submit-max- rate	10	After restart
channel- any_name_for_sms	x-smpp-submit-window- size	10	After restart
channel- any_name_for_sms	x-smpp-system-id	No default value	After restart
channel- any_name_for_sms	x-smpp-system-type	No default value	After restart
channel- any_name_for_sms	x-smpp-ucs2-enc- schema	UCS-2BE	After restart
channel- any_name_for_sms	x-smpp-use-msg- payload	false	After restart
channel- any_name_for_sms	x-smpp-validity-period	No default value	After restart
endpoints:tenant_dbid	endpoint_name_for_MMS	No default value	After restart
endpoints:tenant_dbid	endpoint_name_for_SMS_	p <b>alyping</b> efault value	After restart
log	all	stdout	Immediately
log	buffering	false	Immediately
log	expire	10	Immediately
log	messagefile	smserver.lms	Immediately
log	segment	100MB	Immediately
log	standard	stdout	Immediately
log	time-format	ISO8601	Immediately
log	trace	stdout	Immediately
log	verbose	standard	Immediately
log-filter	default-filter-type	сору	Immediately
log-filter-data	sample_name	hide	Immediately
settings	esp-proc-timeout	60	After restart
settings	hide-attached-data	true	After restart
settings	logging-filter-active	false	After restart
settings	session-chat-request- timeout	40	After restart
Section	Option	Default	<b>Changes Take Effect</b>

Section	Option	Default	<b>Changes Take Effect</b>
settings	session-max-number	10	After restart
settings	session-shutdown- timeout	180	After restart
settings	subject-size	25	After restart
settings	workspace-location	No default value	After restart
Section	Option	Default	<b>Changes Take Effect</b>