



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

## Genesys Engage Digital (eServices)

Classification Server and Training Server

12/12/2025

# Classification Server and Training Server

The options for these two components are the same, except that Training Server does not have a **[license]** section.

Options for this component are contained in the following configuration sections:

- [engine](#)
- [license](#)
- [log](#)
- [log-extended](#)
- [log-filter](#)
- [log-filter-data](#)
- [settings](#)

## Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

**Power users:** [Download a CSV file](#) containing default and valid values and descriptions.

The following options are configured at the application level (in other words, on the application object).

Section	Option	Default	Changes Take Effect
engine	<a href="#">log-level</a>	standard	Immediately
engine	<a href="#">log-path</a>	CEngineLog	Immediately
engine	<a href="#">screen-match-all</a>	false	After restart
engine	<a href="#">screen-timeout</a>	15000	After restart
engine	<a href="#">subject-body-header</a>	false	After restart
engine	<a href="#">treat-empty-as-false</a>	false	Immediately
license	<a href="#">license-file</a>	No default value	At start/restart
log	<a href="#">all</a>	stdout	Immediately
log	<a href="#">buffering</a>	false	Immediately
log	<a href="#">expire</a>	10	Immediately
log	<a href="#">log4j2-config-profile</a>	log4j2.xml	After restart
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
log	messagefile	km-server.lms	Immediately
log	segment	100MB	Immediately
log	standard	stdout	Immediately
log	time-format	ISO8601	Immediately
log	trace	stdout	Immediately
log	verbose	standard	Immediately
log-extended	logger-instr-id	com.genesyslab.platform:level-fast	After restart
log-extended	logger-psdk	com.genesyslab.platform:level-fast	After restart
log-filter	default-filter-type	copy	Immediately
log-filter	string-max-print-size	128	Immediately
log-filter-data	sample_name	hide	Immediately
settings	hide-attached-data	true	Immediately
settings	logging-filter-active	false	After restart
settings	logging-filter-spec	logging-filter-default.json	After restart
settings	logging-max-message-size	5000	
Section	Option	Default	Changes Take Effect