

GENESYS

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

intelligent Workload Distribution

iWD History Node Server

iWD History Node Server

Options for this component are contained in the following configuration sections:

access-log

• log

• iWD

server

Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

Power users: Download a CSV file containing default and valid values and descriptions.

The following options are configured at the application level (in other words, on the application object).

Section	Option	Default	Changes Take Effect
access-log	archive	false	After restart
access-log	archived-file-count	5	After restart
access-log	archived-log-filename- pattern		After restart
access-log	log-filename	/GCTI/iWD/ iwd_history_access.log	After restart
access-log	log-to-console	false	After restart
access-log	log-to-file	true	After restart
access-log	max-file-size		After restart
access-log	max-history	5	After restart
access-log	time-zone	UTC	After restart
iWD	allow-listed-attributes		After restart
iWD	batch-size	1000	After restart
iWD	block-listed-attributes		After restart
iWD	migrate-schema	false	After restart
iWD	process-dm	true	After restart
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
iWD	process-gtl	true	After restart
iWD	processor-threads	10	After restart
iWD	receive-timeout	10	After restart
iWD	stop-processing	remove	After restart
iWD	stop-processing-delay	60	After restart
iWD	stop-processing-interval	60	After restart
iWD	taskEventLimit		After restart
log	archive	false	After restart
log	archived-file-count	5	After restart
log	archived-log-filename- pattern		After restart
log	centralized-log-level	STANDARD	After restart
log	centralized-logging	false	After restart
log	console-log-level		After restart
log	file-log-level		After restart
log	level	INFO	After restart
log	log-filename	/GCTI/iWD/ iwd_history.log	After restart
log	log-to-console	false	After restart
log	log-to-file	true	After restart
log	max-file-size		After restart
log	max-history	5	After restart
log	time-zone	UTC	After restart
server	single-host-bind	false	After restart
Section	Option	Default	Changes Take Effect