



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# Stat Server Deployment Guide

## Appendix B: Log Events

---

## Contents

- 1 Appendix B: Log Events
  - 1.1 Overview
  - 1.2 02-10067
  - 1.3 02-10068
  - 1.4 02-10069
  - 1.5 02-10070
  - 1.6 02-10071
  - 1.7 02-10072
  - 1.8 02-10073
  - 1.9 02-10074
  - 1.10 02-10075
  - 1.11 02-10077
  - 1.12 02-10078
  - 1.13 02-10080
  - 1.14 02-10081
  - 1.15 02-10082
  - 1.16 02-10084
  - 1.17 02-10085
  - 1.18 02-10086
  - 1.19 02-10087

# Appendix B: Log Events

## Overview

The following log events have been added since the most recent update to the Framework Combined Log Events Help. Refer to the [Combined Log Events Help](#) for information about the log events that do not appear in this appendix.

02-100271002810029100291002110022100231002410025100271002810029100211002210024100251002610087

### 02-10067

|                       |   |
|-----------------------|---|
| <b>Level</b>          | Standard  |
| <b>Text</b>           | Application failed to restore session with Config Server              |
| <b>Attributes</b>     | None  |
| <b>Description</b>    | An application failed to restore a session with Configuration Server. |
| <b>Alarm Advisory</b> | None  |
| <b>Actions</b>        | No action is required.  |

### 02-10068

|                       |  |
|-----------------------|--|
| <b>Level</b>          | Standard   |
| <b>Text</b>           | Name uniqueness violation for <agent or place> 'name: string' (tenant 'name: string') (old dbid=<positive integer value>, new dbid=<positive integer value>) |
| <b>Attributes</b>     | Object type: agent or place<br>Object name<br>Tenant name<br>Old object DBID<br>New object DBID  |
| <b>Description</b>    | Reports a situation when Stat Server detects the presence of two agent or place objects with the same type and name but different DBIDs.                     |
| <b>Alarm Advisory</b> | Remove duplicates in the Configuration Server database.  |

---

|                |                        |
|----------------|------------------------|
| <b>Actions</b> | No action is required. |
|----------------|------------------------|

## 02-10069

|                       |  |
|-----------------------|--|
| <b>Level</b>          | Standard   |
| <b>Text</b>           | Building virtual agent groups on tenant '[name1]', [Percentage] percent complete   |
| <b>Attributes</b>     | [name1]<br>Name of a tenant as defined in the Configuration Server database<br><br>[Percentage]<br>Positive integer value in the range [0-100] |
| <b>Description</b>    | Reports progress of building Virtual Agent Groups on a tenant during the Stat Server initialization.   |
| <b>Alarm Advisory</b> | None   |
| <b>Actions</b>        | No action is required.   |

## 02-10070

|                       |  |
|-----------------------|--|
| <b>Level</b>          | Standard   |
| <b>Text</b>           | Overload detected on '[thread]' ([Percentage] current CPU usage)                         |
| <b>Attributes</b>     | [thread]<br>Thread ID<br><br>[Percentage]<br>Positive integer value in the range [0-100] |
| <b>Description</b>    | Stat Server switches from NORMAL to OVERLOAD state.                                      |
| <b>Alarm Advisory</b> | None   |
| <b>Actions</b>        | No action is required.   |

## 02-10071

|                   |   |
|-------------------|---|
| <b>Level</b>      | Standard  |
| <b>Text</b>       | Overload ended on '[thread]' ([Percentage] current CPU usage) |
| <b>Attributes</b> | [thread]  |

---

---

|                       |  |
|-----------------------|--|
|                       | Thread ID<br>[Percentage]<br>Positive integer value in the range [0-100] |
| <b>Description</b>    | Stat Server switches to NORMAL state.                                    |
| <b>Alarm Advisory</b> | None   |
| <b>Actions</b>        | No action is required.   |

## 02-10072

|                       |  |
|-----------------------|--|
| <b>Level</b>          | Standard   |
| <b>Text</b>           | Overload recovery started on '[thread]' ([Percentage] current CPU usage)             |
| <b>Attributes</b>     | [thread]<br>Thread ID<br>[Percentage]<br>Positive integer value in the range [0-100] |
| <b>Description</b>    | Stat Server switches from OVERLOAD to RECOVERY state.                                |
| <b>Alarm Advisory</b> | None   |
| <b>Actions</b>        | No action is required.   |

## 02-10073

|                       |  |
|-----------------------|--|
| <b>Level</b>          | Standard   |
| <b>Text</b>           | Overload recovery failed on '[thread]' ([Percentage] current CPU usage)              |
| <b>Attributes</b>     | [thread]<br>Thread ID<br>[Percentage]<br>Positive integer value in the range [0-100] |
| <b>Description</b>    | Stat Server switches from RECOVERY to OVERLOAD state.                                |
| <b>Alarm Advisory</b> | None   |
| <b>Actions</b>        | No action is required.   |

---

## 02-10074

|                       |   |
|-----------------------|---|
| <b>Level</b>          | Standard                                    |
| <b>Text</b>           | Overload protection on '[thread]' activated |
| <b>Attributes</b>     | [thread]<br>Thread ID                       |
| <b>Description</b>    | Overload protection is activated.           |
| <b>Alarm Advisory</b> | None  |
| <b>Actions</b>        | No action is required.                      |

## 02-10075

|                       |   |
|-----------------------|---|
| <b>Level</b>          | Standard                                      |
| <b>Text</b>           | Overload protection on '[thread]' deactivated |
| <b>Attributes</b>     | [thread]<br>Thread ID                         |
| <b>Description</b>    | Overload protection is deactivated.           |
| <b>Alarm Advisory</b> | None  |
| <b>Actions</b>        | No action is required.                        |

## 02-10077

|                       |  |
|-----------------------|--|
| <b>Level</b>          | Standard   |
| <b>Text</b>           | Budget model is enabled on tenant '[name]'                                 |
| <b>Attributes</b>     | [name]<br>Name of a tenant as defined in the Configuration Server database |
| <b>Description</b>    | The budget model is enabled on the specified Tenant.                       |
| <b>Alarm Advisory</b> | None   |
| <b>Actions</b>        | No action is required.   |

## 02-10078

|              |   |
|--------------|---|
| <b>Level</b> | Standard                                    |
| <b>Text</b>  | Budget model is disabled on tenant '[name]' |

---

---

|                       |  |
|-----------------------|--|
| <b>Attributes</b>     | [name]<br>Name of a tenant as defined in the Configuration Server database |
| <b>Description</b>    | The budget model is disabled on the specified Tenant.                      |
| <b>Alarm Advisory</b> | None   |
| <b>Actions</b>        | No action is required.   |

## 02-10080

|                       |  |
|-----------------------|--|
| <b>Level</b>          | Standard   |
| <b>Text</b>           | Invalid filter: '[name]' = '[value]'                 |
| <b>Attributes</b>     | [name]<br>Filter name<br><br>[value]<br>Filter value |
| <b>Description</b>    | Invalid filter is detected.                          |
| <b>Alarm Advisory</b> | None   |
| <b>Actions</b>        | No action is required.                               |

## 02-10081

|                       |  |
|-----------------------|--|
| <b>Level</b>          | Standard   |
| <b>Text</b>           | Invalid time-range: '[name]' = '[value]'                     |
| <b>Attributes</b>     | [name]<br>Time-range name<br><br>[value]<br>Time-range value |
| <b>Description</b>    | Invalid time-range is detected.                              |
| <b>Alarm Advisory</b> | None   |
| <b>Actions</b>        | No action is required.                                       |

## 02-10082

|              |  |
|--------------|--|
| <b>Level</b> | Trace  |
| <b>Text</b>  | Large kv-list ([number] bytes) in CurrentState value |

---

|                       |  |
|-----------------------|--|
| <b>Attributes</b>     | [number]<br>A number of bytes in the sent key-value list.                            |
| <b>Description</b>    | Large key-value lists (over 65K) in the CurrentState statistic's value are detected. |
| <b>Alarm Advisory</b> | None   |
| <b>Actions</b>        | No action is required.   |

## 02-10084

|                       |  |
|-----------------------|--|
| <b>Level</b>          | Standard   |
| <b>Text</b>           | Normal configuration monitoring mode started     |
| <b>Attributes</b>     | None   |
| <b>Description</b>    | Normal configuration monitoring mode is started. |
| <b>Alarm Advisory</b> | None   |
| <b>Actions</b>        | No action is required.                           |

## 02-10085

|                       |   |
|-----------------------|---|
| <b>Level</b>          | Standard  |
| <b>Text</b>           | Normal configuration monitoring mode stopped (duration='[number]' sec)      |
| <b>Attributes</b>     | [number]<br>Duration (in seconds) of how long Stat Server was in that mode. |
| <b>Description</b>    | Normal configuration monitoring mode is stopped.                            |
| <b>Alarm Advisory</b> | None  |
| <b>Actions</b>        | No action is required.  |

## 02-10086

|                       |   |
|-----------------------|---|
| <b>Level</b>          | Standard  |
| <b>Text</b>           | Protected configuration monitoring mode started     |
| <b>Attributes</b>     | None  |
| <b>Description</b>    | Protected configuration monitoring mode is started. |
| <b>Alarm Advisory</b> | None  |
| <b>Actions</b>        | No action is required.                              |

---



02-10087

|                       |   |
|-----------------------|---|
| <b>Level</b>          | Standard  |
| <b>Text</b>           | Protected configuration monitoring mode stopped (duration='[number]' sec)   |
| <b>Attributes</b>     | [number]<br>Duration (in seconds) of how long Stat Server was in that mode. |
| <b>Description</b>    | Protected configuration monitoring mode is stopped.                         |
| <b>Alarm Advisory</b> | None  |
| <b>Actions</b>        | No action is required.  |