T-Server for CSTA Connector Deployment Guide

Debug Log Options

5/9/2025

Debug Log Options

The options in this section enable you to generate Debug logs containing information about specific operations of an application.

x-conn-debug-all

x-conn-debug-all

Default Value: 0 (zero)
Valid Values:

0	Log records are not generated.
1	Log records are generated.

Changes Take Effect: After restart

Generates Debug log records about open connection, socket select, timer creation and deletion, write, security-related, and DNS operations, and connection library function calls. This option is the same as enabling or disabling all of the previous x-conn-debug-<op type> options.

Warning: Use this option only when requested by Genesys Technical Support.

x-conn-debug-api

x-conn-debug-api

Default Value: 0 (zero)
Valid Values:

0	Log records are not generated.

1	Log records are generated.

Changes Take Effect: After restart

Generates Debug log records about connection library function calls.

Warning:: Use this option only when requested by Genesys Technical Support.

x-conn-debug-dns

x-conn-debug-dns

Default Value: 0 (zero)
Valid Values:

0	Log records are not generated.
1	Log records are generated.

Changes Take Effect: After restart

Generates Debug log records about DNS operations.

Warning: Use this option only when requested by Genesys Technical Support.

x-conn-debug-open

x-conn-debug-open

Default Value: 0 (zero)
Valid Values:

0	Log records are not generated.

1	Log records are generated.

Changes Take Effect: After restart
Generates Debug log records about *open connection* operations of the application.

Warning: Use this option only when requested by Genesys Technical Support.

x-conn-debug-security

x-conn-debug-security

Default Value: 0 (zero)
Valid Values:

0	Log records are not generated.
1	Log records are generated.

Changes Take Effect: After restart

Generates Debug log records about security-related operations, such as Transport Layer Security and security certificates.

Warning: Use this option only when requested by Genesys Technical Support.

x-conn-debug-select

x-conn-debug-select

Default Value: 0 (zero)
Valid Values:

0	Log records are not generated.

1	Log records are generated.

Changes Take Effect: After restart

Generates Debug log records about *socket select* operations of the application.

Warning: Use this option only when requested by Genesys Technical Support.

x-conn-debug-timers

x-conn-debug-timers

Default Value: 0 (zero)
Valid Values:

0	Log records are not generated.
1	Log records are generated.

Changes Take Effect: After restart

Generates Debug log records about the timer creation and deletion operations of the application.

Warning: Use this option only when requested by Genesys Technical Support.

x-conn-debug-write

x-conn-debug-write

Default Value: 0 (zero)
Valid Values:

0	Log records are not generated.

1	Log records are generated.

Changes Take Effect: After restart

Generates Debug log records about the *write* operations of the application.

Warning: Use this option only when requested by Genesys Technical Support.