

GENESYS

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Administrator Extension Help

Parameter Properties

Parameter Properties

Properties of Operational Parameters

Property	Description
Display Name	The name of the parameter. It must be unique in the system.
Key Name	The name of the parameter as it would be entered in the Annex/Options tab of the Transaction object in Genesys Administrator. If this field is left blank, the name that is displayed under Display Name is used.
Туре	The parameter.
Object Type	This field appears only for parameters of Type Configuration Object, and specifies the type of configuration object. Optionally, when Configuration Object is selected, you can check the checkbox named Multiple Types to select multiple configuration objects to add to this parameter. If the checkbox named Global is checked, a separate panel will open to allow you to select which tenants will receive the parameter.
DN Type	This field appears only for parameters of Type Configuration Object and Object Type DN, and specifies the type of DN.
Custom List Custom Value	 These properties apply only to parameters of type Custom List and specify the members of the Custom List. Define the list, as follows: To add an item to the list, enter it in the Custom Value edit box, and click Add. To modify an item in the list, select the value, make the change, and click OK. Note: If you want the display value of an item in the Custom List to be different from the actual value stored in the transaction object, enter that information in the Key field. To remove an item from the list, select it, and click Delete. To reorder the items in the list, select an item in the list and use the Up and Down arrow buttons to move it up or down in the list. For integers, dates, and times, you can define minimum and/or maximum values (limits).
Mandatory	Specifies whether the parameter is mandatory or optional. If checked, a value must be entered for this parameter before it is saved. If not checked,

Property	Description
	the parameter is considered optional and can be saved without a value. This property can be modified later (for example, to change a mandatory parameter to an optional parameter).
Global	If checked, this parameter is unique in the entire system and is shared across all tenants. Its actual value must be defined at the time of creation, and can be changed only by the Service Provider.
Value	If this parameter is Global, this is the actual value of the parameter and cannot be changed. A default value can be set that is not propagated to deployed Parameter Group instances. Providing of a default value is optional.
Help Text	Optional text describing the parameter or providing additional information.