



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# iWD Deployment Guide

Creating the (Tenant and) Solution in iWD GAX Plugin

5/9/2025

# Creating the (Tenant and) Solution in iWD GAX Plugin

## Important

After the IPs are installed, you must create an iWD solution in iWD GAX Plugin to proceed with the configuration of iWD. It is most unlikely that you will need to create a new Tenant, but instructions for this are included anyway.

## Important

It is recommended that you do not create any Solutions and Services under the System Tenant. You should do so under a managed Tenant.

## Procedure

1. Login to iWD GAX Plugin.
2. Navigate to **Environment > Tenants**.
3. Click **New** to open a configuration page. This has five tabs: **General**, **Options**, **Permissions**, **Dependencies** and **iWD Attributes**.
4. Enter the following information. For some fields, you can either enter the name of a value or click **Browse** to select a value from a list: **General tab**
  - **Name**—The name of the Tenant. You must specify a value for this property, and that value must be unique within the Configuration Database.
  - **Password**—A password that must be used to access this Tenant.
  - **Confirm Password**—A confirmation of the password.
  - **Parent Tenant**—The parent Tenant of this Tenant. By default, the parent Tenant is the Tenant in which you are creating the new Tenant. If you change this field, the new Tenant will be created as a new child Tenant under the specified parent Tenant. To subsequently change the parent Tenant, refer to the Structure tab, above.
  - **Chargeable Number**—The account number to which activities for this Tenant are charged, for cost-tracking purposes.
  - **Default Contract**—The default cost contract applied to resources of this Tenant. For more information, refer to the Routing Solutions chapter of the [Universal Routing 8.0 Routing Application Configuration Guide](#).
  - **State Enabled**—If selected, indicates that the object is in regular operating condition and can be

used without any restrictions.

- Ignore the **Options tab**.

### Permissions

5. Configure user permissions for this Tenant.

### Dependencies

6. Configure any Dependencies for this Tenant.

### iWD Attributes

7. Configure the iWD Attributes for this Tenant.

- **ID**—The Tenant's runtime ID, generated automatically.
- Description of the tenant.
- **Social Messaging Enabled**—Check to enable social engagement integration for this Tenant.
- **Rule Authoring Tool URL**—The URL of the Genesys Rules Authoring Tool for this iWD Tenant.
- Click **Inventory Report** to print to screen a complete view of the Tenant hierarchy, including Solutions, Departments and Processes.
- Add any Custom Tenant attributes by clicking **Add** and filling in the Name Type and Value table.

### Important

If you are not logged in as the default User, or are not a member of the **SuperAdministrators** Access Group, you must have special permissions and role privileges to create a Tenant. Refer to the **Genesys 8.1 Security Deployment Guide** for details about the security requirements for creating a Tenant.

## Next Steps

Configure your IWD Soluton by installing and running the iWD Setup Utility. Create as many iWD solutions as are required for your business needs. Each iWD solution requires its own dedicated Stat Server. For each iWD solution that you you create, run the iWD Setup Utility and install the Stat Server Java Extension.

### Important

Each iWD solution requires its own iWD Data Mart.