



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

## Genesys Engage Digital (eServices)

channel-any\_name\_for\_mms\_mm7 Section

12/15/2025

## channel-any\_name\_for\_mms\_mm7 Section

- driver-classname
- inbound-route
- reconnection-timeout
- x-debug-mode
- x-jsms-config-file

### driver-classname

**Default Value:** com.genesyslab.mcr.smsserver.channel.sms\_mms.jsms\_mm7.MM7Driver

**Valid Values:** com.genesyslab.mcr.smsserver.channel.sms\_mms.jsms\_mm7.MM7Driver

**Changes Take Effect:** After restart

Specifies the class name of the driver used to connect to a media service provider.

### inbound-route

**Default Value:** tenant\_dbid:endpoint\_name\_for\_MMS

**Valid Values:** Any string

**Changes Take Effect:** After restart

This option defines the endpoints for inbound messages arriving from the media channel. The option value includes a tenant ID, to refer to corresponding endpoints section, and the name of an option inside that section; for example, 101:mms\_queue refers to the mms\_queue option in the endpoints:101 section.

### reconnection-timeout

**Default Value:** 180

**Valid Values:** Any integer greater than or equal to 10.

**Changes Take Effect:** After restart

Specifies the delay, in seconds, before the server starts the reconnection procedure for this media channel if the connection was lost.

## x-debug-mode

**Default Value:** false

**Valid Values:** true, false

**Changes Take Effect:** Immediately

If set to true, an extended form of logging is set for the server. If set to false, a reduced form of logging is set for the server.

## x-jsms-config-file

**Default Value:** jsms-mm7.conf

**Valid Values:** The full name of the jSMS configuration file

**Changes Take Effect:** After restart

Specifies the name and location of the configuration file for the jSMS implementation. If a full path is not specified, SMS Server searches its current (working) folder for the file. This option applies to jSMS drivers. The parameters of the jSMS configuration file are described in the file located at `SMSServerInstallationFolder\media-channel-drivers\channel-sms-mms\jsms\bin\jsms.conf` and in the jSMS User's Guide located at `SMSServerInstallationFolder\media-channel-drivers\channel-sms-mms\jsms\docs\users_guide.pdf` (SMSServerInstallationFolder is a sample name).

The jSMS configuration file **jsms.conf** specifies the jSMS license that is needed to activate MMS/MM7 service. Genesys provides jSMS MMS/MM7 licenses to customers on requests. The following is an example only:

```
license.company=Genesys Telecommunications Laboratories, Inc
license.serial-nr=45383732
license.version=2.9
license.type=RUNTIME LICENSE
license.sig=JsshFtt5ffafst/4jsdydgGdvIUtfd^%FHytrfvhKMeVg==
license.modules=mm7
```