



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# Genesys Voice Platform

UCM Connector

5/7/2025

# UCM Connector

Options for this component are contained in the following configuration sections:

- **ems**
- **log**
- **sip**
- **TServer**
- **UCMC**

## Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

**Power users:** **Download a CSV file** containing default and valid values and descriptions.

The following options are configured at the application level (in other words, on the application object).

Section	Option	Default	Changes Take Effect
ems	<a href="#">logconfig.MFSINK</a>	•	immediately
ems	<a href="#">logconfig.TRAPSINK</a>	•	At start/restart
ems	<a href="#">trace_flag</a>	FALSE	immediately
log	<a href="#">all</a>	../logs/UCMConnector	immediately
log	<a href="#">check-point</a>	1	immediately
log	<a href="#">compatible-output-priority</a>	false	immediately
log	<a href="#">debug</a>	../logs/UCMConnector	immediately
log	<a href="#">expire</a>	20	immediately
log	<a href="#">interaction</a>	../logs/UCMConnector	immediately
log	<a href="#">keep-startup-file</a>	false	After restart
log	<a href="#">memory</a>		immediately
log	<a href="#">messagefile</a>		Immediately, if an
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
			application cannot find its *.lms file at startup
log	message_format	short	immediately
log	print-attributes	false	immediately
log	segment	10000	immediately
log	spool		immediately
log	standard	../logs/UCMConnector	immediately
log	time_convert	local	immediately
log	time_format	time	immediately
log	trace	../logs/UCMConnector	immediately
log	verbose	standard	immediately
sip	localuser	UCMConnector	At start/restart
sip	mtusize	1500	After restart
sip	tcp.portrange		At start/restart
sip	tls.portrange		At start/restart
sip	transport.0	transport0 udp:any:5080	At start/restart
sip	transport.1	transport1 tcp:any:5080	At start/restart
sip	transport.2	transport2 tls:any:5081 cert=\$InstallationRoot\$/config/ x509_certificate.pem key=\$InstallationRoot\$/config/ x509_private_key.pem	At start/restart
sip	transport.localaddress		At start/restart
sip	transport.localaddress.srv	false	At start/restart
sip	transport.localaddress_ipv6		At start/restart
sip	transport.routefailovertime	5	At start/restart
sip	transport.routeretrytime	30	At start/restart
sip	transport.staticroutelist		At start/restart
TServer	smloc	SM	After restart
TServer	TServerAddress		After restart
TServer	TSvrConnectionRetryCount	10	After restart
TServer	UCMCClientPortRange		After restart
UCMC	fips_enabled	False	After restart
UCMC	NotifyGMSDTMF	false	After restart
UCMC	RMAAddress		After restart
UCMC	UseSecureSIP	false	After restart
Section	Option	Default	Changes Take Effect